



# **Advanced Network Security**

Amir Mahdi Sadeghzadeh, Ph.D.

## Outline

- What is network security?
- Principles of cryptography
- Message integrity, authentication
- Securing e-mail
- Securing TCP connections: TLS
- Network layer security: IPsec



# What is Security?

- Confidentiality
- Integrity
- Availability

## **More Definitions**


• Vulnerability (آسيبپذيرى): An error or weakness in the design, implementation, or operation of a system

- Attack (حمله): A means of exploiting some vulnerability in a system

• Threat (تهدید): An adversary that is motivated and capable of exploiting a vulnerability

# Friends and enemies: Alice, Bob, Trudy

- Well-known in network security world
- Bob, Alice (Azam, Babak) want to communicate "securely"
- Trudy (intruder) may intercept, delete, add messages



## **Network Vulnerabilities**


- Each layer has it's own vulnerabilities
  - Link layer example: ARP-spoofing
  - Network layer example: IP address forgery
  - TCP example: Sequence number guessing attack
  - Application example: email-borne worms

## Outline

- What is network security?
- Principles of cryptography
- Message integrity, authentication
- Securing e-mail
- Securing TCP connections: TLS
- Network layer security: IPsec



# The language of cryptography



# Kerckhoffs's principle

- Auguste Kerckhoffs was a professor in Paris. In early 1883, Kerckhoffs' article, La Cryptographie Militaire states six design rules for military ciphers.
  - 1. The system must be practically, if not mathematically, indecipherable;
  - 2. It should not require secrecy, and it should not be a problem if it falls into enemy hands;
  - 3. It must be possible to communicate and remember the key without using written notes, and correspondents must be able to change or modify it at will;
  - 4. It must be applicable to telegraph communications;
  - 5. It must be portable, and should not require several persons to handle or operate;
  - 6. Lastly, given the circumstances in which it is to be used, the system must be easy to use and should not be stressful to use or require its users to know and comply with a long list of rules.

## Breaking an encryption scheme


cipher-text only attack: Trudy has ciphertext she can analyze

known-plaintext attack:
 Trudy has plaintext
 corresponding to
 ciphertext

chosen-plaintext attack:
 Trudy can get ciphertext for chosen plaintext

- two approaches:
  - brute force: search through all keys
  - statistical analysis

# Symmetric key cryptography



symmetric key crypto: Bob and Alice share same (symmetric) key: K

- e.g., key is knowing substitution pattern in mono alphabetic substitution cipher
- Q: how do Bob and Alice agree on key value?

## Simple encryption scheme

substitution cipher: substituting one thing for another

monoalphabetic cipher: substitute one letter for another

```
plaintext: abcdefghijklmnopqrstuvwxyz
ciphertext: mnbvcxzasdfghjklpoiuytrewq

e.g.: Plaintext: bob. i hear you. alice
ciphertext: nkn. s acmo wky. mgsbc
```

Encryption key: mapping from set of 26 letters to set of 26 letters

## A more sophisticated encryption approach

- n substitution ciphers, M<sub>1</sub>,M<sub>2</sub>,...,M<sub>n</sub>
- cycling pattern:
  - e.g., n=4:  $M_1$ ,  $M_3$ ,  $M_4$ ,  $M_3$ ,  $M_2$ ;  $M_1$ ,  $M_3$ ,  $M_4$ ,  $M_3$ ,  $M_2$ ; ...
- for each new plaintext symbol, use subsequent substitution pattern in cyclic pattern
  - dog: d from M<sub>1</sub>, o from M<sub>3</sub>, g from M<sub>4</sub>
- Encryption key: n substitution ciphers, and cyclic pattern
  - key need not be just n-bit pattern

## Confusion and Diffusion

- In cryptography, confusion and diffusion are two properties of the operation of a secure cipher
  - identified by Claude Shannon in his 1945 classified report A Mathematical Theory of Cryptography.

## Confusion

- Confusion refers to making the relationship between the key and the ciphertext as complex and involved as possible.
  - The property of confusion hides the relationship between the ciphertext and the key.
- How It's Achieved:
  - Non-linearity: Using non-linear mathematical functions to introduce complexity.
  - Substitution: Substituting bits or blocks of data based on the key.
- Example: S-boxes in the Advanced Encryption Standard (AES) provide confusion.


## Diffusion

- Diffusion refers to the property that the redundancy in the statistics of the plaintext is dissipated in the statistics of the ciphertext.
  - In other words, the <u>non-uniformity in the distribution of the individual letters</u> (and pairs of neighbouring letters) in the plaintext <u>should be redistributed</u> into the <u>non-uniformity in the distribution of much larger structures</u> of the ciphertext, which is much harder to detect.
  - In a cipher with good diffusion, if one bit of the plaintext is changed, then the ciphertext should change completely, in an unpredictable or pseudorandom manner.

## Diffusion

- How It's Achieved:
  - Permutation: Rearranging bits or blocks of data.
  - Mixing: Applying mathematical operations that mix data.
  - Generally speaking, Linear operation.
- Example: Permutation layers in block ciphers contribute to diffusion.

# **Encryption Scheme**




## Symmetric key crypto: DES

#### **DES: Data Encryption Standard**

- US encryption standard [NIST 1993]
- 56-bit symmetric key, 64-bit plaintext input
- DES has 16 rounds
- how secure is DES?
  - DES Challenge: 56-bit-key-encrypted phrase decrypted (brute force) in less than a day
  - no known good analytic attack
- making DES more secure:
  - 3DES: encrypt 3 times with 3 different keys

# Feistel Cipher (DES)

- Feistel Cipher Operations
  - F Function: the right half of the block (R) undergoes a non-linear transformation (F function) using a round-specific subkey.
  - XOR Operation: The output of the F function is XORed with the left half of the block (L).
  - Swap: The left and right halves are swapped, becoming the new L and R for the next round.




Wikipedia AdvNetSec: 1- 20

## Feistel Function F

#### The Feistel (F) function [edit]

The F-function, depicted in Figure 2, operates on half a block (32 bits) at a time and consists of four stages:

- 1. Expansion: the 32-bit half-block is expanded to 48 bits using the expansion permutation, denoted E in the diagram, by duplicating half of the bits. The output consists of eight 6-bit (8 × 6 = 48 bits) pieces, each containing a copy of 4 corresponding input bits, plus a copy of the immediately adjacent bit from each of the input pieces to either side.
- Key mixing: the result is combined with a subkey using an XOR operation. Sixteen 48-bit subkeys one for each round—are derived from the main key using the key schedule (described below).
- 3. Substitution: after mixing in the subkey, the block is divided into eight 6-bit pieces before processing by the S-boxes, or substitution boxes. Each of the eight S-boxes replaces its six input bits with four output bits according to a non-linear transformation, provided in the form of a lookup table. The S-boxes provide the core of the security of DES—without them, the cipher would be linear, and trivially breakable.
- 4. Permutation: finally, the 32 outputs from the S-boxes are rearranged according to a fixed permutation, the P-box. This is designed so that, after permutation, the bits from the output of each S-box in this round are spread across four different S-boxes in the next round.



Wikipedia AdvNetSec: 1- 21


## **AES: Advanced Encryption Standard**

- symmetric-key NIST standard, replaced DES (Nov 2001)
- processes data in 128 bit blocks
- 128, 192, or 256 bit keys
  - 10 rounds for 128-bit keys.
  - 12 rounds for 192-bit keys.
  - 14 rounds for 256-bit keys.
- brute force decryption taking 1 sec on DES, takes 149 trillion years for AES

# Substitution-Permutation Network (AES)


#### SPN Cipher Operations

- Substitution (S-Box): each block undergoes a nonlinear substitution operation, often involving lookup tables (S-boxes).
- Permutation (P-Box): The permutation layer rearranges the bits within each block, introducing confusion and diffusion.
- Key Mixing: The key is combined with the block at various points in the structure.




# **Block Cipher modes of Operation**

• Electronic Code Book (ECB)



Cipher Block Chaining (CBC)



# Public Key Cryptography

### symmetric key crypto:


- requires sender, receiver know shared secret key
- Q: how to agree on key in first place (particularly if never "met")?
- Message integrity, authentication?

## public key crypto

- radically different approach
   [Diffie-Hellman76, RSA78]
- sender, receiver do not share secret key
- public encryption key known to all
- private decryption key known only to receiver



# Public Key Cryptography



Public key cryptography revolutionized 2000-year-old (previously only symmetric key) cryptography!

• similar ideas emerged at roughly same time, independently in US and UK (classified)

## Public key encryption algorithms

#### requirements:

- 1 need  $K_B^+(\cdot)$  and  $K_B^-(\cdot)$  such that  $K_B^-(K_B^+(m)) = m$
- given public key  $K_B^+$ , it should be impossible to compute private key  $K_B^-$

RSA: Rivest, Shamir, Adelson algorithm

## One-Way Functions for Public-Key Cryptography

#### One-way Function

- One-way functions are easy to compute but it is very difficult to compute their inverse functions.
  - Thus, having data x it is easy to calculate f(x) but, on the other hand, knowing the value of f(x) it is quite difficult to calculate the value of x.
- Modular exponentiation is a common example of a one-way function in RSA cryptography.
  - Computing  $c = m^e \mod n$  is easy, but finding m given c, e, and n is computationally difficult.

## One-Way Functions for Public-Key Cryptography

- Trapdoor one-way function
  - Trapdoor one-way functions are types of one-way functions that contain a kind of "back door" (trapdoor).
    - As in the case of ordinary one-way functions it is easy to compute their values for given data but it is very difficult to compute their inverse functions.
      - However, if one has some additional secret information, he can easily compute the inverse function as well.
      - Example: in RSA, d is the trapdoor.

# Euler's phi function

- Euler's phi function  $\phi(n)$  counts the positive integers up to a given integer n that are relatively prime to n.
  - In other words, it is the number of integers k in the range  $1 \le k \le n$  for which the greatest common divisor gcd(n, k) is equal to 1.

$$arphi(n) = p_1^{k_1-1}(p_1\!-\!1)\,p_2^{k_2-1}(p_2\!-\!1)\cdots p_r^{k_r-1}(p_r\!-\!1),$$

where  $n=p_1^{k_1}p_2^{k_2}\cdots p_r^{k_r}$  is the prime factorization of n (that is,  $p_1,p_2,\ldots,p_r$  are distinct prime numbers).

pedia AdvNetSec: 1- 30

## Euler's theorem

- Fermat's little theorem
  - For any prime number p, and for any number n, 0 < n < p,  $n^{p-1} \equiv 1 \mod p$ .

- Euler's theorem generalizes Fermat's theorem to the case where the modulus is not prime.
  - if p is a positive integer and n, p are coprime (n <p), then  $n^{\phi(p)} \equiv 1 \mod p$  where  $\phi(p)$  is the Euler's phi function .
  - $5^{\phi(12)} mod \ 12 = 5^4 \ mod \ 12 = 625 \ mod \ 12 = 1$

## Prerequisite: modular arithmetic

- x mod n = remainder of x when divide by n
- facts:

```
[(a mod n) + (b mod n)] mod n = (a+b) mod n

[(a mod n) - (b mod n)] mod n = (a-b) mod n

[(a mod n) * (b mod n)] mod n = (a*b) mod n
```

thus

```
(a \mod n)^d \mod n = a^d \mod n
```

example: x=14, n=10, d=2:  $(x \mod n)^d \mod n = 4^2 \mod 10 = 6$  $x^d = 14^2 = 196 \quad x^d \mod 10 = 6$ 

# RSA: getting ready

- message: just a bit pattern
- bit pattern can be uniquely represented by an integer number
- thus, encrypting a message is equivalent to encrypting a number

#### example:

- m= 10010001. This message is uniquely represented by the decimal number 145.
- to encrypt m, we encrypt the corresponding number, which gives a new number (the ciphertext).

## RSA: Creating public/private key pair

- 1. choose two large prime numbers p, q. (e.g., 1024 bits each)
- 2. compute n = pq,  $\phi(n) = z = (p-1)(q-1)$
- 3. choose e (with e < z) that has no common factors with z (e, z are "relatively prime"). The number e is usually 65537 (0x010001).
- 4. choose d such that ed-1 is exactly divisible by z. (in other words: ed mod z=1).
- 5. public key is (n,e). private key is (n,d).  $K_B^+$   $K_B^-$

## RSA: encryption, decryption

- 0. given (n,e) and (n,d) as computed above
- 1. to encrypt message m (<n), compute  $c = m^e \mod n$
- 2. to decrypt received bit pattern, c, compute  $m = c^d \mod n$

$$m = (m^e \mod n)^d \mod n$$

## Why does RSA work?

- must show that c<sup>d</sup> mod n = m, where c = m<sup>e</sup> mod n
- thus,  $c^d \mod n = (m^e \mod n)^d \mod n$  $= m^{ed} \mod n$  $= m^{az+1} \mod n$  $= m^{az} \cdot m^1 \mod n$  $= (m^{az} \mod n. m \mod n) \mod n$  $= ((m^z)^a \mod n. m) \mod n$ =  $((m^z \text{ mod n})^a \text{ mod n. m}) \text{ mod n}$  #Euler's theorem  $= (1^a \mod n. m) \mod n = 1.m \mod n = m$

## RSA example:

```
Bob chooses p=5, q=7. Then n=35, z=24.

e=5 (so e, z relatively prime).

d=29 (so ed-1 exactly divisible by z).

encrypting 8-bit messages.
```

encrypt: 
$$\frac{\text{bit pattern } m}{00001100}$$
  $\frac{m}{12}$   $\frac{\text{c} = m^e \text{mod n}}{248832}$   $\frac{\text{c} = m^e \text{mod n}}{17}$  decrypt:  $\frac{\text{c}}{17}$   $\frac{\text{c}}{481968572106750915091411825223071697}$   $\frac{\text{c} = m^e \text{mod n}}{12}$ 

## RSA: another important property

The following property will be *very* useful later:

$$K_B(K_B^+(m)) = m = K_B^+(K_B^-(m))$$

use public key use private key first, followed by private key by public key

result is the same!

Why 
$$K_B(K_B(m)) = m = K_B(K_B(m))$$
?

follows directly from modular arithmetic:

```
(m^e \mod n)^d \mod n = m^{ed} \mod n
= m^{de} \mod n
= (m^d \mod n)^e \mod n
```

# Why is RSA secure?

- suppose you know Bob's public key (n,e). How hard is it to determine d?
- essentially need to find factors of n without knowing the two factors p and q
  - fact: factoring a big number is hard

## Prime-counting function

- The prime-counting function  $\pi(x)$  is the function counting the number of prime numbers less than or equal to some real number x.
  - It was conjectured in the end of the 18th century by Gauss and by Legendre to be approximately

$$\pi(x) \approx \frac{x}{\ln x}$$

# $\frac{2^{1024}}{\log(2^{1024})}$ Decimal approximation $2.5327372760800758374501125144018857033665685288449674343788... <math display="block">10^{305}$

Input
2<sup>128</sup>

Result
340 282 366 920 938 463 463 374 607 431 768 211 456

Scientific notation
3.40282366920938463463374607431768211456 × 10<sup>38</sup>

## RSA in practice: session keys

- exponentiation in RSA is computationally intensive
- DES is at least 100 times faster than RSA
- use public key crypto to establish secure connection, then establish second key – symmetric session key – for encrypting data

## session key, K<sub>S</sub>

- Bob and Alice use RSA to exchange a symmetric session key K<sub>S</sub>
- once both have K<sub>s</sub>, they use symmetric key cryptography

## References

- Kurose, James F., and Keith W. Ross. "Computer networking: A top-down approach edition." Addision Wesley (2007), chapter 8.
- Paar, Christof, and Jan Pelzl. Understanding cryptography: a textbook for students and practitioners. Springer Science & Business Media, 2009.
- ChatGPT, OpenAI.