


Layer 3 port-channel LAB

Twist 1941 router With L3 Switch Port



Note:

ISRs do not support negotiation protocols like LACP or PAgP.

configure both sides to use a Static EtherChannel (known as mode on).

1941 router, the configuration doesn't even have a mode keyword—assigning the port to a channel group makes it static by default.

Cisco 1941 Router Configuration

On the router side, you must create the logical port-channel first, assign the IP address to it, and then bundle the physical ports.

Router> enable

Router# configure terminal

Create the Port-Channel directly

Router(config)# interface Port-channel 10

Router(config-if)# ip address 10.1.1.1 255.255.255.252

Router(config-if)# no shutdown

Router(config-if)# exit

Assign the built-in ports to the channel

Router(config)# interface range GigabitEthernet 0/0 - 1

Notice there is no 'mode' keyword here for routers

Router(config-if-range)# channel-group 10

Router(config-if-range)# no shutdown

Router(config-if-range)# exit

Layer 3 Switch Configuration

On the switch side, you must convert the physical ports to Layer 3 and force them into a static bundle using mode on so they match the router's behavior.

Switch> enable

Switch# configure terminal

Switch(config)# ip routing

Configure the physical ports for static channeling

```
Switch(config)# interface range GigabitEthernet 1/0/1 - 2
```

```
Switch(config-if-range)# no switchport
```

You must use 'mode on' here instead of 'mode active'

```
Switch(config-if-range)# channel-group 10 mode on
```

```
Switch(config-if-range)# no shutdown
```

```
Switch(config-if-range)# exit
```

Configure the logical Port-Channel

```
Switch(config)# interface Port-channel 10
```

```
Switch(config-if)# no switchport
```

```
Switch(config-if)# ip address 10.1.1.2 255.255.255.252
```

```
Switch(config-if)# no shutdown
```

```
Switch(config-if)# exit
```