MySQL 8.3 Reference Manual / Functions and Operators / Window Functions / Window Function Frame Specification

14.20.3 Window Function Frame Specification

The definition of a window used with a window function can include a frame clause. A frame is a subset of the current partition and the frame clause specifies how to define the subset.

Frames are determined with respect to the current row, which enables a frame to move within a partition depending on the location of the current row within its partition. Examples:

- By defining a frame to be all rows from the partition start to the current row, you can compute running totals for each row.
- By defining a frame as extending \mathbf{N} rows on either side of the current row, you can compute rolling averages.

The following query demonstrates the use of moving frames to compute running totals within each group of time-ordered level values, as well as rolling averages computed from the current row and the rows that immediately precede and follow it:

```
mysql> SELECT
       time, subject, val,
       SUM(val) OVER (PARTITION BY subject ORDER BY time
                     ROWS UNBOUNDED PRECEDING)
         AS running_total,
       AVG(val) OVER (PARTITION BY subject ORDER BY time
                     ROWS BETWEEN 1 PRECEDING AND 1 FOLLOWING)
         AS running_average
      FROM observations;
+----+
         | subject | val | running_total | running_average |
| 07:00:00 | st113
                  | 10 |
                                   10 |
                                                9.5000 |
| 07:15:00 | st113 |
                     9 |
                                   19 |
                                               14.6667 |
| 07:30:00 | st113 | 25 |
                                   44 |
                                               18.0000 |
                                   64 |
| 07:45:00 | st113 | 20 |
                                               22.5000 |
| 07:00:00 | xh458
                  | 0 |
                                   0 |
                                               5.0000 |
| 07:15:00 | xh458
                | 10 |
                                   10 |
                                               5.0000 |
| 07:30:00 | xh458
                  | 5 |
                                   15 |
                                               15.0000 |
| 07:45:00 | xh458
                     30 |
                                   45 |
                                               20.0000 |
| 08:00:00 | xh458
                                   70 I
                                               27.5000 l
                     25
```

For the running_average column, there is no frame row preceding the first one or following the last. In these cases, AVG() computes the average of the rows that are available.

Aggregate functions used as window functions operate on rows in the current row frame, as do these nonaggregate window functions:

```
FIRST_VALUE()
LAST_VALUE()
NTH_VALUE()
```

Standard SQL specifies that window functions that operate on the entire partition should have no frame clause. MySQL permits a frame clause for such functions but ignores it. These functions use the entire partition even if a frame is specified:

```
CUME_DIST()

DENSE_RANK()

LAG()

LEAD()

NTILE()

PERCENT_RANK()

RANK()

ROW_NUMBER()
```

The frame clause, if given, has this syntax:

```
frame_clause:
    frame_units frame_extent

frame_units:
    {ROWS | RANGE}
```

In the absence of a frame clause, the default frame depends on whether an ORDER BY clause is present, as described later in this section.

The *frame units* value indicates the type of relationship between the current row and frame rows:

- ROWS: The frame is defined by beginning and ending row positions. Offsets are differences in row numbers from the current row number.
- RANGE: The frame is defined by rows within a value range. Offsets are differences in row values from the current row value.

The *frame_extent* value indicates the start and end points of the frame. You can specify just the start of the frame (in which case the current row is implicitly the end) or use BETWEEN to specify both frame endpoints:

```
frame_extent:
    {frame_start | frame_between}

frame_between:
    BETWEEN frame_start AND frame_end

frame_start, frame_end: {
    CURRENT ROW
    | UNBOUNDED PRECEDING
    | UNBOUNDED FOLLOWING
    | expr PRECEDING
    | expr FOLLOWING
}
```

With BETWEEN syntax, frame start must not occur later than frame end.

The permitted *frame start* and *frame end* values have these meanings:

- CURRENT ROW: For ROWS, the bound is the current row. For RANGE, the bound is the peers of the current row.
- UNBOUNDED PRECEDING: The bound is the first partition row.
- UNBOUNDED FOLLOWING: The bound is the last partition row.
- expr PRECEDING: For ROWS, the bound is expr rows before the current row. For RANGE, the bound is the rows with values equal to the current row value minus expr; if the current row value is NULL, the bound is the peers of the row.

For <code>expr</code> <code>PRECEDING</code> (and <code>expr</code> <code>FOLLOWING</code>), <code>expr</code> can be a ? parameter marker (for use in a prepared statement), a nonnegative numeric literal, or a temporal interval of the form <code>INTERVAL val unit</code>. For <code>INTERVAL</code> expressions, <code>val</code> specifies nonnegative interval value, and <code>unit</code> is a keyword indicating the units in which the value should be interpreted. (For details about the permitted <code>units</code> specifiers, see the description of the <code>DATE_ADD()</code> function in Section 14.7, "Date and Time Functions".)

RANGE on a numeric or temporal *expr* requires ORDER BY on a numeric or temporal expression, respectively.

Examples of valid <code>expr</code> PRECEDING and <code>expr</code> FOLLOWING indicators:

```
10 PRECEDING
INTERVAL 5 DAY PRECEDING
5 FOLLOWING
INTERVAL '2:30' MINUTE_SECOND FOLLOWING
```

• **expr** FOLLOWING: For ROWS, the bound is **expr** rows after the current row. For RANGE, the bound is the rows with values equal to the current row value plus **expr**; if the current row value is NULL, the bound is the peers of the row.

For permitted values of *expr*, see the description of *expr* PRECEDING.

The following query demonstrates FIRST_VALUE(), LAST_VALUE(), and two instances of
NTH_VALUE():

```
mysql> SELECT
       time, subject, val,
       FIRST_VALUE(val) OVER w AS 'first',
       LAST_VALUE(val) OVER w AS 'last',
       NTH_VALUE(val, 2) OVER w AS 'second',
       NTH_VALUE(val, 4) OVER w AS 'fourth'
     FROM observations
     WINDOW w AS (PARTITION BY subject ORDER BY time
               ROWS UNBOUNDED PRECEDING);
+----+
        | subject | val | first | last | second | fourth |
+----+
| 07:00:00 | st113
                | 10 |
                          10 |
                                10 |
                                     NULL |
                                             NULL |
                          10 | 9 |
                                        9 |
| 07:15:00 | st113
                | 9 |
                                             NULL |
                          10 | 25 |
| 07:30:00 | st113 | 25 |
                                        9 |
                                             NULL |
| 07:45:00 | st113 | 20 |
                         10 | 20 |
                                        9 |
                                              20
| 07:00:00 | xh458
                | 0 |
                          0 | 0 |
                                     NULL |
                                             NULL |
| 07:15:00 | xh458 | 10 |
                          0 | 10 |
                                       10 |
                                            NULL |
| 07:30:00 | xh458
                           0 | 5 |
                   5 |
                                       10 |
                                             NULL |
| 07:45:00 | xh458
                   30 |
                           0 |
                                30 |
                                       10 |
                                              30 |
| 08:00:00 | xh458
               25 |
                           0 |
                                25 |
                                       10 |
                                              30 I
```

Each function uses the rows in the current frame, which, per the window definition shown, extends from the first partition row to the current row. For the $NTH_VALUE()$ calls, the current frame does not always include the requested row; in such cases, the return value is NULL.

In the absence of a frame clause, the default frame depends on whether an <code>ORDER BY</code> clause is present:

• With ORDER BY: The default frame includes rows from the partition start through the current row, including all peers of the current row (rows equal to the current row according to the ORDER BY clause). The default is equivalent to this frame specification:

RANGE BETWEEN UNBOUNDED PRECEDING AND CURRENT ROW

• Without ORDER BY: The default frame includes all partition rows (because, without ORDER BY, all partition rows are peers). The default is equivalent to this frame specification:

RANGE BETWEEN UNBOUNDED PRECEDING AND UNBOUNDED FOLLOWING

Because the default frame differs depending on presence or absence of ORDER BY, adding ORDER BY to a query to get deterministic results may change the results. (For example, the values produced by SUM() might change.) To obtain the same results but ordered per ORDER BY, provide an explicit frame specification to be used regardless of whether ORDER BY is present.

The meaning of a frame specification can be nonobvious when the current row value is NULL. Assuming that to be the case, these examples illustrate how various frame specifications apply:

- ORDER BY X ASC RANGE BETWEEN 10 FOLLOWING AND 15 FOLLOWING
 - The frame starts at NULL and stops at NULL, thus includes only rows with value NULL.
- ORDER BY X ASC RANGE BETWEEN 10 FOLLOWING AND UNBOUNDED FOLLOWING
 - The frame starts at NULL and stops at the end of the partition. Because an ASC sort puts NULL values first, the frame is the entire partition.
- ORDER BY X DESC RANGE BETWEEN 10 FOLLOWING AND UNBOUNDED FOLLOWING
 - The frame starts at NULL and stops at the end of the partition. Because a DESC sort puts NULL values last, the frame is only the NULL values.
- ORDER BY X ASC RANGE BETWEEN 10 PRECEDING AND UNBOUNDED FOLLOWING
 - The frame starts at NULL and stops at the end of the partition. Because an ASC sort puts NULL values first, the frame is the entire partition.
- ORDER BY X ASC RANGE BETWEEN 10 PRECEDING AND 10 FOLLOWING
 - The frame starts at NULL and stops at NULL, thus includes only rows with value NULL.
- ORDER BY X ASC RANGE BETWEEN 10 PRECEDING AND 1 PRECEDING
 - The frame starts at NULL and stops at NULL, thus includes only rows with value NULL.
- ORDER BY X ASC RANGE BETWEEN UNBOUNDED PRECEDING AND 10 FOLLOWING
 - The frame starts at the beginning of the partition and stops at rows with value NULL. Because an ASC sort puts NULL values first, the frame is only the NULL values.

© 2024 Oracle