Login with HANA users

In order to login to the Controller with a HANA user, you need to assign a preconfigured "Role Collection" to the HANA user, first. Currently, this has to be done manually using HANA Studio:

Role Collections For HANA Controller Users

Depending on the proviledges to be granted, add the following role collection in HANA Studio (need newer version > 2.0, tab User Parameters):

Parameter	Value	Controller Scopes	Remarks
XS_RC_XS_CONTROLLER_ ADMIN	XS_CONTROLLER_ADMIN	cloud_controller.{admin,write,read}	An admin user which has no access restrictions
XS_RC_XS_CONTROLLER_ USER	XS_CONTROLLER_USER	cloud_controller.{write,read}	A controller user which is able to modify within its assigned org or space (Controller role needs to be added)
XS_RC_XS_CONTROLLER_ AUDITOR	XS_CONTROLLER_AUDITOR	cloud_controller.read	A controller user which is able to read within its assigned org or space (Controller role needs to be added)

Implications:

- Users having XS_CONTROLLER_ADMIN have access rights to all resources of the Controller. No additional controller roles need to be assigned.
- Users only having XS_CONTROLLER_USER or XS_CONTROLLER_AUDITOR are restricted users. Therefore, you have to grant a set of permissions by adding "Controller User Roles", first (see next paragraph).

Assigning role collections to HANA users can also be accomplished in the **Admin UI** (XS Advanced Administration and Monitoring Tools => User Management)

Controller User Roles

Having XS_CONTROLLER_USER or XS_CONTROLLER_AUDITOR role collection still does not grant access to any resource in Controller. You have to assign a set of Controller User Roles, first:

Available Controller User Roles

Role or scope	Permissions		
OrgManager	 manages spaces manages roles (also in spaces) manages domains view org (plus it's spaces) 		
OrgAuditor	• view org (plus it's spaces, no credentials since SPS12)		
SpaceManager	manages space rolesview space		
SpaceDeveloper	manages apps, services, routes etc.view space		
SpaceAuditor	view space (nocredentials since SPS12)		

Possible Controller User Roles

XS_CONTROLLER_USER	OrgManagerOrgAuditorSpaceManagerSpaceDeveloperSpaceAuditor
XS_CONTROLLER_AUDITOR	OrgAuditorSpaceAuditor

Granting Controller User Roles

Granting a user a specific role in the Controller can be accomplished by using the xs command line client:

```
xs set-org-role <user> <org> <OrgManager | OrgAuditor>
```

resp.

```
xs set-space-role <user> <org> <space> <SpaceManager | SpaceDeveloper | SpaceAuditor>
```

Note, that the first role-grant has to be performed by an admin user.

Granting Controller roles can also be accomplished in the **Admin UI** (XS Advanced Administration and Monitoring Tools => Organization and Space Management)

Controller Login

To login as a Controller-enabled HANA user, just use the xs client login command:

```
xs login -u <user>
```

Changing the initial password

In case you login with a newly created HANA user, you'll get the following error message:

```
Authentication failed: SAP DBTech JDBC: [414]: user is forced to change password: alter password required for user RESTRICTED
```

This is because HANA does not allow user access with the initial password. Unfortunately, the xs client does not provide a method to change the password. Therefore, please change the initial password:

- either in HANA Studio
- or navigate to the UAA login page once before logging in to the XS Controller.

```
https://<hostname>:3<xx>32/uaa-security/login
```

where:

- <hostname> is the host the Controller is running
- <xx> is your HANA instance number

Once you login with the username and the initial password, you will be asked to change the PW.