


Actual downup_ac_area values versus the corrected classifications

(a) Stored legacy result: 2017-07


wind: 119.4 deg from East misread as 119.4 deg compass



downwind = 459.7 km2 | upwind = 104.7 km2
downup_ac_area = 1

(c) Stored legacy result: 2017-03


wind: -75.0 deg from East misread as 285.0 deg compass



downwind = 159.7 km2 | upwind = 404.7 km2
downup_ac_area = 0

(b) Corrected convention: 2017-07


wind: 119.4 deg from East -> 330.6 deg compass



downwind = 24.0 km2 | upwind = 540.4 km2
downup_ac_area = 0

(d) Corrected convention: 2017-03

wind: -75.0 deg from East -> 165.0 deg compass



downwind = 557.2 km2 | upwind = 7.2 km2
downup_ac_area = 1

Area stored as downwind
Corrected downwind area

Upwind remainder
AC direction: clockwise from North