Data Science and Advanced Programming — Lecture 12

High Performance Computing

Simon Scheidegger
Department of Economics, University of Lausanne, Switzerland

December 1st, 2025 | 12:30 - 16:00 | Internef 263

Introduction to parallel and high-performance computing

From making fire to flying rockets in 2 weeks

From making fire to flying rockets in 2 weeks



Fortran: first appeared: 1957. For us, we start out here in early May 2023



By end of December, 2025, we are here...
Since 2012: MPI, OpenMP, Fortran, C++, Cuda,...

Scope of today's lecture

The purpose of the next 3 lectures is to give you an introduction to the main approaches to exploit modern parallel and High-Performance Computing (HPC) systems.

- Intended to provide only a very quick overview of the extensive and broad topic of parallel computing.
- Familiarize with the big picture, ideas and concepts.
- Familiarize with the main programming models.

YOU SHOULD START TO THINK PARALLEL

Outline of this introductory lecture

1. Motivation — why should we use parallel programming.
2. Contemporary hardware.
3. Programming Models.

Some Resources

Full standard/API specification:

- http://mpi-forum.org
- http://openmp.org

Tutorials:

- https://computing.llnl.gov/tutorials/mpi/
- https://computing.llnl.gov/tutorials/openMP/
- http://cse-lab.ethz.ch/index.php/teaching/42-teaching/classes/577-hpcsei

Books:

- "Introduction to High Performance Computing for Scientists and Engineers" Georg Hager, Gerhard Wellein
- "Using Advanced MPI: Modern Features of the Message-Passing Interface" (Scientific and Engineering Computation) MIT Press, 2014 Gropp, W.; Höfler, T.; Thakur, R. & Lusk, E.

Study complex phenomena

https://hpc.llnl.gov/documentation/tutorials/introduction-parallel-computing-tutorial

Rush Hour Traffic


Plate Tectonics


Weather

- In the natural world, many complex, interrelated events are happening at the same time, yet within a temporal sequence.
- Interrelated events happen concurrently.
- Compared to serial computing, parallel computing is much better suited for modelling, simulating and understanding complex, real world phenomena.

Past: parallel computing = high-end science*

*with special-purpose hardware



Parallel computing has been used to model difficult problems in many areas of science and engineering:

- Atmosphere, Earth, Environment
- Physics - applied, nuclear, particle, condensed matter, high pressure, fusion, photonics
- Bioscience, Biotechnology, Genetics, Chemistry, Molecular Sciences
- Geology, Seismology Defense, Weapons
- ...

Today: Parallel computing = every day (industry, academia) computing





- Pharmaceutical design
- Data mining
- Financial modelling
- Advanced graphics, virtual reality
- Artificial intelligence/Machine learning
- ...

Why parallel computing?

HPC helps with:

- Huge data
  - → Data management in memory
  - → Data management on disk
- Complex problems
  - → Time consuming algorithms
  - → Data mining
  - → Visualization
- Requires special purpose solutions in terms of:
  - → Processors
  - → Networks
  - → Storage
  - → Software
  - → Applications

Why parallel computing* (II)

*List from P. Koumoutsakos

Transmission speeds Speed of a serial computer is directly dependent on how fast data can be moved through hardware. Absolute limits are the speed of light ($30\ \mathrm{cm/ns}$) and the transition limit of copper wire ($9\ \mathrm{cm/ns}$). Increased speeds necessitate increasing proximity of processing elements.

Limits of miniaturization Processor technology is allowing an increasing number of transistors to be placed on a chip. However, even with atomic-level components, a limit will be reached on how small components can be.

Economic limits It is increasingly expensive to make a single processor faster. Using a larger number of commodity processors to achieve same (or better) performance is less expensive.

Energy limits Limits imposed by cooling needs for chips and supercomputers.

A way out

- Current computer architectures are increasingly relying upon hardware level parallelism.
- Multiple execution units.
- Multi-core.

Who and what applies parallel computing?



Why should YOU parallelize your code?

- A single core may be too slow to perform the required task(s) in a "tolerable'' amount of time. The definition of "tolerable" certainly varies, but "overnight" is often a reasonable estimate.
- The memory requirements cannot be met by the amount of memory which is available on a single "Desktop".

Heterogeneity in Nature — Stylized modelling not always possible

- Supernova explosions - observable.
- Modelling in 1D:
  - $\rightarrow$ incl. fancy (GR/nuclear) physics.
  - $\rightarrow$ no explosions.
  - $\rightarrow$ only 1D models. due to lack of compute power (early 2000's).
- Only recently (last $\sim 5y$): "realistic" 3D models possible to run on supercomputers
  - $\rightarrow$ resources now available.
  - $\rightarrow$ stylized models not sufficient.



February 24, 1987; SN 1987 A in the large Magellanic cloud. Closest SN next to earth since 1604 . Distance from earth: $\sim 50\mathrm{kpc}$; 150'000 LY. $1\mathrm{kpc} = 3.08 \times 10^{19}\ \mathrm{m}, 1\mathrm{LY} = 9.46 \times 10^{15}\ \mathrm{m}$
Progenitor: $20\mathrm{M}_{\mathrm{sun}}$

Supercomputers



- HPC is the "third" pillar of science — nowadays is the dawn of an era (in physics, chemistry, biology, ..., next to experiment and theory).
- "In Silico" experiments.
- Modern Supercomputers (e.g. world's number 7 Summit at Oak Ridge National Lab) 200×10^{15} Flops/Sec. $\rightarrow$ 1 **day vs. Laptop:** $\sim 30,000$ **years.**

Supercomputers



- $\rightarrow$ Move away from stylized models towards "realistically-sized" problems.
- **Creating "good" HPC software can be very difficult...**

Petascale Computers — How can we tap them?

*Slide adjusted from O. Schenk

Modern Supercomputers (Summit) 200×10^{15} Flops/Sec. $\rightarrow$ 1 day
vs. Laptop: $\sim 30,000y$.

Let us say you can print:
10^{18} numbers (Exaflop) = 100,000,000 km
(distance to the sun) stack printed per second
(Exaflop/s)





June 2025 top500

https://top500.org/lists/top500/2025/06/

Rank	System	Cores	Rmax (PFlop/s)	Rpeak (PFlop/s)	Power (kW)
1	**El Capitan** - HPE Cray EX255a, AMD 4th Gen EPYC 24C 1.8GHz, AMD Instinct MI300A, Slingshot-11, TOSS, HPE DOE/NNSA/LLNL United States	11,039,616	1,742.00	2,746.38	29,581
2	**Frontier** - HPE Cray EX235a, AMD Optimized 3rd Generation EPYC 64C 2GHz, AMD Instinct MI250X, Slingshot-11, HPE Cray OS, HPE DOE/SC/Oak Ridge National Laboratory United States	9,066,176	1,353.00	2,055.72	24,607
3	**Aurora** - HPE Cray EX - Intel Exascale Compute Blade, Xeon CPU Max 9470 52C 2.4GHz, Intel Data Center GPU Max, Slingshot-11, Intel DOE/SC/Argonne National Laboratory United States	9,264,128	1,012.00	1,980.01	38,698
4	**JUPITER Booster** - BullSequana XH3000, GH Superchip 72C 3GHz, NVIDIA GH200 Superchip, Quad-Rail NVIDIA InfiniBand NDR200, RedHat Enterprise Linux, EVIDEN EuroHPC/FZJ Germany	4,801,344	793.40	930.00	13,088
5	**Eagle** - Microsoft NDv5, Xeon Platinum 8480C 48C 2GHz, NVIDIA H100, NVIDIA Infiniband NDR, Microsoft Azure Microsoft Azure United States	2,073,600	561.20	846.84	
6	**HPC6** - HPE Cray EX235a, AMD Optimized 3rd Generation EPYC 64C 2GHz, AMD Instinct MI250X, Slingshot-11, RHEL 8.9, HPE Eni S.p.A. Italy	3,143,520	477.90	606.97	8,461
7	**Supercomputer Fugaku** - Supercomputer Fugaku, A64FX 48C 2.2GHz, Tofu interconnect D, Fujitsu RIKEN Center for Computational Science Japan	7,630,848	442.01	537.21	29,899
8	**Alps** - HPE Cray EX254n, NVIDIA Grace 72C 3.1GHz, NVIDIA GH200 Superchip, Slingshot-11, HPE Cray OS, HPE Swiss National Supercomputing Centre (CSCS) Switzerland	2,121,600	434.90	574.84	7,124

II. Contemporary hardware



From a programming language to hardware

- A computer is a "stupid" device, only understands "on" and "off".
- The symbols for these states are 0 and 1 (binary).
- First programmers communicated in 0 and 1.
- Later programs where developed to translate from symbolic notation to binary. The first was called "**assembly**".

```
> add A, B (programmer writes in assembly language)
>1000110010100000 (assembly translates to machine language)
```

Advanced programming languages are better than "assembly":

- programmer thinks in a more natural language.
- productivity of software development.
- portability.

Basics: von Neumann Architecture

https://hpc.llnl.gov/documentation/tutorials/introduction-parallel-computing-tutorial

- Virtually all computers have followed this basic design. Comprised of **four main components**: Memory, Control Unit, Arithmetic Logic Unit, Input/Output.
- **Read/write, random access memory** is used to store both program instructions and data:
  - Program instructions are coded data which tell the computer to do something.
  - Data is simply information to be used by the program.
- **Control unit**
  - fetches instructions/data from memory, decodes the instructions and then sequentially coordinates operations to accomplish the programmed task.
- **Arithmetic unit**: performs basic arithmetic operations.
- **Input/Output**: interface to the human operator.



Performance measures

- Execution time: time between start and completion of a task.
- Throughput/Bandwidth: total amount of work per elapsed time.
- Performance and execution time:

$$\text{Perf}_x = \frac{1}{\text{Exectime}_x}$$

$$\text{Perf}_x > \text{Perf}_y \Longrightarrow \text{Exectime}_y > \text{Exectime}_x$$

x is N times faster than ***y*** means:

$$\frac{\text{Perf}_x}{\text{Perf}_y} = n = \frac{\text{Exectime}_y}{\text{Exectime}_x}$$

The free lunch

- For a long time speeding up computations was a "free lunch":
  - $\rightarrow$ the density of the transistors in chips increased, decreasing the size of integrated circuits.
  - $\rightarrow$ the clock speeds steadily rose, increasing the number of operations per second (MHz to GHz).
- But the free lunch has been over for a few years now:
  - $\rightarrow$ We are reaching the limitations of transistor density.
  - $\rightarrow$ Increasing clock frequency requires too much power.

$\rightarrow$ We used to focus on floating point operations per second. Now we also think about floating point operations per Watt.

The free lunch is over



Clock speed cannot increase More:

1. heat (too much of it and too hard to dissipate).
2. current leakage.
3. power consumption (too high - also memory must be considered).

Processor performance doubles every 18 month:

- Still true for the number of transistors.
- Not true for clock speed ($W \sim f^3 +$ hardware failures).
- Not true for memory/storage.

What is parallel computing?

Serial Computing:

Traditionally, software has been written for serial computation.

- A problem is broken into a discrete series of instructions.
- Instructions are executed serially one after another.
- Executed on a single processor.
- Only one instruction may execute at any moment in time.





"**To pull a bigger wagon, it is easier to add more oxen than to grow a gigantic ox**" — (Skjellum et al. 1999)

What is parallel computing II?

Parallel Computing: **In the simplest sense, parallel computing is the simultaneous use of multiple compute resources to solve a computational problem.**

- A problem is broken into a discrete series of instructions that can be solved concurrently.
- Each part is further broken down to a series of instructions.
- Instructions from each part execute simultaneously on different processors.
- An overall control/coordination mechanism is employed.



Flynn's Taxonomy

https://hpc.llnl.gov/documentation/tutorials/introduction-parallel-computing-tutorial

- There are different ways to classify parallel computers.
- One of the most commonly used (since 1966) is Flynn's Taxonomy.
- It distinguishes multiprocessor computer architectures according to how they can be classified along the two independent dimensions of Instruction Stream and Data Stream.
- Each of these dimensions can have only one of two possible states: Single or Multiple.



Single Instruction, Single Data (SISD)

A serial (non-parallel) computer.

- **Single Instruction:**
  - → Only one instruction stream is being acted on by the CPU during any one clock cycle.
- **Single Data:**
  - → Only one data stream is being used as input during any one clock cycle.
- This is the oldest type of computer.
- Examples: single processor/core PCs.



Single Instruction, Multiple Data (SIMD)

A type of parallel computer.

- **Single Instruction:**
- → All processing units execute the same instruction at any given clock cycle.
- **Multiple Data:**
- Each processing unit can operate on a different data element.
- Best suited for specialized problems characterized by a high degree of regularity.
- Most modern computers, particularly those with graphics processor units (GPUs) employ SIMD instructions and execution units.





Multiple Instruction, Multiple Data (MIMD)

A type of parallel computer.

- **Multiple Instruction:**
  - → Every processor may be executing a different instruction stream.
- **Multiple Data:**
  - → Every processor may be working with a different data stream.
- **Currently, the most common type of parallel computer most modern supercomputers fall into this category.**
- Note: many MIMD architectures also include SIMD execution subcomponents.



Speedup, Efficiency & Amdahl's Law

$T(p, N) :=$ **time to solve problem of total size N on p processors.**

Parallel speedup: $S(p, N) = \frac{T(1,N)}{T(p,N)}$

$\rightarrow$ Compute same problem with more processors in **shorter time.**

Parallel Efficiency: $E(p, N) = \frac{S(p,N)}{p}$

Amdahl's Law: $T(p, N) = f * T(1, N) + \frac{(1-f)T(1,N)}{p}$

f...sequential part of the code that can not be done in parallel.

$$S(p, N) = \frac{T(1, N)}{T(p, N)} = \frac{1}{(f + \frac{1-f}{p})}$$

For $p \rightarrow \infty$, speedup is limited by $S(p, N) < \frac{1}{f}$

Amdahl's Law: Scaling is tough





For $p \to \infty$, speedup is limited by $S(p, N) < \frac{1}{f}$



Weak versus strong scaling

Strong scaling:
Is defined as how the solution time varies with the number of processors for a fixed total problem size.

Weak scaling:
Is defined as how the solution time varies with the number of processors for a fixed problem size per processor.

HPC systems: off-shelf components



Your “Desktop”
Virtually all stand-alone computers today are parallel from a hardware perspective.

HPC systems

- Each compute node is a multi-processor parallel computer itself.
- Multiple compute nodes are networked together.
- Building blocks need to communicate (via the network) and give feedback (User/Storage).



Strengths of Commodity Clusters

- Excellent performance to cost.
- Exploits economy of scale.
  - Through mass-production of components
  - Many competing cluster vendors
- Flexible just-in-place configuration.
  - Scalable up and down
- Rapid tracking of technology.
  - First to exploit newest components
- Programmable.
  - Uses industry standard programming languages and tools
- User empowerment.
  - Low cost, ubiquitous systems
  - Programming systems make it relatively easy to program for expert users
- nearly all of TOP-500 deployed systems commodity clusters.

Two problems with this model

1. pure CPU-systems are becoming too expensive:
   - Power consumption.
   - Cooling and infrastructural costs (can be O (mio \$/ year)) $\rightarrow$ e.g. one Olympic swimming pool per hour cooling water needed.
2. It is hard to increase the performance:
   - Speed-up the processor.
   - Increase network bandwidth.
   - Make I/O faster.
   - ...

HPC system's power consumption

...how to get 1000x more performance without building a nuclear power plant next to your HPC? (J. Shalf, September 09, Lausanne/Switzerland)

Coming HPC systems are anticipated to draw enormous amounts of electrical power...
Example: N.1 Top 500

Year (Nov.)	System	Performance (Tflop/s)	Electrical power (KW)
2002	Hearth Simulator	41	3200
2005	Blue Gene/L	367	1433
2008	Roadrunner	1105	2483
2009	Jaguar	2331	6950
2011	K computer	11280	12659
2012	Titan	27112	8209
2014	Tianhe-2	54902	17808
→2020	????????	1000000	>100000 (100 MW!!!)

$\Longrightarrow$ **Not sustainable**

Improving performance: multi & many-cores

- Adding more and more "classical" cores can increase the computing power without having to increase the clock speed. However:
- $\rightarrow$ Hardware strongly limits the scalability.
- Progressively,a new generation of processors with less general, more specialized architecture, capable superior performance on a narrower range of problems, is growing:
- Many-core accelerators:
  - Nvidia Graphics Processor Units (GPUs).
  - Intel Xeon Phi Many Integrated Cores (MIC) architecture.
  - TPU (Tensor Processing Units)
  - *ldots*
- They all support a massively parallel computing paradigm.

Why are accelerators more efficient than CPUs?

A few reasons:

- Lower frequencies of GPU clocks.
- More of the transistors in a GPU are working on the computation. **CPUs are more general purpose. They require energy to support such flexibility.**
- Single Instruction Multiple Data (SIMD) approach, which leads to a simpler architecture and instruction set.

More hardware accelerators for ML*

Microsoft

FPGA – field programmable gate arrays

Google

TPU — Tensor Processing Unit

ALTERA
Part of INTEL

facebook

intel

NVIDIA

intel + nervana

Today's HPC systems



Overall picture of programming models

(Slide from C. Gheller)



Where are we going?

(Slide from C. Gheller)

Heterogeneous systems are the next future. Right now, they represent the only viable solution for efficient high performance computing



3. Programming Models



Questions for parallel programming

Asanovic et. al. (2006) — The landscape of Parallel Computing Research: A View from Berkeley



Figure 1. A view from Berkeley: seven critical questions for 21st Century parallel computing. (This figure is inspired by a view of the Golden Gate Bridge from Berkeley.)

Programming models: Overview

- **There are several parallel programming models in common use:**
  1. Shared Memory (without threads)
  2. Threads
  3. Distributed Memory / Message Passing
  4. Data Parallel
  5. Hybrid
  6. Single Program Multiple Data (SPMD)
  7. Multiple Program Multiple Data (MPMD)
- **Parallel programming models exist as an abstraction above hardware and memory architectures.**
- Although it might not seem apparent, these models are NOT specific to a particular type of machine or memory architecture. In fact, any of these models can (theoretically) be implemented on any underlying hardware.
- **Which model to use?**
- This is often a combination of what is available and personal choice. There is no "best" model, although there certainly are better implementations of some models over others.

Parallel program design: Understand the problem

- The first step in developing parallel software is to first understand the problem that you wish to solve in parallel.
- Before spending time in an attempt to develop a parallel solution for a problem, determine whether or not the problem is one that can actually be parallelized.
  - Example of Parallelizable Problem: Monte Carlo integration
  - Example of a Non-parallelizable Problem: Calculation of the Fibonacci series $(0, 1, 1, 2, 3, 5, 8, 13, 21, \ldots)$ by use of the formula: $F(n) = F(n-1) + F(n-2)$
    - This is a non-parallelizable problem because the calculation of the Fibonacci sequence as shown would entail dependent calculations rather than independent ones. The calculation of the $F(n)$ value uses those of both $F(n-1)$ and $F(n-2)$. These three terms cannot be calculated independently and therefore, not in parallel.
- **Identify hotspots** (where is the real work being done?)
- **Identify bottlenecks** in the program
  - are there disproportionally slow regions in code, e.g. I/O; can restructuring of program help?

Decomposition of Problem

https://hpc.llnl.gov/documentation/tutorials/introduction-parallel-computing-tutorial



e.g. domain decomposition (e.g. for PDEs)



Functional decomposition (e.g. for climate modelling)

Communication

Is communication needed?

The need for communication between tasks depend upon your problem

- you don't need communications: embarrassingly parallel (e.g. Monte Carlo)
- you need communications (e.g. stencil computation in a finite difference scheme (data dependency))
- Cost of communication (e.g. transmit data implies overhead)

Load balancing

https://hpc.llnl.gov/documentation/tutorials/introduction-parallel-computing-tutorial



- Load balancing refers to the practice of distributing work among tasks so that all tasks are kept busy all of the time.
- **It can be considered a minimization of task idle time.**
- Load balancing is important to parallel programs for performance reasons. For example, if all tasks are subject to a barrier synchronization point, the slowest task will determine the overall performance.

We will consider mainly OpenMP* & MPI**

*https://hpc-tutorials.llnl.gov/openmp/ (Open Multi-Processing) and **https://hpc-tutorials.llnl.gov/mpi/ (Message Passing Interface)



Shared Memory (OpenMP)



Distributed Memory (MPI)

Using SIMD instruction sets→ Vectorization

- Vectorization performs multiple operations in parallel on a core with a single instruction (SIMD - single instruction multiple data).
- Data is loaded into vector registers that are described by their width in bits:
  - 256 bit registers: $8x$ float, or $4x$ double
  - 512 bit registers: $16x$ float, or $8x$ double
- Vector units perform arithmetic operations on vector registers simultaneously.
- Vectorization is key to maximising computational performance.

Vectorization illustrated



In an optimal situation all this is carried out by the compiler automatically.
Compiler directives can be used to give hints as to where vectorization is safe and/or beneficial.

```
1  ! vectorized part
2  rest = mod(N,4)
3  do i=1,N-rest,4
4    load R1 = [x(i),x(i+1),x(i+2),x(i+3)]
5    load R2 = [y(i),y(i+1),y(i+2),y(i+3)]
6    ! "packed" addition (4 SP flops)
7    R3 = ADD(R1,R2)
8    store [r(i),r(i+1),r(i+2),r(i+3)] = R3
9  enddo
10 ! remainder loop
11 do i=N-rest+1,N
12   r(i) = x(i) + y(i)
13 enddo
```

Advanced Vector Extensions (AVX)



Fig. 7. Vector registers on modern CPUs: a scalar program can utilize only 1/4 of computational parallelism on AVX-enabled CPUs, e.g. the SandyBridge.

Shared memory systems

- **Process can access same GLOBAL memory**
- **Uniform Memory Access (UMA) model**
  - Access time to memory is uniform.
  - Local cache, all other peripherals are shared.
- **Non-Uniform Memory Access (NUMA) model**
  - Memory is physically distributed among processors.
  - Global virtual address spaces accessible from all processors.
  - **Access time to local and remote data is different.**
- **OpenMP**, but other solutions available (e.g. Intel's TBB).



Shared Memory — Pros & Cons

Pros:

- Global address space provides a user-friendly programming perspective to memory.
- Data sharing between tasks is both fast and uniform due to the proximity of memory to CPUs.

Cons:

- Lack of scalability between memory and CPUs. Adding more CPUs geometrically increases traffic on the shared memory-CPU path...
- Programmer responsibility for synchronization constructs that ensure "correct" access of global memory.

Distributed-memory parallel programming (with MPI)

- We need to use explicit message passing, i.e., communication between processes:
  - Most tedious and complicated but also the most flexible parallelization method.
- Message passing is required if a parallel computer is of **distributed-memory** type, i.e., if there is no way for one processor to directly access the address space of another.
- However, it can also be regarded as a programming model and used on shared-memory or **hybrid systems** as well.
- → **Message Passing Interface (MPI).**



Parallel programming with MPI

- The Message Passing Interface Standard (MPI) is a message passing library standard based on the consensus of the MPI Forum, which has over 40 participating organizations, including vendors, researchers, software library developers, and users.
- The goal of the MPI is to establish a portable, efficient, and flexible standard for message passing that will be widely used for writing message passing programs. As such, MPI is the first standardized, vendor independent, message passing library.
- Several MPI implementations exist (Mpich, OpenMPI, IntelMPI, CrayMPI, ...).
- The current MPI standard currently defines over 500 functions, and it is beyond the scope of this introduction even try to cover them all. Here, I will concentrate on the important concepts of message passing and MPI in particular, and provide some knowledge that will enable you to consult more advanced textbooks and tutorials.

Message Passing Interface (MPI)

- Resources are LOCAL (different from shared memory).
- Each process runs in an "isolated" environment. Interactions requires Messages to be exchanged
- Messages can be: instructions, data, synchronization.
- MPI works also on Shared Memory systems.
- Time to exchange messages is much larger than accessing local memory.

Message Passing is a COOPERATIVE Approach, based on 3 operations:

- SEND (a message)
- RECEIVE (a message)
- SYNCHRONIZE



MPI availability

- MPI is standard defined in a set of documents compiled by a consortium of organizations : `http://www.mpi-forum.org/`
- In particular the MPI documents define the APIs for C, C++, FORTRAN77 and FORTRAN 90.
- Bindings available for Perl, Python, Java...
- In all systems MPI is implemented as **a library of subroutines/functions** over the network drivers and primitives.

GPU Programming

API currently available

- **CUDA**
  - NVIDIA product, best performance, low portability
- **OpenCL**
  - Open standard, API similar to CUDA, high portability
- **OpenACC**
  - Directive based open standard
- **OpenMP**
  - Directive based open standard
- **Libraries**
  - MAGMA, cuFFT, Thrust, CULA, cuBLAS, cuSOLVER...
- **C++11**
  - High level abstraction



Supported languages: C, C++, Fortran but also Java, Python (not from all the APIs)

GPU programming II



Degrees of Parallelism

- Current supercomputers are hybrid.
- There are 4 main degrees of parallelism on multi-core (HPC) systems.
- Parallelism among nodes/sockets (e.g. MPI).
- Parallelism among cores in a socket (e.g. OpenMP).
- Vector units in each core (e.g. AVX).
- Accelerators...

All should be exploited at once ($\rightarrow$lecture next week)

Questions?