# WebDAV Servers

#### 0.1 Documentation

by Michael Wechner

### 1. Apache 1

Download the Apache Web Server and WebDAV module source code from the Apache website, e.g. apache\_1.3.24.tar.gz and mod\_dav-1.0.3-1.3.6.tar.gz. Configure and compile mod\_dav:

```
cd /home/michiii/src/mod_dav-1.0.3-1.3.6
./configure --with-apache=/home/michiii/src/apache_1.3.24
make
make install
cd /home/michiii/src/apache_1.3.24
find . -name "*dav*" -print
./configure --prefix=/usr/local/apache --activate-module=src/modules/dav/libdav.a
(./configure --prefix=/usr/local/apache --enable-module=proxy --activate-module=src/mod
make
make install
```

You need to reconfigure httpd.conf, e.g.:

```
DAVLockDB /home/michiii/build/apache/logs/DavLock 
<Directory "/home/michiii/build/apache/htdocs"> 
Dav On
```

To see the files open "Konqueror" and type webdav://127.0.0.1:8080.

More info on mod dav can be found at

- <a href="http://www.webdav.org/mod\_dav/">http://www.webdav.org/mod\_dav/</a>
- Apache and DAV with LDAP and SSL

## 2. Apache 2

Download the Apache Web Server source code from the Apache website, e.g.

httpd-2.0.46.tar.gz. The mod\_dav module is inlcuded with the Apache 2 distribution. Configure and compile Apache:

```
./configure --prefix=/home/michiii/build/apache2 --with-dav --enable-dav make
make install
/home/michiii/build/apache2/bin/httpd -l | grep dav
```

You need to reconfigure Apache:

```
DAVLockDB /home/michiii/build/apache2/logs/DavLock <Directory "/home/michiii/build/apache2/htdocs">
Dav On </Directory>
```

More info on mod\_dav can be found at

- <a href="http://apacheworld.org/ty24/site.chapter13.html">http://apacheworld.org/ty24/site.chapter13.html</a>
- <a href="http://httpd.apache.org/docs-2.0/mod/mod\_dav.html">http://httpd.apache.org/docs-2.0/mod/mod\_dav.html</a>
- Apache and DAV

#### 3. Tomcat

Point your WebDAV client to http://127.0.0.1:8080/webdav/. The webdav context is DAV enabled, but has been set up in read-only mode for safety reasons. It can be put in read-write mode by editing the web application descriptor file /webapps/webdav/WEB-INF/web.xml.

```
<!-- Uncomment this to enable read and write access -->
<init-param>
  <param-name>readonly</param-name>
  <param-value>false</param-value>
</init-param>
```

## 4. Apache Jakarta Slide

Point your WebDAV client to http://127.0.0.1:8080/slide/. One needs to configure Domain.xml

```
<contentstore classname="slidestore.reference.FileContentStore">
  <parameter name="rootpath">/home/michiii/build/jakarta-tomcat-4.1.21-LE-jdk14/webapps
```

И	/eł	ıΩ	Д١	/	Se	rv/	e	rs
v	1	JLJ.	$\boldsymbol{\neg}$	•	C)C	ıv	7	

. . .