NAME

XtVaCreateArgsList - dynamically allocate a varargs list

SYNTAX

#include <X11/Intrinsic.h>

XtVarArgsList XtVaCreateArgsList(XtPointer unused, ...);

ARGUMENTS

unused Must be specified as NULL.

Specifies a variable parameter list of resource name and value pairs.

DESCRIPTION

The **XtVaCreateArgsList** function allocates memory and copies its arguments into a single list pointer, which may be used with **XtVaNestedList**. The end of both lists is identified by aname entry containing NULL. Any entries of type **XtVaTypedArg** are copied as specified without applying conversions. Data passed by reference (including Strings) are not copied, only the pointers themselves; the caller must ensure that the data remain valid for the lifetime of the created varargs list. The list should be freed using **XtFree** when no longer needed.

SEE ALSO

X Toolkit Intrinsics – C Language Interface Xlib – C Language X Interface