## **NAME**

rpc\_clnt\_calls, clnt\_call, clnt\_freeres, clnt\_geterr, clnt\_perrno, clnt\_perror, clnt\_sperrno, clnt\_sperror, rpc\_broadcast, rpc\_broadcast\_exp, rpc\_call — library routines for client side calls

#### SYNOPSIS

```
#include <rpc/rpc.h>
enum clnt stat
clnt_call(CLIENT *clnt, const rpcproc_t procnum, const xdrproc_t inproc,
    const caddr_t in, const xdrproc_t outproc, caddr_t out,
    const struct timeval tout);
bool t
clnt_freeres(CLIENT *clnt, const xdrproc_t outproc, caddr_t out);
clnt_geterr(const CLIENT * clnt, struct rpc_err * errp);
clnt_perrno(const enum clnt_stat stat);
void
clnt_perror(CLIENT *clnt, const char *s);
clnt_sperrno(const enum clnt_stat stat);
char *
clnt_sperror(CLIENT *clnt, const char * s);
enum clnt_stat
rpc_broadcast(const rpcprog_t prognum, const rpcvers_t versnum,
    const rpcproc_t procnum, const xdrproc_t inproc, const caddr_t in,
    const xdrproc_t outproc,caddr_t out,const resultproc_t eachresult,
    const char *nettype);
enum clnt stat
rpc_broadcast_exp(const rpcprog_t prognum,const rpcvers_t versnum,
    const rpcproc_t procnum,const xdrproc_t xargs,caddr_t argsp,
    const xdrproc_t xresults, caddr_t resultsp,
    const resultproc_t each result, const int inittime, const int waittime,
    const char * nettype);
enum clnt_stat
rpc_call(const char *host, const rpcprog_t prognum,
    const rpcvers_t versnum,const rpcproc_t procnum,
    const xdrproc_t inproc,const char *in,const xdrproc_t outproc,
    char *out, const char *nettype);
```

## DESCRIPTION

RPC library routines allow C language programs to make procedure calls on other machines across the network. First, the client calls a procedure to send a request to the server. Upon receipt of the request, the server calls a dispatch routine to perform the requested service, and then sends back a reply.

The clnt\_call(), rpc\_call(), and rpc\_broadcast() routines handle the client side of the procedure call. The remaining routines deal with error handling in the case of errors.

Some of the routines take a *CLIENT* handle as one of the arguments. A*CLIENT* handle can be created by an RPC creation routine such as **clnt\_create**() (see rpc\_clnt\_create(3)).

These routines are safe for use in multithreaded applications. *CLIENT* handles can be shared between threads, however in this implementation requests by different threads are serialized (that is, the first request will receive its results before the second request is sent).

### **Routines**

See rpc(3) for the definition of the CLIENT data structure.

### clnt\_call()

A function macro that calls the remote procedure procnum associated with the client handle, clnt, which is obtained with an RPC client creation routine such as clnt\_create() (see rpc\_clnt\_create(3)). Theinproc ar gument is the XDR function used to encode the procedure's arguments, and outproc is the XDR function used to decode the procedure's results; in is the address of the procedure's argument(s), and out is the address of where to place the result(s). The tout argument is the time allowed for results to be returned, which is overridden by a time-out set explicitly through clnt\_control(), see rpc\_clnt\_create(3). If the remote call succeeds, the status returned is RPC\_SUCCESS, otherwise an appropriate status is returned.

### clnt freeres()

A function macro that frees any data allocated by the RPC/XDR system when it decoded the results of an RPC call. The *out* argument is the address of the results, and *outproc* is the XDR routine describing the results. This routine returns 1 if the results were successfully freed, and 0 otherwise.

## clnt\_geterr()

A function macro that copies the error structure out of the client handle to the structure at address errp.

## clnt\_perrno()

Print a message to standard error corresponding to the condition indicated by stat. A newline is appended. Normally used after a procedure call fails for a routine for which a client handle is not needed, for instance rpc call().

# clnt\_perror()

Print a message to the standard error indicating why an RPC call failed; *clnt* is the handle used to do the call. The message is prepended with string s and a colon. A newline is appended. Normally used after a remote procedure call fails for a routine which requires a client handle, for instance clnt\_call().

## clnt\_sperrno()

Take the same arguments as <code>clnt\_perrno()</code>, but instead of sending a message to the standard error indicating why an RPC call failed, return a pointer to a string which contains the message. The <code>clnt\_sperrno()</code> function is normally used instead of <code>clnt\_perrno()</code> when the program does not have a standard error (as a program running as a server quite likely does not), or if the programmer does not want the message to be output with <code>printf()</code> (see <code>printf(3)</code>), or if a message format different than that supported by <code>clnt\_perrno()</code> is to be used. Note: unlike <code>clnt\_sperror()</code> and <code>clnt\_sperreateerror()</code> (see <code>rpc\_clnt\_create(3))</code>, <code>clnt\_sperrno()</code> does not return pointer to static data so the result will not get overwritten on each call.

## clnt\_sperror()

Like **clnt\_perror**(), except that (like **clnt\_sperroo**()) it returns a string instead of printing to standard error. However, **clnt\_sperror**() does not append a newline at the end of the message. Warning: returns pointer to a buffer that is overwritten on each call.

### rpc broadcast()

Like **rpc\_call**(), except the call message is broadcast to all the connectionless transports specified by <code>nettype</code>. If <code>nettype</code> is NULL, it def aults to "netpath". Each time it receives a response, this routine calls <code>eachresult()</code>, whose form is: <code>bool\_t</code> <code>eachresult(caddr\_t</code> out, <code>const struct netbuf \* addr</code>, <code>const struct netconfig \* netconf()</code> where out is the same as out passed to <code>rpc\_broadcast()</code>, except that the remote procedure's output is decoded there; <code>addr</code> points to the address of the machine that sent the results, and <code>netconf()</code> is the netconfig structure of the transport on which the remote server responded. If <code>eachresult()</code> returns 0, <code>rpc\_broadcast()</code> waits for more replies; otherwise it returns with appropriate status. Warning: broadcast file descriptors are limited in size to the maximum transfer size of that transport. For Ethernet, this value is 1500 bytes. The <code>rpc\_broadcast()</code> function uses AUTH\_SYS credentials by default (see <code>rpc\_clnt\_auth(3))</code>.

## rpc\_broadcast\_exp()

Like **rpc\_broadcast**(), except that the initial timeout, *inittime* and the maximum timeout, *waittime* are specified in milliseconds. The *inittime* argument is the initial time that **rpc\_broadcast\_exp**() waits before resending the request. After the first resend, the re-transmission interval increases exponentially until it exceeds *waittime*.

### rpc\_call()

Call the remote procedure associated with prognum, versnum, and procnum on the machine, host. The inproc ar gument is used to encode the procedure's arguments, and outproc is used to decode the procedure's results; in is the address of the procedure's argument(s), and out is the address of where to place the result(s). The nettype argument can be any of the values listed on rpc(3). This routine returnsRPC\_SUCCESS if it succeeds, or an appropriate status is returned. Use the clnt\_perrno() routine to translate failure status into error messages. Warning: rpc\_call() uses the first available transport belonging to the class nettype, on which it can create a connection. You do not have control of timeouts or authentication using this routine.

### **AVAILABILITY**

These functions are part of libtirpc.

## **SEE ALSO**

printf(3), rpc(3), rpc\_clnt\_auth(3), rpc\_clnt\_create(3)