NAME

provider-base - The basic OpenSSL library <-> provider functions

SYNOPSIS

```
#include <openssl/core_dispatch.h>
/*
 ^{\star} None of these are actual functions, but are displayed like this for
 \star the function signatures for functions that are offered as function
 * pointers in OSSL_DISPATCH arrays.
/* Functions offered by libcrypto to the providers */
const OSSL_ITEM *core_gettable_params(const OSSL_CORE_HANDLE *handle);
int core_get_params(const OSSL_CORE_HANDLE *handle, OSSL_PARAM params[]);
typedef void (*OSSL_thread_stop_handler_fn)(void *arg);
int core_thread_start(const OSSL_CORE_HANDLE *handle,
                      OSSL_thread_stop_handler_fn handfn,
                      void *arg);
OPENSSL_CORE_CTX *core_get_libctx(const OSSL_CORE_HANDLE *handle);
void core_new_error(const OSSL_CORE_HANDLE *handle);
void core_set_error_debug(const OSSL_CORE_HANDLE *handle,
                          const char *file, int line, const char *func);
void core_vset_error(const OSSL_CORE_HANDLE *handle,
                     uint32_t reason, const char *fmt, va_list args);
int core_obj_add_sigid(const OSSL_CORE_HANDLE *prov, const char *sign_name,
                       const char *digest_name, const char *pkey_name);
int core_obj_create(const OSSL_CORE_HANDLE *handle, const char *oid,
                    const char *sn, const char *ln);
 * Some OpenSSL functionality is directly offered to providers via
 * dispatch
 * /
void *CRYPTO_malloc(size_t num, const char *file, int line);
void *CRYPTO_zalloc(size_t num, const char *file, int line);
void CRYPTO_free(void *ptr, const char *file, int line);
void CRYPTO_clear_free(void *ptr, size_t num,
                       const char *file, int line);
void *CRYPTO_realloc(void *addr, size_t num,
                     const char *file, int line);
void *CRYPTO_clear_realloc(void *addr, size_t old_num, size_t num,
                           const char *file, int line);
void *CRYPTO_secure_malloc(size_t num, const char *file, int line);
void *CRYPTO_secure_zalloc(size_t num, const char *file, int line);
void CRYPTO_secure_free(void *ptr, const char *file, int line);
void CRYPTO_secure_clear_free(void *ptr, size_t num,
                              const char *file, int line);
int CRYPTO_secure_allocated(const void *ptr);
void OPENSSL_cleanse(void *ptr, size_t len);
unsigned char *OPENSSL_hexstr2buf(const char *str, long *buflen);
```

```
OSSL_CORE_BIO *BIO_new_file(const char *filename, const char *mode);
OSSL_CORE_BIO *BIO_new_membuf(const void *buf, int len);
int BIO_read_ex(OSSL_CORE_BIO *bio, void *data, size_t data_len,
                size t *bytes read);
int BIO_write_ex(OSSL_CORE_BIO *bio, const void *data, size_t data_len,
                 size_t *written);
int BIO_up_ref(OSSL_CORE_BIO *bio);
int BIO free(OSSL CORE BIO *bio);
int BIO_vprintf(OSSL_CORE_BIO *bio, const char *format, va_list args);
int BIO_vsnprintf(char *buf, size_t n, const char *fmt, va_list args);
void OSSL_SELF_TEST_set_callback(OSSL_LIB_CTX *libctx, OSSL_CALLBACK *cb,
                                 void *cbarg);
size_t get_entropy(const OSSL_CORE_HANDLE *handle,
                   unsigned char **pout, int entropy,
                   size_t min_len, size_t max_len);
void cleanup_entropy(const OSSL_CORE_HANDLE *handle,
                     unsigned char *buf, size_t len);
size_t get_nonce(const OSSL_CORE_HANDLE *handle,
                 unsigned char **pout, size_t min_len, size_t max_len,
                 const void *salt, size_t salt_len);
void cleanup_nonce(const OSSL_CORE_HANDLE *handle,
                   unsigned char *buf, size_t len);
/* Functions for querying the providers in the application library context */
int provider_register_child_cb(const OSSL_CORE_HANDLE *handle,
                    int (*create_cb)(const OSSL_CORE_HANDLE *provider,
                                     void *cbdata),
                    int (*remove_cb)(const OSSL_CORE_HANDLE *provider,
                                     void *cbdata),
                    int (*global_props_cb)(const char *props, void *cbdata),
                    void *cbdata);
void provider_deregister_child_cb(const OSSL_CORE_HANDLE *handle);
const char *provider_name(const OSSL_CORE_HANDLE *prov);
void *provider_get0_provider_ctx(const OSSL_CORE_HANDLE *prov);
const OSSL_DISPATCH *provider_get0_dispatch(const OSSL_CORE_HANDLE *prov);
int provider_up_ref(const OSSL_CORE_HANDLE *prov, int activate);
int provider_free(const OSSL_CORE_HANDLE *prov, int deactivate);
/* Functions offered by the provider to libcrypto */
void provider_teardown(void *provctx);
const OSSL_ITEM *provider_gettable_params(void *provctx);
int provider get params(void *provctx, OSSL PARAM params[]);
const OSSL_ALGORITHM *provider_query_operation(void *provctx,
                                               int operation_id,
                                               const int *no_store);
void provider_unquery_operation(void *provctx, int operation_id,
                                const OSSL_ALGORITHM *algs);
const OSSL_ITEM *provider_get_reason_strings(void *provctx);
int provider_get_capabilities(void *provctx, const char *capability,
                              OSSL_CALLBACK *cb, void *arg);
```

int provider_self_test(void *provctx);

DESCRIPTION

All "functions" mentioned here are passed as function pointers between *libcrypto* and the provider in **OSSL_DISPATCH** arrays, in the call of the provider initialization function. See "Provider" in **provider** (7) for a description of the initialization function. They are known as "upcalls".

All these "functions" have a corresponding function type definition named **OSSL_FUNC_{name}_fn**, and a helper function to retrieve the function pointer from a **OSSL_DISPATCH** element named **OSSL_FUNC_{name}**. For example, the "function" **core_gettable_params**() has these:

```
typedef OSSL_PARAM *
    (OSSL_FUNC_core_gettable_params_fn)(const OSSL_CORE_HANDLE *handle);
static ossl_inline OSSL_NAME_core_gettable_params_fn
    OSSL_FUNC_core_gettable_params(const OSSL_DISPATCH *opf);
```

OSSL_DISPATCH arrays are indexed by numbers that are provided as macros in **openssl-core_dispatch.h** (7), as follows:

For in (the **OSSL_DISPATCH** array passed from *libcrypto* to the provider):

```
core_gettable_params
                               OSSL FUNC CORE GETTABLE PARAMS
                               OSSL_FUNC_CORE_GET_PARAMS
core_get_params
                               OSSL_FUNC_CORE_THREAD_START
core_thread_start
core_get_libctx
                               OSSL FUNC CORE GET LIBCTX
                               OSSL_FUNC_CORE_NEW_ERROR
core_new_error
core_set_error_debug
                               OSSL_FUNC_CORE_SET_ERROR_DEBUG
core_vset_error
                               OSSL_FUNC_CORE_VSET_ERROR
core obj add sigid
                               OSSL FUNC CORE OBJ ADD SIGID
                               OSSL_FUNC_CORE_OBJ_CREATE
core_obj_create
                               OSSL FUNC CRYPTO MALLOC
CRYPTO_malloc
CRYPTO zalloc
                               OSSL FUNC CRYPTO ZALLOC
CRYPTO_free
                               OSSL_FUNC_CRYPTO_FREE
CRYPTO_clear_free
                               OSSL_FUNC_CRYPTO_CLEAR_FREE
CRYPTO_realloc
                               OSSL_FUNC_CRYPTO_REALLOC
CRYPTO clear realloc
                               OSSL FUNC CRYPTO CLEAR REALLOC
CRYPTO_secure_malloc
                               OSSL_FUNC_CRYPTO_SECURE_MALLOC
CRYPTO_secure_zalloc
                               OSSL_FUNC_CRYPTO_SECURE_ZALLOC
CRYPTO secure free
                               OSSL FUNC CRYPTO SECURE FREE
CRYPTO_secure_clear_free
                               OSSL FUNC CRYPTO SECURE CLEAR FREE
CRYPTO_secure_allocated
                               OSSL_FUNC_CRYPTO_SECURE_ALLOCATED
BIO_new_file
                               OSSL_FUNC_BIO_NEW_FILE
                               OSSL FUNC BIO NEW MEMBUF
BIO new mem buf
                               OSSL_FUNC_BIO_READ_EX
BIO_read_ex
                               OSSL_FUNC_BIO_WRITE_EX
BIO_write_ex
BIO_up_ref
                               OSSL_FUNC_BIO_UP_REF
BIO free
                               OSSL_FUNC_BIO_FREE
BIO_vprintf
                               OSSL_FUNC_BIO_VPRINTF
BIO_vsnprintf
                               OSSL_FUNC_BIO_VSNPRINTF
BIO puts
                               OSSL FUNC BIO PUTS
BIO_gets
                               OSSL FUNC BIO GETS
                               OSSL_FUNC_BIO_CTRL
BIO_ctrl
                               OSSL_FUNC_OPENSSL_CLEANSE
OPENSSL_cleanse
OSSL_SELF_TEST_set_callback
                               OSSL_FUNC_SELF_TEST_CB
ossl_rand_get_entropy
                               OSSL_FUNC_GET_ENTROPY
ossl_rand_cleanup_entropy
                               OSSL_FUNC_CLEANUP_ENTROPY
ossl_rand_get_nonce
                               OSSL_FUNC_GET_NONCE
ossl_rand_cleanup_nonce
                               OSSL_FUNC_CLEANUP_NONCE
provider_register_child_cb
                               OSSL_FUNC_PROVIDER_REGISTER_CHILD_CB
```

3.0.2 2023-02-06 3

```
provider_deregister_child_cb OSSL_FUNC_PROVIDER_DEREGISTER_CHILD_CB provider_name OSSL_FUNC_PROVIDER_NAME OSSL_FUNC_PROVIDER_GET0_PROVIDER_CTX provider_get0_dispatch OSSL_FUNC_PROVIDER_GET0_DISPATCH provider_up_ref OSSL_FUNC_PROVIDER_UP_REF provider_free OSSL_FUNC_PROVIDER_FREE
```

For *out (the **OSSL_DISPATCH** array passed from the provider to *libcrypto*):

```
provider teardown
                               OSSL FUNC PROVIDER TEARDOWN
provider_gettable_params
                               OSSL_FUNC_PROVIDER_GETTABLE_PARAMS
provider_get_params
                               OSSL_FUNC_PROVIDER_GET_PARAMS
provider_query_operation
                               OSSL FUNC PROVIDER QUERY OPERATION
provider_unquery_operation
                               OSSL_FUNC_PROVIDER_UNQUERY_OPERATION
                               OSSL_FUNC_PROVIDER_GET_REASON_STRINGS
provider_get_reason_strings
provider_get_capabilities
                               OSSL_FUNC_PROVIDER_GET_CAPABILITIES
provider self test
                               OSSL FUNC PROVIDER SELF TEST
```

Core functions

core_gettable_params() returns a constant array of descriptor OSSL_PARAM, for parameters that core_get_params() can handle.

core_get_params() retrieves parameters from the core for the given *handle*. See "Core parameters" below for a description of currently known parameters.

The **core_thread_start()** function informs the core that the provider has stated an interest in the current thread. The core will inform the provider when the thread eventually stops. It must be passed the *handle* for this provider, as well as a callback *handfn* which will be called when the thread stops. The callback will subsequently be called, with the supplied argument *arg*, from the thread that is stopping and gets passed the provider context as an argument. This may be useful to perform thread specific clean up such as freeing thread local variables.

core_get_libctx() retrieves the core context in which the library object for the current provider is stored, accessible through the *handle*. This function is useful only for built-in providers such as the default provider. Never cast this to OSSL_LIB_CTX in a provider that is not built-in as the OSSL_LIB_CTX of the library loading the provider might be a completely different structure than the OSSL_LIB_CTX of the library the provider is linked to. Use OSSL_LIB_CTX_new_child (3) instead to obtain a proper library context that is linked to the application library context.

core_new_error(), **core_set_error_debug()** and **core_vset_error()** are building blocks for reporting an error back to the core, with reference to the *handle*.

core_new_error()

allocates a new thread specific error record.

This corresponds to the OpenSSL function ERR_new (3).

core_set_error_debug()

sets debugging information in the current thread specific error record. The debugging information includes the name of the file *file*, the line *line* and the function name *func* where the error occurred.

This corresponds to the OpenSSL function **ERR_set_debug** (3).

core_vset_error()

sets the *reason* for the error, along with any addition data. The *reason* is a number defined by the provider and used to index the reason strings table that's returned by **provider_get_reason_strings**(). The additional data is given as a format string *fmt* and a set of arguments *args*, which are treated in the same manner as with **BIO_vsnprintf**(). *file* and *line* may also be passed to indicate exactly where the error occurred or was reported.

This corresponds to the OpenSSL function **ERR_vset_error** (3).

The core_obj_create() function registers a new OID and associated short name sn and long name ln for the

given *handle*. It is similar to the OpenSSL function **OBJ_create** (3) except that it returns 1 on success or 0 on failure. It will treat as success the case where the OID already exists (even if the short name *sn* or long name *ln* provided as arguments differ from those associated with the existing OID, in which case the new names are not associated). This function is not thread safe.

The **core_obj_add_sigid()** function registers a new composite signature algorithm (*sign_name*) consisting of an underlying signature algorithm (*pkey_name*) and digest algorithm (*digest_name*) for the given *handle*. It assumes that the OIDs for the composite signature algorithm as well as for the underlying signature and digest algorithms are either already known to OpenSSL or have been registered via a call to **core_obj_create()**. It corresponds to the OpenSSL function **OBJ_add_sigid(3)**, except that the objects are identified by name rather than a numeric NID. Any name (OID, short name or long name) can be used to identify the object. It will treat as success the case where the composite signature algorithm already exists (even if registered against a different underlying signature or digest algorithm). For *digest_name*, NULL or an empty string is permissible for signature algorithms that do not need a digest to operate correctly. The function returns 1 on success or 0 on failure. This function is not thread safe.

CRYPTO_malloc(), CRYPTO_zalloc(), CRYPTO_free(), CRYPTO_clear_free(), CRYPTO_realloc(), CRYPTO_secure_malloc(), CRYPTO_secure_gralloc(), CRYPTO_secure_free(), CRYPTO_secure_gralloc(), CRYPTO_secure_free(), CRYPTO_secure_gralloc(), CRYPTO_secure_gralloc(), CRYPTO_secure_gralloc(), BIO_new_file(), BIO_new_mem_buf(), BIO_read_ex(), BIO_write_ex(), BIO_up_ref(), BIO_free(), BIO_vprintf(), BIO_vprintf(), BIO_gets(), BIO_puts(), BIO_ctrl(), OPENSSL_cleanse() and OPENSSL_hexstr2buf() correspond exactly to the public functions with the same name. As a matter of fact, the pointers in the OSSL_DISPATCH array are typically direct pointers to those public functions. Note that the BIO functions take an OSSL_CORE_BIO type rather than the standard BIO type. This is to ensure that a provider does not mix BIOs from the core with BIOs used on the provider side (the two are not compatible). OSSL_SELF_TEST_set_callback() is used to set an optional callback that can be passed into a provider. This may be ignored by a provider.

get_entropy() retrieves seeding material from the operating system. The seeding material will have at least *entropy* bytes of randomness and the output will have at least *min_len* and at most *max_len* bytes. The buffer address is stored in *pout and the buffer length is returned to the caller. On error, zero is returned.

cleanup_entropy() is used to clean up and free the buffer returned by **get_entropy()**. The entropy pointer returned by **get_entropy()** is passed in **buf** and its length in **len**.

get_nonce() retrieves a nonce using the passed *salt* parameter of length *salt_len* and operating system specific information. The *salt* should contain uniquely identifying information and this is included, in an unspecified manner, as part of the output. The output is stored in a buffer which contrains at least *min_len* and at most *max_len* bytes. The buffer address is stored in *pout and the buffer length returned to the caller. On error, zero is returned.

cleanup_nonce() is used to clean up and free the buffer returned by **get_nonce()**. The nonce pointer returned by **get_nonce()** is passed in **buf** and its length in **len**.

provider_register_child_cb() registers callbacks for being informed about the loading and unloading of providers in the application's library context. *handle* is this provider's handle and *cbdata* is this provider's data that will be passed back to the callbacks. It returns 1 on success or 0 otherwise. These callbacks may be called while holding locks in librarypto. In order to avoid deadlocks the callback implementation must not be long running and must not call other OpenSSL API functions or upcalls.

create_cb is a callback that will be called when a new provider is loaded into the application's library context. It is also called for any providers that are already loaded at the point that this callback is registered. The callback is passed the handle being used for the new provider being loadded and this provider's data in *cbdata*. It should return 1 on success or 0 on failure.

remove_cb is a callback that will be called when a new provider is unloaded from the application's library context. It is passed the handle being used for the provider being unloaded and this provider's data in cbdata. It should return 1 on success or 0 on failure.

global_props_cb is a callback that will be called when the global properties from the parent library context

3.0.2 2023-02-06 5

are changed. It should return 1 on success or 0 on failure.

provider_deregister_child_cb() unregisters callbacks previously registered via provider_register_child_cb(). If provider_register_child_cb() has been called then provider_deregister_child_cb() should be called at or before the point that this provider's teardown function is called.

provider name() returns a string giving the name of the provider identified by *handle*.

provider_get0_provider_ctx() returns the provider context that is associated with the provider identified by *prov*.

provider_get0_dispatch() gets the dispatch table registered by the provider identified by prov when it initialised.

provider_up_ref() increments the reference count on the provider *prov*. If *activate* is nonzero then the provider is also loaded if it is not already loaded. It returns 1 on success or 0 on failure.

provider_free() decrements the reference count on the provider *prov*. If *deactivate* is nonzero then the provider is also unloaded if it is not already loaded. It returns 1 on success or 0 on failure.

Provider functions

provider_teardown() is called when a provider is shut down and removed from the core's provider store. It must free the passed *provctx*.

provider_gettable_params() should return a constant array of descriptor **OSSL_PARAM**, for parameters that **provider_get_params()** can handle.

provider_get_params() should process the **OSSL_PARAM** array *params*, setting the values of the parameters it understands.

provider_query_operation() should return a constant **OSSL_ALGORITHM** that corresponds to the given *operation_id*. It should indicate if the core may store a reference to this array by setting**no_stor e* to 0 (core may store a reference) or 1 (core may not store a reference).

provider_unquery_operation() informs the provider that the result of a **provider_query_operation()** is no longer directly required and that the function pointers have been copied. The *operation_id* should match that passed to **provider_query_operation()** and *algs* should be its return value.

provider_get_reason_strings() should return a constant **OSSL_ITEM** array that provides reason strings for reason codes the provider may use when reporting errors using **core_put_error**().

The **provider_get_capabilities**() function should call the callback *cb* passing it a set of **OSSL_PARAM**s and the caller supplied argument *arg*. The **OSSL_PARAM**s should provide details about the capability with the name given in the *capability* argument relevant for the provider context *provctx*. If a provider supports multiple capabilities with the given name then it may call the callback multiple times (one for each capability). Capabilities can be useful for describing the services that a provider can offer. For further details see the "CAPABILITIES" section below. It should return 1 on success or 0 on error.

The **provider_self_test()** function should perform known answer tests on a subset of the algorithms that it uses, and may also verify the integrity of the provider module. It should return 1 on success or 0 on error. It will return 1 if this function is not used.

None of these functions are mandatory, but a provider is fairly useless without at least **provider_query_operation()**, and **provider_gettable_params()** is fairly useless if not accompanied by **provider_get_params()**.

Provider parameters

provider_get_params() can return the following provider parameters to the core:

"name" (OSSL_PROV_PARAM_NAME) <UTF8 string ptr>

This points to a string that should give a unique name for the provider.

3.0.2 2023-02-06 6

"version" (OSSL_PROV_PARAM_VERSION) <UTF8 string ptr>

This points to a string that is a version number associated with this provider. OpenSSL in-built providers use OPENSSL_VERSION_STR, but this may be different for any third party provider. This string is for informational purposes only.

"buildinfo" (OSSL_PROV_PARAM_BUILDINFO) <UTF8 string ptr>

This points to a string that is a build information associated with this provider. OpenSSL in-built providers use OPENSSL_FULL_VERSION_STR, but this may be different for any third party provider.

"status" (OSSL_PROV_PARAM_STATUS) <unsigned integer>

This returns 0 if the provider has entered an error state, otherwise it returns 1.

provider_gettable_params() should return the above parameters.

Core parameters

core_get_params() can retrieve the following core parameters for each provider:

"openssl-version" (OSSL_PROV_PARAM_CORE_VERSION) <UTF8 string ptr>

This points to the OpenSSL libraries' full version string, i.e. the string expanded from the macro OPENSSL_VERSION_STR.

"provider-name" (OSSL_PROV_PARAM_CORE_PROV_NAME) <UTF8 string ptr>

This points to the OpenSSL libraries' idea of what the calling provider is named.

"module-filename" (OSSL_PROV_PARAM_CORE_MODULE_FILENAME) < UTF8 string ptr>

This points to a string containing the full filename of the providers module file.

Additionally, provider specific configuration parameters from the config file are available, in dotted name form. The dotted name form is a concatenation of section names and final config command name separated by periods.

For example, let's say we have the following config example:

```
config diagnostics = 1
 openssl_conf = openssl_init
 [openssl init]
 providers = providers_sect
 [providers sect]
 foo = foo sect
 [foo sect]
 activate = 1
 data1 = 2
 data2 = str
 more = foo_more
 [foo_more]
 data3 = foo,bar
The provider will have these additional parameters available:
"activate"
   pointing at the string "1"
"data1"
   pointing at the string "2"
   pointing at the string "str"
```

"more.data3"

pointing at the string "foo,bar"

For more information on handling parameters, see OSSL_PARAM(3) as OSSL_PARAM_int (3).

CAPABILITIES

Capabilities describe some of the services that a provider can offer. Applications can query the capabilities to discover those services.

"TLS-GROUP" Capability

The "TLS-GROUP" capability can be queried by libssl to discover the list of TLS groups that a provider can support. Each group supported can be used for *key exchange* (KEX) or *key encapsulation method* (KEM) during a TLS handshake. TLS clients can advertise the list of TLS groups they support in the supported_groups extension, and TLS servers can select a group from the offered list that they also support. In this way a provider can add to the list of groups that libssl already supports with additional ones.

Each TLS group that a provider supports should be described via the callback passed in through the provider_get_capabilities function. Each group should have the following details supplied (all are mandatory, except OSSL_CAPABILITY_TLS_GROUP_IS_KEM):

"tls-group-name" (OSSL_CAPABILITY_TLS_GROUP_NAME) <UTF8 string>

The name of the group as given in the IANA TLS Supported Groups registry https://www.iana.org/assignments/tls-parameters/tls-parameters.xhtml#tls-parameters-8.

"tls-group-name-internal" (OSSL_CAPABILITY_TLS_GROUP_NAME_INTERNAL) <UTF8 string>
The name of the group as known by the provider. This could be the same as the "tls-group-name", but does not have to be.

"tls-group-id" (OSSL_CAPABILITY_TLS_GROUP_ID) <unsigned integer>

The TLS group id value as given in the IANA TLS Supported Groups registry.

"tls-group-alg" (OSSL_CAPABILITY_TLS_GROUP_ALG) <UTF8 string>

The name of a Key Management algorithm that the provider offers and that should be used with this group. Keys created should be able to support key exchange or key encapsulation method (KEM), as implied by the optional OSSL_CAPABILITY_TLS_GROUP_IS_KEM flag. The algorithm must support key and parameter generation as well as the key/parameter generation parameter, OSSL_PKEY_PARAM_GROUP_NAME. The group name given via "tls-group-name-internal" above will be passed via OSSL_PKEY_PARAM_GROUP_NAME when libssl wishes to generate keys/parameters.

"tls-group-sec-bits" (OSSL_CAPABILITY_TLS_GROUP_SECURITY_BITS) <unsigned integer>

The number of bits of security offered by keys in this group. The number of bits should be comparable with the ones given in table 2 and 3 of the NIST SP800–57 document.

"tls-group-is-kem" (OSSL_CAPABILITY_TLS_GROUP_IS_KEM) <unsigned integer>

Boolean flag to describe if the group should be used in *key exchange* (KEX) mode (0, default) or in *key encapsulation method* (KEM) mode (1).

This parameter is optional: if not specified, KEX mode is assumed as the default mode for the group.

In KEX mode, in a typical Diffie-Hellman fashion, both sides execute *keygen* then *derive* against the peer public key. To operate in KEX mode, the group implementation must support the provider functions as described in **provider-keyexch** (7).

In KEM mode, the client executes *keygen* and sends its public key, the server executes *encapsulate* using the client's public key and sends back the resulting *ciphertext*, finally the client executes *decapsulate* to retrieve the same *shared secret* generated by the server's *encapsulate*. To operate in KEM mode, the group implementation must support the provider functions as described in **provider–kem** (7).

Both in KEX and KEM mode, the resulting *shared secret* is then used according to the protocol specification.

```
"tls-min-tls" (OSSL_CAPABILITY_TLS_GROUP_MIN_TLS) <integer>
"tls-max-tls" (OSSL_CAPABILITY_TLS_GROUP_MAX_TLS) <integer>
"tls-min-dtls" (OSSL_CAPABILITY_TLS_GROUP_MIN_DTLS) <integer>
"tls-max-dtls" (OSSL_CAPABILITY_TLS_GROUP_MAX_DTLS) <integer>
```

These parameters can be used to describe the minimum and maximum TLS and DTLS versions supported by the group. The values equate to the on-the-wire encoding of the various TLS versions. For example TLSv1.3 is 0x0304 (772 decimal), and TLSv1.2 is 0x0303 (771 decimal). A 0 indicates that there is no defined minimum or maximum. A -1 indicates that the group should not be used in that protocol.

EXAMPLES

This is an example of a simple provider made available as a dynamically loadable module. It implements the fictitious algorithm FOO for the fictitious operation BAR.

```
#include <malloc.h>
#include <openssl/core.h>
#include <openssl/core dispatch.h>
/* Errors used in this provider */
#define E MALLOC
static const OSSL_ITEM reasons[] = {
    { E_MALLOC, "memory allocation failure" }.
    { 0, NULL } /* Termination */
};
 * To ensure we get the function signature right, forward declare
 * them using function types provided by openssl/core_dispatch.h
* /
OSSL_FUNC_bar_newctx_fn foo_newctx;
OSSL_FUNC_bar_freectx_fn foo_freectx;
OSSL_FUNC_bar_init_fn foo_init;
OSSL_FUNC_bar_update_fn foo_update;
OSSL_FUNC_bar_final_fn foo_final;
OSSL_FUNC_provider_query_operation_fn p_query;
OSSL FUNC provider get reason strings fn p reasons;
OSSL_FUNC_provider_teardown_fn p_teardown;
OSSL_provider_init_fn OSSL_provider_init;
OSSL_FUNC_core_put_error *c_put_error = NULL;
/* Provider context */
struct prov_ctx_st {
   OSSL_CORE_HANDLE *handle;
}
/* operation context for the algorithm FOO */
struct foo_ctx_st {
    struct prov_ctx_st *provctx;
    int b;
};
static void *foo_newctx(void *provctx)
```

```
{
   struct foo_ctx_st *fooctx = malloc(sizeof(*fooctx));
   if (fooctx != NULL)
        fooctx->provctx = provctx;
   else
        c_put_error(provctx->handle, E_MALLOC, __FILE__, __LINE__);
   return fooctx;
}
static void foo_freectx(void *fooctx)
   free(fooctx);
}
static int foo init(void *vfooctx)
   struct foo_ctx_st *fooctx = vfooctx;
   fooctx->b = 0x33;
}
static int foo_update(void *vfooctx, unsigned char *in, size_t inl)
    struct foo_ctx_st *fooctx = vfooctx;
    /* did you expect something serious? */
   if (inl == 0)
       return 1;
    for (; inl-- > 0; in++)
        *in ^= fooctx->b;
   return 1;
}
static int foo final(void *vfooctx)
   struct foo_ctx_st *fooctx = vfooctx;
   fooctx->b = 0x66;
}
static const OSSL_DISPATCH foo_fns[] = {
    { OSSL_FUNC_BAR_NEWCTX, (void (*)(void))foo_newctx },
    { OSSL_FUNC_BAR_FREECTX, (void (*)(void))foo_freectx },
    { OSSL FUNC BAR INIT, (void (*)(void))foo init },
    { OSSL_FUNC_BAR_UPDATE, (void (*)(void))foo_update },
    { OSSL_FUNC_BAR_FINAL, (void (*)(void))foo_final },
    { 0, NULL }
};
static const OSSL_ALGORITHM bars[] = {
    { "FOO", "provider=chumbawamba", foo_fns },
    { NULL, NULL, NULL }
};
```

```
static const OSSL_ALGORITHM *p_query(void *provctx, int operation_id,
                                     int *no store)
{
   switch (operation id) {
   case OSSL_OP_BAR:
       return bars;
   return NULL;
}
static const OSSL_ITEM *p_reasons(void *provctx)
   return reasons;
}
static void p_teardown(void *provctx)
   free(provctx);
static const OSSL_DISPATCH prov_fns[] = {
    { OSSL_FUNC_PROVIDER_TEARDOWN, (void (*)(void))p_teardown },
    { OSSL_FUNC_PROVIDER_QUERY_OPERATION, (void (*)(void))p_query },
    { OSSL_FUNC_PROVIDER_GET_REASON_STRINGS, (void (*)(void))p_reasons },
    { 0, NULL }
};
int OSSL_provider_init(const OSSL_CORE_HANDLE *handle,
                       const OSSL_DISPATCH *in,
                       const OSSL DISPATCH **out,
                       void **provctx)
{
    struct prov ctx st *pctx = NULL;
    for (; in->function_id != 0; in++)
        switch (in->function_id) {
        case OSSL_FUNC_CORE_PUT_ERROR:
            c_put_error = OSSL_FUNC_core_put_error(in);
            break;
        }
    *out = prov_fns;
    if ((pctx = malloc(sizeof(*pctx))) == NULL) {
         * ALEA IACTA EST, if the core retrieves the reason table
         * regardless, that string will be displayed, otherwise not.
        c_put_error(handle, E_MALLOC, __FILE__, __LINE__);
        return 0;
    }
   pctx->handle = handle;
   return 1;
```

```
}
This relies on a few things existing in openssl/core_dispatch.h:
 #define OSSL_OP_BAR
                                 4711
 #define OSSL_FUNC_BAR_NEWCTX
 typedef void *(OSSL_FUNC_bar_newctx_fn)(void *provctx);
 static ossl_inline OSSL_FUNC_bar_newctx(const OSSL_DISPATCH *opf)
 { return (OSSL_FUNC_bar_newctx_fn *)opf->function; }
 #define OSSL_FUNC_BAR_FREECTX
 typedef void (OSSL_FUNC_bar_freectx_fn)(void *ctx);
 static ossl_inline OSSL_FUNC_bar_newctx(const OSSL_DISPATCH *opf)
 { return (OSSL_FUNC_bar_freectx_fn *)opf->function; }
 #define OSSL FUNC BAR INIT
 typedef void *(OSSL_FUNC_bar_init_fn)(void *ctx);
 static ossl_inline OSSL_FUNC_bar_init(const OSSL_DISPATCH *opf)
 { return (OSSL_FUNC_bar_init_fn *)opf->function; }
 #define OSSL_FUNC_BAR_UPDATE
 typedef void *(OSSL_FUNC_bar_update_fn)(void *ctx,
                                        unsigned char *in, size_t inl);
 static ossl_inline OSSL_FUNC_bar_update(const OSSL_DISPATCH *opf)
 { return (OSSL_FUNC_bar_update_fn *)opf->function; }
 #define OSSL FUNC BAR FINAL
 typedef void *(OSSL_FUNC_bar_final_fn)(void *ctx);
 static ossl_inline OSSL_FUNC_bar_final(const OSSL_DISPATCH *opf)
```

SEE ALSO

provider (7)

HISTORY

The concept of providers and everything surrounding them was introduced in OpenSSL 3.0.

COPYRIGHT

Copyright 2019–2021 The OpenSSL Project Authors. All Rights Reserved.

{ return (OSSL_FUNC_bar_final_fn *)opf->function; }

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at https://www.openssl.org/source/license.html>.