NAME

ungetwc - push back a wide character onto a FILE stream

LIBRARY

Standard C library (libc, -lc)

SYNOPSIS

#include <wchar.h>

wint_t ungetwc(wint_t wc, FILE *stream);

DESCRIPTION

The **ungetwc**() function is the wide-character equivalent of the **ungetc**(3) function. It pushes back a wide character onto *stream* and returns it.

If wc is **WEOF**, it returns **WEOF**. If wc is an in valid wide character, it sets errno to **EILSEQ** and returns **WEOF**.

If wc is a valid wide character, it is pushed back onto the stream and thus becomes available for future wide-character read operations. The file-position indicator is decremented by one or more. The end-of-file indicator is cleared. The backing storage of the file is not affected.

Note: wc need not be the last wide-character read from the stream; it can be any other valid wide character.

If the implementation supports multiple push-back operations in a row, the pushed-back wide characters will be read in reverse order; however, only one level of push-back is guaranteed.

RETURN VALUE

The **ungetwc**() function returns wc when successful, or **WEOF** upon failure.

ATTRIBUTES

For an explanation of the terms used in this section, see **attributes**(7).

Interface	Attribute	Value
ungetwc()	Thread safety	MT-Safe

STANDARDS

POSIX.1-2001, POSIX.1-2008, C99.

NOTES

The behavior of **ungetwc**() depends on the **LC_CTYPE** category of the current locale.

SEE ALSO

fgetwc(3)