NAME

pcap_findalldevs, pcap_freealldevs - get a list of capture devices, and free that list

SYNOPSIS

#include <pcap/pcap.h>

char errbuf[PCAP ERRBUF SIZE];

int pcap_findalldevs(pcap_if_t **alldevsp, char *errbuf);
void pcap_freealldevs(pcap_if_t *alldevs);

DESCRIPTION

pcap_findalldevs() constructs a list of network devices that can be opened with **pcap_create**(3PCAP) and **pcap_activate**(3PCAP) or with **pcap_open_live**(3PCAP). (Note that there may be network devices that cannot be opened by the process calling **pcap_findalldevs**(), because, for example, that process does not have sufficient privileges to open them for capturing; if so, those devices will not appear on the list.) If **pcap_findalldevs**() succeeds, the pointer pointed to by *alldevsp* is set to point to the first element of the list, or to **NULL** if no devices were found (this is considered success). Each element of the list is of type **pcap_if_t**, and has the following members:

next if not **NULL**, a pointer to the next element in the list; **NULL** for the last element of the list

name a pointer to a string giving a name for the device to pass to **pcap_open_live**()

description

if not NULL, a pointer to a string giving a human-readable description of the device

addresses

a pointer to the first element of a list of network addresses for the device, or **NULL** if the device has no addresses

flags device flags:

PCAP_IF_LOOPBACK

set if the device is a loopback interface

PCAP IF UP

set if the device is up

PCAP IF RUNNING

set if the device is running

PCAP_IF_WIRELESS

set if the device is a wireless interface; this includes IrDA as well as radio-based networks such as IEEE 802.15.4 and IEEE 802.11, so it doesn't just mean Wi-Fi

PCAP IF CONNECTION STATUS

a bitmask for an indication of whether the adapter is connected or not; for wireless interfaces, "connected" means "associated with a network"

The possible values for the connection status bits are:

PCAP_IF_CONNECTION_STATUS_UNKNOWN

it's unknown whether the adapter is connected or not

PCAP IF CONNECTION STATUS CONNECTED

the adapter is connected

PCAP_IF_CONNECTION_STATUS_DISCONNECTED

the adapter is disconnected

PCAP IF CONNECTION STATUS NOT APPLICABLE

the notion of "connected" and "disconnected" don't apply to this interface; for example, it doesn't apply to a loopback device

Each element of the list of addresses is of type **pcap_addr_t**, and has the following members:

next if not **NULL**, a pointer to the next element in the list; **NULL** for the last element of the list

addr a pointer to a struct sockaddr containing an address

netmask

if not **NULL**, a pointer to a **struct sockaddr** that contains the netmask corresponding to the address pointed to by **addr**

broadaddr

if not **NULL**, a pointer to a **struct sockaddr** that contains the broadcast address corresponding to the address pointed to by **addr**; may be null if the device doesn't support broadcasts

dstaddr

if not **NULL**, a pointer to a **struct sockaddr** that contains the destination address corresponding to the address pointed to by **addr**; may be null if the device isn't a point-to-point interface

Note that the addresses in the list of addresses might be IPv4 addresses, IPv6 addresses, or some other type of addresses, so you must check the **sa_family** member of the **struct sockaddr** before interpreting the contents of the address; do not assume that the addresses are all IPv4 addresses, or even all IPv4 or IPv6 addresses. IPv4 addresses have the value **AF_INET**, IPv6 addresses have the value **AF_INET6** (which older operating systems that don't support IPv6 might not define), and other addresses have other values. Whether other addresses are returned, and what types they might have is platform-dependent. For IPv4 addresses, the **struct sockaddr** pointer can be interpreted as if it pointed to a **struct sockaddr_in**; for IPv6 addresses, it can be interpreted as if it pointed to a **struct sockaddr_in6**.

The list of devices must be freed with pcap_freealldevs(3PCAP), which frees the list pointed to by alldevs.

RETURN VALUE

pcap_findalldevs() returns **0** on success and **PCAP_ERROR** on failure; as indicated, finding no devices is considered success, rather than failure, so 0 will be returned in that case. If **PCAP_ERROR** is returned, *errbuf* is filled in with an appropriate error message. *errbuf* is assumed to be able to hold at least **PCAP_ERRBUF_SIZE** chars.

BACKWARD COMPATIBILITY

The PCAP_IF_UP and PCAP_IF_RUNNING constants became available in libpcap release 1.6.1. The PCAP_IF_WIRELESS, PCAP_IF_CONNECTION_STATUS, PCAP_IF_CONNECTION_STATUS_UNKNOWN, PCAP_IF_CONNECTION_STATUS_CONNECTED, PCAP_IF_CONNECTION_STATUS_DISCONNECTED, and PCAP_IF_CONNECTION_STATUS_NOT_APPLICABLE constants became available in libpcap release 1.9.0.

SEE ALSO

pcap(3PCAP)