NAME

bindresvport - bind a socket to a privileged IP port

LIBRARY

Standard C library (libc, -lc)

SYNOPSIS

#include <sys/types.h>
#include <netinet/in.h>

int bindresvport(int sockfd, struct sockaddr_in *sin);

DESCRIPTION

bindresvport() is used to bind the socket referred to by the file descriptor *sockfd* to a privileged anonymous IP port, that is, a port number arbitrarily selected from the range 512 to 1023.

If the **bind**(2) performed by **bindresvport**() is successful, and *sin* is not NULL, then *sin*—>*sin_port* returns the port number actually allocated.

sin can be NULL, in which case $sin->sin_family$ is implicitly taken to be **AF_INET**. However, in this case, **bindresvport**() has no way to return the port number actually allocated. (This information can later be obtained using **getsockname**(2).)

RETURN VALUE

bindresvport() returns 0 on success; otherwise –1 is returned and *errno* is set to indicate the error.

ERRORS

bindresvport() can fail for any of the same reasons as **bind**(2). In addition, the following errors may occur:

EACCES

The calling process was not privileged (on Linux: the calling process did not have the **CAP_NET_BIND_SERVICE** capability in the user namespace governing its network namespace).

EADDRINUSE

All privileged ports are in use.

EAFNOSUPPORT (**EPFNOSUPPORT** in glibc 2.7 and earlier)

sin is not NULL and *sin*->*sin_family* is not **AF_INET**.

ATTRIBUTES

For an explanation of the terms used in this section, see **attributes**(7).

Interface	Attribute	Value
bindresvport()	Thread safety	glibc >= 2.17: MT-Safe; glibc < 2.17: MT-Unsafe

The **bindresvport**() function uses a static variable that was not protected by a lock before glibc 2.17, rendering the function MT-Unsafe.

STANDARDS

Not in POSIX.1. Present on the BSDs, Solaris, and many other systems.

NOTES

Unlike some **bindresvport**() implementations, the glibc implementation ignores any value that the caller supplies in $sin->sin_port$.

SEE ALSO

bind(2), getsockname(2)