NAME

iptunnel - Create and manage IP tunnels

SYNOPSIS

```
iptunnel { add | change | del | show } [ NAME ]
  [ mode { ipip | gre | sit } ] [ remote ADDR ] [ local ADDR ]
  [ [i|o]seq ] [ [i|o]key KEY ] [ [i|o]csum ]
  [ ttl TTL ] [ tos TOS ] [ nopmtudisc ] [ dev PHYS_DEV ]

iptunnel -V | ---version

Where: NAME := STRING
    ADDR := { IP_ADDRESS | any }
    TOS := { NUMBER | inherit }
    TTL := { 1..255 | inherit }
    KEY := { DOTTED_QUAD | NUMBER }
```

DESCRIPTION

iptunnel can be used to add, change, delete and show IP tunnels on the machine.

OPTIONS

help Show the help text.

show List existing IP tunnels.

{ add | change | del } [NAME]

Specify an action (add, change or delete an IP tunnel) to be executed by **iptunnel** on the tunnel named **NAME**, which must be a string. You must specify one action.

mode PROTOCOL

Specify the **PROTOCOL** to be used for the IP tunnel. It can be **ipip** for TCP/IP, **gre** for Cisco GRE tunnel (RFCs 1701 and 1702), or **sit** for IPv6-in-IPv4 tunneling.

remote ADDR

Set the remote (i.e., destination) address of the tunnel. **ADDR** must be an IP address or the w ord **any**.

local ADDR

Set the local (i.e., source) address of the tunnel. **ADDR** must be an IP address or the word **any**.

iseq Require that all incoming packets are serialized. Only applicable for **GRE** tunnels.

oseq Enable serialization (sequencing) for all outgoing packets. Only applicable for **GRE** tunnels.

ikey KEY

Specify the input key for the Cisco GRE tunnel. **KEY** must be either in dotted quad (dotted decimal) or a number. Only applicable for**GRE** tunnels.

okey KEY

Same as ikey, but set the output key instead. Only applicable for GRE tunnels.

icsum Require that all incoming packets have the correct checksum. Only applicable for GRE tunnels.

ocsum Calculate checksums for all outgoing packets. Only applicable forGRE tunnels.

ttl TTL

Specify the **Time-To-Live** value for the IP tunnel. **TTL** must be a value between **1** and **255**, or the word **inherit**, which causes the field to be copied from the original IP header.

tos TOS

Specify the **Type-Of-Service** value for the IP tunnel. **T OS** must be a value between **1** and **255**, or the word **inherit**, which causes the field to be copied from the original IP header.

nopmtudisc

Disable **Path MTU Discovery** on this tunnel. Note that a fixed **ttl** is incompatible with this option.

dev PHYS DEV

Bind the tunnel to the device **PHYS_DEV**.

HOMEPAGE

https://sourceforge.net/projects/net-tools/

AUTHORS

This manpage was written by Sergio Durigan Junior <sergiodj (at) sergiodj (dot) net>. A few parts were inspired by **ip-tunnel(1)**'s manpage.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU General Public License, Version 2 or any later version published by the Free Software Foundation.