Win::Hivex(3pm)

NAME

Win::Hivex - Perl bindings for reading and writing Windows Registry hive files

SYNOPSIS

```
use Win::Hivex;

$h = Win::Hivex->open ('SOFTWARE');
$root_node = $h->root ();
print $h->node_name ($root_node);
```

DESCRIPTION

The Win::Hivex module provides a Perl XS binding to the **hivex**(3) API for reading and writing Windows Registry binary hive files.

ERRORS

All errors turn into calls to croak (see Carp (3)).

METHODS

open

Open a Windows Registry binary hive file.

The verbose and debug flags enable different levels of debugging messages.

The write flag is required if you will be modifying the hive file (see "WRITING TO HIVE FILES" in **hivex** (3)).

This function returns a hive handle. The hive handle is closed automatically when its reference count drops to 0.

```
root
    $node = $h->root ()
```

Return root node of the hive. All valid hives must contain a root node.

This returns a node handle.

```
last_modified
```

```
$int64 = $h->last_modified ()
```

Return the modification time from the header of the hive.

The returned value is a Windows filetime. To convert this to a Unix time_t see: <http://stackoverflow.com/questions/6161776/convert-windows-filetime-to-second-in-unix-linux/6161842#6161842

```
node_name
```

```
$string = $h->node_name ($node)
```

Return the name of the node.

Note that the name of the root node is a dummy, such as \$\$\$PROTO.HIV (other names are possible: it seems to depend on the tool or program that created the hive in the first place). You can only know the "real" name of the root node by knowing which registry file this hive originally comes from, which is knowledge that is outside the scope of this library.

The name is recoded to UTF-8 and may contain embedded NUL characters.

```
node_name_len
   $size = $h->node_name_len ($node)
```

Return the length of the node name as produced by node_name.

This returns a size.

node_timestamp

```
$int64 = $h->node_timestamp ($node)
```

Return the modification time of the node.

node children

```
@nodes = $h->node_children ($node)
```

Return an array of nodes which are the subkeys (children) of node.

This returns a list of node handles.

node_get_child

```
$node = $h->node_get_child ($node, $name)
```

Return the child of node with the name name, if it exists.

The name is matched case insensitively.

This returns a node handle, or undef if the node was not found.

node_nr_children

```
$size = $h->node_nr_children ($node)
```

Return the number of nodes as produced by node_children.

This returns a size.

node parent

```
$node = $h->node_parent ($node)
```

Return the parent of node.

The parent pointer of the root node in registry files that we have examined seems to be invalid, and so this function will return an error if called on the root node.

This returns a node handle.

node_values

```
@values = $h->node_values ($node)
```

Return the array of (key, value) pairs attached to this node.

This returns a list of value handles.

node get value

```
$value = $h->node_get_value ($node, $key)
```

Return the value attached to this node which has the name key, if it exists.

The key name is matched case insensitively.

Note that to get the default key, you should pass the empty string " " here. The default key is often written "@", but inside hives that has no meaning and won't give you the default key.

This returns a value handle.

node_nr_values

```
$size = $h->node_nr_values ($node)
```

Return the number of (key, value) pairs attached to this node as produced by node_values.

This returns a size.

```
value_key_len
$size = $h->value_key_len ($val)
```

Return the length of the key (name) of a (key, value) pair as produced by value_key. The length can legitimately be 0, so errno is the necessary mechanism to check for errors.

In the context of Windows Registries, a zero-length name means that this value is the default key for this node in the tree. This is usually written as "@".

The key is recoded to UTF-8 and may contain embedded NUL characters.

This returns a size.

value_key

```
$string = $h->value_key ($val)
```

Return the key (name) of a (key, value) pair. The name is reencoded as UTF-8 and returned as a string.

The string should be freed by the caller when it is no longer needed.

Note that this function can return a zero-length string. In the context of Windows Registries, this means that this value is the default key for this node in the tree. This is usually written as "@".

value_type

```
($type, $len) = $h->value_type ($val)
```

Return the data length and data type of the value in this (key, value) pair. See alsovalue_value which returns all this information, and the value itself. Also, value_* functions below which can be used to return the value in a more useful form when you know the type in advance.

node_struct_length

```
$size = $h->node_struct_length ($node)
```

Return the length of the node data structure.

This returns a size.

value_struct_length

```
$size = $h->value_struct_length ($val)
```

Return the length of the value data structure.

This returns a size.

```
value_data_cell_offset
```

```
($len, $value) = $h->value_data_cell_offset ($val)
```

Return the offset and length of the value's data cell.

The data cell is a registry structure that contains the length (a 4 byte, little endian integer) followed by the data.

If the length of the value is less than or equal to 4 bytes then the offset and length returned by this function is zero as the data is inlined in the value.

Returns 0 and sets errno on error.

value_value

```
($type, $data) = $h->value_value ($val)
```

Return the value of this (key, value) pair. The value should be interpreted according to its type (see hive_type).

value_string

```
$string = $h->value_string ($val)
```

If this value is a string, return the string reencoded as UTF-8 (as a C string). This only works for

values which have type hive_t_string, hive_t_expand_string or hive_t_link.

value_multiple_strings

```
@strings = $h->value_multiple_strings ($val)
```

If this value is a multiple-string, return the strings reencoded as UTF-8 (in C, as a NULL-terminated array of C strings, in other language bindings, as a list of strings). This only works for values which have type hive_t_multiple_strings.

value dword

```
$int32 = $h->value_dword ($val)
```

If this value is a DWORD (Windows int32), return it. This only works for values which have type hive_t_dword or hive_t_dword_be.

value qword

```
$int64 = $h->value_qword ($val)
```

If this value is a QWORD (Windows int64), return it. This only works for values which have type hive_t_qword.

commit

```
$h->commit ([$filename|undef])
```

Commit (write) any changes which have been made.

filename is the new file to write. If filename is null/undefined then we overwrite the original file (ie. the file name that was passed to open).

Note this does not close the hive handle. You can perform further operations on the hive after committing, including making more modifications. If you no longer wish to use the hive, then you should close the handle after committing.

node add child

```
$node = $h->node_add_child ($parent, $name)
```

Add a new child node named name to the existing node parent. The new child initially has no subnodes and contains no keys or values. The sk-record (security descriptor) is inherited from the parent.

The parent must not have an existing child called name, so if you want to overwrite an existing child, call node_delete_child first.

This returns a node handle.

node_delete_child

```
$h->node_delete_child ($node)
```

Delete the node node. All values at the node and all subnodes are deleted (recursively). Thenode handle and the handles of all subnodes become invalid. You cannot delete the root node.

node_set_values

```
$h->node_set_values ($node, \@values)
```

This call can be used to set all the (key, value) pairs stored in node.

node is the node to modify.

@values is an array of (keys, value) pairs. Each element should be a hashref containing key, t (type) and data.

Any existing values stored at the node are discarded, and their value handles become invalid. Thus you can remove all values stored at node by passing @values = [].

Win::Hivex(3pm)

```
node_set_value
```

```
$h->node_set_value ($node, $val)
```

This call can be used to replace a single (key, value) pair stored in node. If the key does not already exist, then a new key is added. Key matching is case insensitive.

node is the node to modify.

COPYRIGHT

Copyright (C) 2009–2021 Red Hat Inc.

LICENSE

Please see the file COPYING.LIB for the full license.

SEE ALSO

hivex (3), hivexsh (1), http://libguestfs.org, Sys::Guestfs (3).