Sys::Virt::StoragePool(3pm)

NAME

Sys::Virt::StoragePool - Represent & manage a libvirt storage pool

DESCRIPTION

The Sys::Virt::StoragePool module represents a storage pool managed by libvirt. There are a variety of storage pool implementations for LVM, Local directories/filesystems, network filesystems, disk partitioning, iSCSI, and SCSI.

METHODS

my \$uuid = \$pool->get_uuid()

Returns a 16 byte long string containing the raw globally unique identifier (UUID) for the storage pool.

my \$uuid = \$pool->get_uuid_string()

my \$name = \$pool->get_name()

Returns a string with a locally unique name of the storage pool

\$pool->is_active()

Returns a true value if the storage pool is currently running

\$pool->is_persistent()

Returns a true value if the storage pool has a persistent configuration file defined

my \$xml = \$pool->get_xml_description()

Returns an XML document containing a complete description of the storage pool's configuration

\$pool->create()

Start a storage pool whose configuration was previously defined using the define_storage_pool method in Sys::Virt.

\$pool->undefine()

Remove the configuration associated with a storage pool previously defined with the define_storage poolmethod in Sys::V irt. If the storage pool is running, you probably want to use the destroy method instead.

\$pool->destroy()

Immediately stop the storage pool.

\$flag = \$pool->get_autostart();

Return a true value if the storage pool is configured to automatically start upon boot. Return false, otherwise

\$pool->set_autostart(\$flag)

Set the state of the autostart flag, which determines whether the storage pool will automatically start upon boot of the host OS

\$pool->refresh([\$flags]);

Refresh the storage pool state. Typically this will rescan the list of storage volumes. The \$flags parameter is currently unused and if omitted defaults to zero.

\$pool->build([\$flags]);

Construct the storage pool if it does not exist. As an example, for a disk based storage pool this would ensure a partition table exists. The\$flags parameter allo ws control over the build operation and if omitted defaults to zero.

\$pool->delete([\$flags]);

Delete the storage pool. The \$flags parameter allows the data to be optionally wiped during delete and if omitted defaults to zero.

\$info = \$pool->get_info()

Retrieve information about the current storage pool state. The returned hash reference has the following keys

Sys::Virt::StoragePool(3pm)

state

The current status of the storage pool. See constants later.

capacity

The total logical size of the storage pool

allocation

The current physical allocation of the storage pool

available

The available space for creation of new volumes. This may be less than the difference between capacity & allocation if there are sizing / metadata constraints for volumes

my \$nnames = \$pool->num_of_storage_volumes()

Return the number of running volumes in this storage pool. The value can be used as the maxnames parameter to list_storage_vol_names.

my @volNames = \$pool->list_storage_vol_names(\$maxnames)

Return a list of all volume names in this storage pool. The names can be used with the get_volume_by_name method.

my @vols = \$pool->list_volumes()

Return a list of all volumes in the storage pool. The elements in the returned list are instances of the $Sys::Virt::StorageVol \ class.$ This method requires O(n) RPC calls, so the $list_all_volumes$ method is recommended as a more efficient alternative.

my @volumes = \$pool->list_all_volumes(\$flags)

Return a list of all storage volumes associated with this pool. The elements in the returned list are instances of the Sys::Virt::StorageVol class. The \$flags parameter can be used to filter the list of return storage volumes.

my \$vol = \$pool->get_volume_by_name(\$name)

Return the volume with a name of \$name. The returned object is an instance of the Sys::Virt::StorageVol class.

my \$vol = \$pool->create_volume(\$xml)

Create a new volume based on the XML description passed into the \$xml parameter. The returned object is an instance of the Sys::Virt::StorageVol class. If the optional clonevol is provided, data will be copied from that source volume

my \$vol = \$pool->clone volume(\$xml, \$clonevol);

Create a new volume based on the XML description passed into the \$xml parameter. The returned object is an instance of the Sys::Virt::StorageVol class. The new volume will be populated with data from the specified clone source volume.

CONSTANTS

The following sets of constants may be useful in dealing with some of the methods in this package

STORAGE POOL DEFINE

The following constants can be used to control the behaviour of storage pool define operations

Sys::Virt::StoragePool::DEFINE_VALIDATE

Validate the XML document against the XML schema

POOL STATES

The following constants are useful for interpreting the state key value in the hash returned by get info

Sys::Virt::StoragePool::STATE_INACTIVE

The storage pool is not currently active

Sys::Virt::StoragePool::STATE_BUILDING

The storage pool is still being constructed and is not ready for use yet.

Sys::Virt::StoragePool(3pm)

Sys::Virt::StoragePool::STATE_RUNNING

The storage pool is running and can be queried for volumes

Sys::Virt::StoragePool::STATE DEGRADED

The storage pool is running, but its operation is degraded due to a failure.

Sys::Virt::StoragePool::STATE_INACCESSIBLE
The storage pool is not currently accessible

DELETION MODES

Sys::Virt::StoragePool::DELETE_NORMAL

Delete the pool without any attempt to scrub data

Sys::Virt::StoragePool::DELETE_ZEROED

Fill the allocated storage with zeros when deleting

BUILD MODES

Sys::Virt::StoragePool::BUILD NEW

Construct a new storage pool from constituent bits

Sys::Virt::StoragePool::BUILD_RESIZE

Resize an existing built storage pool preserving data where appropriate

Sys::Virt::StoragePool::BUILD_REPAIR

Repair an existing storage pool operating in degraded mode

Sys::Virt::StoragePool::BUILD_NO_OVERWRITE

Do not overwrite existing storage pool data

Sys::Virt::StoragePool::BUILD_OVERWRITE

Overwrite existing storage pool data

CREATE MODES

When creating a storage pool it can be built at the same time. The following values are therefore close to their BUILD counterparts.

Sys::Virt::StoragePool::CREATE_NORMAL

Just create the storage pool without building it.

Sys::Virt::StoragePool::CREATE_WITH_BUILD

When creating new storage pool also perform pool build without any flags.

Sys::Virt::StoragePool::CREATE WITH BUILD OVERWRITE

Create the pool and perform pool build using the BUILD_OVERWRITE flag. This is mutually exclusive to CREATE_WITH_BUILD_NO_OVERWRITE.

Sys::Virt::StoragePool::CREATE_WITH_BUILD_NO_OVERWRITE

Create the pool and perform pool build using the BUILD_NO_OVERWRITE flag. This is mutually exclusive to CREATE_WITH_BUILD_OVERWRITE.

XML DOCUMENTS

The following constants are useful when requesting XML for storage pools

Sys::Virt::StoragePool::XML_INACTIVE

Return XML describing the inactive state of the storage pool.

LIST FILTERING

The following constants are used to filter object lists

Sys::Virt::StoragePool::LIST_ACTIVE

Include storage pools which are active

Sys::Virt::StoragePool::LIST INACTIVE

Include storage pools which are inactive

- Sys::Virt::StoragePool::LIST_AUTOSTART
 - Include storage pools which are marked for autostart
- Sys::Virt::StoragePool::LIST_NO_AUTOSTART
 Include storage pools which are not marked for autostart
- Sys::Virt::StoragePool::LIST_PERSISTENT Include storage pools which are persistent
- Sys::Virt::StoragePool::LIST_TRANSIENT Include storage pools which are transient
- Sys::Virt::StoragePool::LIST_DIR
 Include directory storage pools
- Sys::Virt::StoragePool::LIST_DISK Include disk storage pools
- Sys::Virt::StoragePool::LIST_FS
 Include filesystem storage pools
- Sys::Virt::StoragePool::LIST_ISCSI Include iSCSI storage pools
- Sys::Virt::StoragePool::LIST_LOGICAL Include LVM storage pools
- Sys::Virt::StoragePool::LIST_MPATH Include multipath storage pools
- Sys::Virt::StoragePool::LIST_NETFS
 Include network filesystem storage pools
- Sys::Virt::StoragePool::LIST_RBD Include RBD storage pools
- Sys::Virt::StoragePool::LIST_SCSI Include SCSI storage pools
- Sys::Virt::StoragePool::LIST_SHEEPDOG Include sheepdog storage pools
- Sys::Virt::StoragePool::LIST_GLUSTER Include gluster storage pools
- Sys::Virt::StoragePool::LIST_ZFS Include ZFS storage pools
- Sys::Virt::StoragePool::LIST_VSTORAGE Include VStorage storage pools
- Sys::Virt::StoragePool::LIST_ISCSI_DIRECT Include direct iSCSI pools

EVENT ID CONSTANTS

- Sys::Virt::StoragePool::EVENT_ID_LIFECYCLE Storage pool lifecycle events
- Sys::Virt::StoragePool::EVENT_ID_REFRESH Storage pool volume refresh events

LIFECYCLE CHANGE EVENTS

The following constants allow storage pool lifecycle change events to be interpreted. The events contain both a state change, and a reason though the reason is currently unused.

Sys::Virt::StoragePool::EVENT_DEFINED

Indicates that a persistent configuration has been defined for the storage pool

Sys::Virt::StoragePool::EVENT_STARTED
The storage pool has started running

Sys::Virt::StoragePool::EVENT_STOPPED
The storage pool has stopped running

Sys::Virt::StoragePool::EVENT_UNDEFINED

The persistent configuration has gone away

Sys::Virt::StoragePool::EVENT_CREATED
The underlying storage has been built

Sys::Virt::StoragePool::EVENT_DELETED

The underlying storage has been released

AUTHORS

Daniel P. Berrange berrange@redhat.com

COPYRIGHT

Copyright (C) 2006–2009 Red Hat Copyright (C) 2006–2009 Daniel P. Berrange

LICENSE

This program is free software; you can redistribute it and/or modify it under the terms of either the GNU General Public License as published by the Free Software Foundation (either version 2 of the License, or at your option any later version), or, the Artistic License, as specified in the Perl README file.

SEE ALSO

Sys::Virt, Sys::Virt::Error, http://libvirt.org