NAME

XtAppGetErrorDatabase, XtAppGetErrorDatabaseText - obtain error database

SYNTAX

#include <X11/Intrinsic.h>

XrmDatabase *XtAppGetErrorDatabase(XtAppContext app_context);

void XtAppGetErrorDatabaseText(XtAppContext app_context, const char *name, const char *type, const char *class, const char *defaultMsg, char *buffer_return, int nbytes, XrmDatabase database);

ARGUMENTS

app_context Specifies the application context.

buffer_return Specifies the buffer into which the error message is to be returned.

class Specifies the resource class of the error message.

database Specifies the name of the alternative database that is to be used or NULL if the applica-

tion's database is to be used.

defaultMsg Specifies the default message to use.

name

type Specifies the name and type that are concatenated to form the resource name of the error

message.

nbytes Specifies the size of the buffer in bytes.

DESCRIPTION

The **XtAppGetErrorDatabase** function returns the address of the error database. The Intrinsics do a lazy binding of the error database and do not merge in the database file until the first call to **XtAppGetError-DatabaseText**.

The **XtAppGetErrorDatabaseText** returns the appropriate message from the error database or returns the specified default message if one is not found in the error database.

SEE ALSO

XtAppError(3), XtAppErrorMsg(3) X Toolkit Intrinsics — C Language Interface Xlib — C Language X Interface