NAME

jmap - print details of a specified process

SYNOPSIS

Note: This command is experimental and unsupported.

jmap [options] pid

mand.

options This represents the jmap command-line options. See Options for the jmap Command.

pid The process ID for which the information specified by the *options* is to be printed. The process must be a Java process. To get a list of Java processes running on a machine, use either the **ps** command or, if the JVM processes are not running in a separate docker instance, the **jps** com-

DESCRIPTION

The jmap command prints details of a specified running process.

Note:

This command is unsupported and might not be available in future releases of the JDK. On Windows Systems where the **dbgeng.dll** file isn't present, the Debugging Tools for Windows must be installed to make these tools work. The**PATH** en vironment variable should contain the location of the <code>jvm.dll</code> file that's used by the target process or the location from which the core dump file was produced.

OPTIONS FOR THE JMAP COMMAND

-clstats pid

Connects to a running process and prints class loader statistics of Java heap.

-finalizerinfo pid

Connects to a running process and prints information on objects awaiting finalization.

-histo[:live] pid

Connects to a running process and prints a histogram of the Java object heap. If the **live** suboption is specified, it then counts only live objects.

-dump:dump_options pid

Connects to a running process and dumps the Java heap. The *dump_options* include:

- **live** When specified, dumps only the live objects; if not specified, then dumps all objects in the heap.
- format=b --- Dumps the Java heap in hprof binary format
- **file**=*filename* --- Dumps the heap to *filename*

Example: jmap -dump:live,format=b,file=heap.bin pid