### **NAME**

pam\_motd - Display the motd file

#### **SYNOPSIS**

pam\_motd.so [motd=/path/filename] [motd\_dir=/path/dirname.d]

### DESCRIPTION

pam\_motd is a PAM module that can be used to display arbitrary motd (message of the day) files after a successful login. By default, pam motd shows files in the following locations:

/etc/motd /run/motd /usr/lib/motd /etc/motd.d/ /run/motd.d/ /usr/lib/motd.d/

Each message size is limited to 64KB.

If /etc/motd does not exist, then /run/motd is shown. If /run/motd does not exist, then /usr/lib/motd is shown.

Similar overriding behavior applies to the directories. Files in /etc/motd.d/ override files with the same name in /run/motd.d/ and /usr/lib/motd.d/. Files in /run/motd.d/ override files with the same name in /usr/lib/motd.d/.

Files the in the directories listed above are displayed in lexicographic order by name.

To silence a message, a symbolic link with target /dev/null may be placed in /etc/motd.d with the same filename as the message to be silenced. Example: Creating a symbolic link as follows silences /usr/lib/motd.d/my\_motd.

## ln -s /dev/null /etc/motd.d/my motd

The **MOTD\_SHOWN=pam** environment variable is set after showing the motd files, even when all of them were silenced using symbolic links.

## **OPTIONS**

### motd=/path/filename

The /path/filename file is displayed as message of the day. Multiple paths to try can be specified as a colon–separated list. By default this option is set to /etc/motd:/run/motd:/usr/lib/motd.

# motd\_dir=/path/dirname.d

The /path/dirname.d directory is scanned and each file contained inside of it is displayed. Multiple directories to scan can be specified as a colon–separated list. By default this option is set to /etc/motd.d:/run/motd.d:/usr/lib/motd.d.

## noupdate

Don't run the scripts in /etc/update-motd.d to refresh the motd file.

When no options are given, the default behavior applies for both options. Specifying either option (or both) will disable the default behavior for both options.

# MODULE TYPES PROVIDED

Only the **session** module type is provided.

## **RETURN VALUES**

PAM\_ABORT

Not all relevant data or options could be obtained.

PAM BUF ERR

Memory buffer error.

PAM\_IGNORE

This is the default return value of this module.

# **EXAMPLES**

The suggested usage for /etc/pam.d/login is:

session optional pam\_motd.so

To use a motd file from a different location:

session optional pam\_motd.so motd=/elsewhere/motd

To use a motd file from elsewhere, along with a corresponding .d directory:

session optional pam\_motd.so motd=/elsewhere/motd motd\_dir=/elsewhere/motd.d

# **SEE ALSO**

 $\boldsymbol{motd}(5), \boldsymbol{pam.conf}(5), \boldsymbol{pam.d}(5), \boldsymbol{pam}(7), \boldsymbol{update\text{-}motd}(5)$ 

## **AUTHOR**

pam\_motd was written by Ben Collins <bcollins@debian.org>.

The **motd\_dir=** option was added by Allison Karlitskaya <allison.karlitskaya@redhat.com>.