REVERSING WITH IDA PRO FROM SCRATCH

PART 5

We will continue with the main instructions and their use in the code. Logically, when we see the debugger section, we will have more examples to apply the results in real time.

LEA (LOAD EFFECTIVE ADDRESS)

LEA A,B

The instruction LEA moves the specified address from **B** to **A**. It never accesses the content of **B**. It will always be the address or result of the operation in brackets of the second operand. It is used so much to get the memory addresses of variables and arguments.

Let's see some examples:

```
iew-A 🖾
           A Structures
      00401170
      00401170 sub 401170 proc near
      00401170
      00401170 var_24= byte ptr -24h
      00401170 var_18= byte ptr -18h
      00401170 var_14= dword ptr -14h
00401170 var_10= dword ptr -10h
      00401170 var_C= dword ptr -0Ch
      00401170 var_4= dword ptr -4
00401170 arg_0= dword ptr 8
      00401170
      00401170 push
                       ebp, esp
      00401171 mov
      00401173 push
                       OFFFFFFF
                       offset sub_429AD9
      00401175 push
      0040117A mov
                       eax, large fs:0
      00401180 push
                       eax
      00401181 sub
                       esp, 18h
                       eax, ____
      00401184 mov
                               _security_cookie
      00401189 xor
      0040118B mov
                       [ebp+var_10], eax
      0040118E push
                       esi
      0040118F push
                       edi
      00401190 push
                       eax
      00401191 lea
                       eax, [ebp+var_C]
      00401194 mov
                       large fs:0, eax
(311.70) (947.193) 000011F0 004011F0; sub 401170+80 (Synchron.
```

Normally, in the functions detected by IDA, there are arguments received by them. Most of the times, through a PUSH before calling the function.

The PUSH saves those values on the stack. These values are called arguments.

```
00401170
00401170; Attributes: bp-based frame
00401170
00401170 sub_401170 proc near
00401170
00401170 var_24= byte ptr -24h
00401170 var_18= byte ptr -18h
00401170 var_14= dword ptr -14h
00401170 var_10= dword ptr -10h
00401170 var_C= dword ptr -0Ch
00401170 var_4= dword ptr -4
00401170 arg_0= dword ptr 8
```

In the list of variables and arguments of the header in each function, there is just an argument on the stack as in the list. In this case, **arg_0**.


The function also has local variables to reserve space on the stack above the arguments.

More ahead, I will explain the exact location of arguments and variables on the stack. By now, it is just important that each argument or variable used by a function has an address where it is located and a value as any other variable does anywhere in the memory.

```
00401170
        98491179 push
98491171 mov
98491171 mov
98491173 push
98491175 push
                              ebp, esp
OFFFFFFFh
                              offset sub_429AD9
eax, large fs:0
        90491178 push
90491181 sub
90491184 mov
90491189 xor
9049118B mov
                              eax
                              eax
esp, 18h
eax, ___security_c
eax, ebp
[ebp+var_10], eax
esi
                                        _security_cookie
        0040118E push
0040118F push
                              edi
        00401190 push
00401191 lea
                              eax, [ebp+var_C]
large fs:0, eax
        00401194 mov
(311.70) (947.193) 000011F0 004011F0: sub 401170+80 (Synchron
```

In this picture, we see when the program, in 0x401191, uses LEA. It moves just the address from the stack. If it were a MOV, it would move the content or value saved in that variable.

LEA, in spite of using brackets, it just moves the address without accessing its content because it just solves the operations in brackets and as EBP is normally used as a base of variables and arguments of the stack in each function, what it really does is adding or subtracting a constant to the EBP value that points to an address of the stack taken as a base for that function.



If we right click on that variable, we see that the mathematical way to write it and modify it using the Q key is **[EBP-0C]**.

That's why **LEA** just solves that **EBP-0C** operation as **EBP** has a stack address that will be the base in this function subtracting **0C**, I get the address of that variable.

Here, many people wonder if it is not easier that IDA uses the pure math notation for variables and arguments instead of [EBP - or + a tag.]

In reversing, it is very important for us to be able to rename the variables and arguments in real time to know what they do and have a better orientation.

It's not the same to use a variable called EBP-0C than a variable that I can rename as EBP+SIZE, for example. (Using the N key. Try it.) If I know that it saves a size. If I need to see the original value, I right click on it.

```
89491179 var_18= dword ptr -18h
89491179 size= dword ptr -9Ch
89491179 var b dword ptr -4
89491170 drg_6= dword ptr 8
00401170
00401170 push
                       ebp
00401171 mov
                       ebp, esp
OFFFFFFFh
00401173 push
00401175 push
                       offset sub_429AD9
0040117A mov
                       eax, large fs:0
00401180 push
                       eax
00401181 sub
                       esp, 18h
                                 _security_cookie
00401184 mov
                       eax, ____
00401189 xor
0040118B mov
                       [ebp+var_10], eax
0040118E push
                       esi
0040118F push
                       edi
00401190 push
00401191 lea
                       eax
                       eax, [ebp+size]
large [fs:0, eax
00401194 mov
0040119A mov
```

LEA is also used to solve operations in brackets moving the result to a destination register without accessing its content.

Example:

LEA EAX,[4+5]

It will move 9 to EAX, not the content of the address 0x9 as a MOV would do.

MOV EAX,[4+5]

That's why...

LEA EAX,[EBP - 0C]

...moves the result of **EBP-0C** that is the result of the variable memory address gotten when solving **EBP-0C** and moves it to **EAX**.


MOV EAX, [EBP - 0C]

Apart from solving EBP-0C and getting the address, it looks for its content (the saved value in that variable) and moves it to EAX.

It is very important to differentiate a LEA from MOV and their use.


LEA gets variable addresses.

MOV gets the values saved in the variable addresses.




The result of the search of the **LEA** text in the VEWIEVER shows us that it is used most of the times to get variable addresses or stack arguments. There are more instructions using **[EBP+something]**.

The rest is combined operations between registers and constants whose result is moved to the first operand that can have numerical results or some address also depending on the registers value.



When solving the operation, if ESI equals 400000, for example, and EAX equals 2, the result of **0x400000 + 2 *4+0x14** will be moved to EDX.



That means it will move 0x40001C.

Ricardo Narvaja

Translated by: @IvinsonCLS