본 강의 동영상 및 자료는 대한민국 저작권법을 준수합니다. 본 강의 동영상 및 자료는 상명대학교 재학생들의 수업 목적으로 제작·배포되는 것으로, 수업목적으로 내려받은 강의 동영상 및 자료는 수업목적이외에 다른 용도로 사용할 수 없으며, 다른 장소 및 타인에게 복제, 전송하여 공유할 수 없습니다. 이를 위반해서 발생하는 모든 법적 책임은 행위 주체인 본인에게 있습니다.

본 수업의 주 교재는 Silberschatz, Galvin, Gagne, "Operating System Concepts Essentials 2nd ed.", Wiley, 또는 한글번역본인 박민규, 조유근, "Operating System Concepts 에센셜 2판", 홍릉과학출판사입니다. 본 강의 동영상의 슬라이드는 이 책의 홈페이지에서 제공하는 것을 사용했음을 밝힙니다 (https://codex.cs.yale.edu/avi/os-book/OSE2/slide-dir/index.html). 다만 강의의 편의를 위해 내용 변경없이 슬라이드 레이아웃을 변경하였고, 진도 관리에 필요한 경우 일부 슬라이드는 생략하였습니다.

## Chapter 8: Virtual Memory

virtual memory system demand paging, page-replacement, and allocation of page frames working-set model shared memory and memory-mapped files

#### Contents

- Background
- Demand Paging
- Page Replacement
- Allocation of Frames
- Thrashing
- Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

#### 8.1 Background

- Code needs to be in memory to execute, but entire program rarely used
  - Error code, unusual routines, large data structures
- Entire program code not needed at same time
- Consider ability to execute partially-loaded program
  - Program no longer constrained by limits of physical memory
  - Each program takes less memory while running -> more programs r un at the same time
    - Increased CPU utilization and throughput with no increase in response time or turnaround time
  - Less I/O needed to load or swap programs into memory -> each us er program runs faster


#### Background (Cont.)

- Virtual memory separation of user logical memory from physical memory
  - Only part of the program needs to be in memory for execution
  - Logical address space can therefore be much larger than physical address space
  - Allows address spaces to be shared by several processes
  - Allows for more efficient process creation
  - More programs running concurrently
  - Less I/O needed to load or swap processes

#### Background (Cont.)


- Virtual address space logical view of how process is stored in memory
  - Usually start at address 0, contiguous addresses until end of space
  - Meanwhile, physical memory organized in page frames
  - MMU must map logical to physical
- Virtual memory can be implemented via:
  - Demand paging
  - Demand segmentation

# Virtual Memory That is Larger Than Physical Memory



## 8.2 Demand Paging Priva

- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
  - Less I/O needed, no unnecessary I/O
  - Less memory needed
  - Faster response
  - More users
- Similar to paging system with swapping (diagram on right)
- Page is needed ⇒ reference to it
  - invalid reference ⇒ abort
  - not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
  - Swapper that deals with pages is a pager




#### **Basic Concepts**


- Pager brings in only those pages into memory; how to deter mine that set of pages?
  - Need new MMU functionality to implement demand paging
- If pages needed are already memory resident
  - No difference from non demand-paging
- If page needed and not memory resident
  - Need to detect and load the page into memory from storage
    - Without changing program behavior
    - Without programmer needing to change code

#### Valid-Invalid Bit

- With each page table entry a valid–invalid bit is associated (v ⇒ in-memory – memory r esident, i ⇒ not-in-memory)
- Initially valid—invalid bit is set to i on all entries
- During MMU address transla tion, if valid–invalid bit in pa ge table entry is i ⇒ page fa ult




# Page Table When Some Pages Are Not in Main Memory



## Page Fault

- 1. If there is a reference to a page
- 2. First reference to that page will trap to operating system: page fault
- 3. Locate the page in disk
- 4. Find free frame and Swap pag e into frame via scheduled disk operation
- 5. Reset tables to indicate page n ow in memory; set validation bi
- 6. Restart the instruction that caused the page fault




#### Aspects of Demand Paging

- Extreme case start process with no pages in memory
  - OS sets instruction pointer to first instruction of process, non-memory-resident -> page fault
  - And for every other process pages on first access
  - Pure demand paging 分分人
- Actually, a given instruction could access multiple pages -> multiple page faults
  - Consider fetch and decode of instruction which adds 2 numbers from mem ory and stores result back to memory
  - ory and stores result back to memory
     Pain decreased because of locality of reference
- Hardware support needed for demand paging
  - Page table with valid / invalid bit
  - Secondary memory (swap device with swap space)
  - Instruction restart

#### Instruction Restart

- Consider an instruction that could access several different location
  - block move



- auto increment/decrement location
- Restart the whole operation?
  - What if source and destination overlap?

#### Performance of Demand Paging

#### म्रेकेन प्रदे

- Stages in Demand Paging (worse case)
- 1. Trap to the operating system
- 2. Save the user registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
  - 1. Wait in a queue for this device until the read request is serviced
  - 2. Wait for the device seek and/or latency time
  - 3. Begin the transfer of the page to a free frame
- 6. While waiting, allocate the CPU to some other user
- 7. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other user
- 9. Determine that the interrupt was from the disk
- 10. Correct the page table and other tables to show page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- 12. Restore the user registers, process state, and new page table, and then resume the interrupted instruction

### Performance of Demand Paging (Cont.)

- Three major activities
  - 1. Service the interrupt careful coding means just several hundred instructions needed
  - 2. Read the page lots of time
  - 3. Restart the process again just a small amount of time
- Page Fault Rate  $0 \le p \le 1$ 
  - if p = 0 no page faults
  - if p = 1, every reference is a fault
- Effective Access Time (EAT)

effective access time =  $(1 - p) \times ma + p \times page$  fault time

#### Demand Paging Example

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds

```
• EAT = (1 - p) \times 200 + p (8 \text{ milliseconds})
= (1 - p \times 200 + p \times 8,000,000)
= 200 + p \times 7,999,800
```

- If one access out of 1,000 causes a page fault, then EAT = 8.2 microseconds This is a slowdown by a factor of 40!!
- If want performance degradation < 10 percent

  220 > 200 + 7,999,800 x p

  20 > 7,999,800 x p

  p < .0000025 → one page fault in every 400,000 memory accesses !!


#### Demand Paging Optimizations


- Swap space I/O faster than file system I/O even if on the same device
  - Swap allocated in larger chunks, less management needed than file system
- Copy entire process image to swap space at process load time
  - Then page in and out of swap space
  - Used in older BSD Unix
- Demand page in from program binary on disk, but discard rather than paging out when freeing frame
  - Used in Solaris and current BSD
  - Still need to write to swap space
    - Pages not associated with a file (like stack and heap) anonymous memory
    - Pages modified in memory but not yet written back to the file system
- Mobile systems
  - Typically don't support swapping
  - Instead, demand page from file system and reclaim read-only pages (such as code)

#### 8.3 Copy-on-Write forked (unix)

- Copy-on-Write (COW) allows both parent and child processes to initially share the same pages in memory
  - If either process modifies a shared page, only then is the page copied
- COW allows more efficient process creation as only modified pages are copied
- In general, free pages are allocated from a pool of zero-fill-on-demand pages
  - Pool should always have free frames for fast demand page execution
    - Don't want to have to free a frame as well as other processing on page fault
  - Why zero-out a page before allocating it?
- vfork() variation on fork() system call has parent suspend and child using copy-on-write address space of parent
  - Designed to have child call exec()
  - Very efficient

#### Before and After Process Modifies Page C





#### 8.4 Page Replacement

- What Happens if There is no Free Frame?
  - Used up by process pages
  - Also in demand from the kernel, I/O buffers, etc
- Page replacement find some page in memory, but not reall y in use, page it out া প্রস্থা প্রস্থান ক্রিয়াল
  - Algorithm terminate? swap out? replace the page?
  - Performance want an algorithm which will result in minimum num ber of page faults
- Same page may be brought into memory several times


#### Page Replacement (Cont'd)

- Prevent over-allocation of memory by modifying page-fault s ervice routine to include page replacement
- Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- Page replacement completes separation between logical mem ory and physical memory – large virtual memory can be provided on a smaller physical memory

#### Basic Page Replacement

- Find the location of the desired page on disk
- Find a free frame:

- If there is a free frame, use it If there is no free frame, use a page replacement algorithm to select a victim frame
  - Write victim frame to disk if dirty
- Bring the desired page into the (newly) free frame; update the page and frame tables
- Continue the process by restarting the instruction that caused the trap
- Note now potentially 2 page transfers fo r page fault increasing EAT




#### Page and Frame Replacement Algorithms

- Frame-allocation algorithm determines
  - How many frames to give each process
- Page-replacement algorithm
  - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page f aults on that string
  - String is just page numbers, not full addresses
  - Repeated access to the same page does not cause a page fault
    Results depend on number of frames available
- In all our examples, the reference string of referenced page numb ers is


7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1

# Graph of Page Faults Versus The Number of Frames



#### First-In-First-Out (FIFO) Algorithm


• 3 frames (3 pages can be in memory at a time per process)



- Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5
  - Adding more frames can cause more page faults! → Belady's Anomaly
- 3 79 4710


- How to track ages of pages?
  - Just use a FIFO queue

### FIFO Illustrating Belady's Anomaly



#### Optimal Algorithm

Replace page that will not be used for longest period of time




9 is optimal for the example

- How do you know this?
  - Can't read the future
- Used for measuring how well your algorithm performs

### Least Recently Used (LRU) Algorithm

- Use past knowledge rather than future; replace page that has not been used in the most amount of time
- Associate time of last use with each page




- 12 faults better than FIFO but worse than OPT
- Generally good algorithm and frequently used
- But how to implement?

#### LRU Algorithm (Cont.)

=stuck


- Counter implementation
  - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
  - When a page needs to be changed, look at the counters to find smallest value
    - · Search through table needed
- Stack implementation
  - Keep a stack of page numbers in a double link form:
  - Page referenced:
    - move it to the top
    - · requires 6 pointers to be changed
  - But each update more expensive
  - No search for replacement
- LRU and OPT are cases of stack algorith ms that don't have Belady's Anomaly



### LRU Approximation Algorithms

- LRU needs special hardware and still slow
- Reference bit
  - With each page associate a bit, initially = 0
  - When page is referenced bit set to 1
  - Replace any with reference bit = 0 (if one exists)
    - We do not know the order, however
- Second-chance algorithm
  - Generally FIFO, plus hardware-provided reference bit
  - Clock replacement
  - If page to be replaced has
    - Reference bit = 0 -> replace it
    - reference bit = 1 then:
      - set reference bit 0, leave page in memory
      - replace next page, subject to same rules

## Second-Chance (clock) Page-Replaceme nt Algorithm



### Enhanced Second-Chance Algorithm

• Improve algorithm by using reference bit and modify bit (if available) in concert



- 1. (0, 0) neither recently used not modified best page to replace
- 2. (0, 1) not recently used but modified not quite as good, must write ou t before replacement
- 3. (1, 0) recently used but clean probably will be used again soon
- 4. (1, 1) recently used and modified probably will be used again soon and need to write out before replacement
- When page replacement called for, use the clock scheme but use the four classes replace page in lowest non-empty class
  - Might need to search circular queue several times

#### Counting Algorithms

- Keep a counter of the number of references that have been made to each page
  - Not common
- Least Frequently Used (LFU) Algorithm: replaces page with s mallest count
- Most Frequently Used (MFU) Algorithm: based on the argume nt that the page with the smallest count was probably just br ought in and has yet to be used

### Page-Buffering Algorithms

- Keep a pool of free frames
  - Then frame available when needed, not found at fault time
  - Read page into free frame and select victim to evict and add to free pool
  - When convenient, evict victim
- Possibly, keep list of modified pages
  - When backing store otherwise idle, write pages there and set to non-dirty
- Possibly, keep free frame contents intact and note what is in them
  - If referenced again before reused, no need to load contents again from disk
  - Generally useful to reduce penalty if wrong victim frame selected

### Applications and Page Replacement

- All of these algorithms have OS guessing about future page a ccess
- Some applications have better knowledge i.e. databases
- Memory intensive applications can cause double buffering
  - OS keeps copy of page in memory as I/O buffer
  - Application keeps page in memory for its own work
- Operating system can given direct access to the disk, getting out of the way of the applications; bypasses buffering, lockin g, etc
  - Raw disk mode

#### 8.5 Allocation of Frames

- Each process needs minimum number of frames
- Example: IBM 370 6 pages to handle SS MOVE instruction:
   instruction is 6 bytes, might span 2 pages

  - 2 pages to handle from
  - 2 pages to handle to
- Maximum of course is total frames in the system
- Two major allocation schemes
  - fixed allocation 型地壁 의정한斯
  - 9位をgromのH3N 受今 priority allocation
- Many variations

#### Fixed Allocation

- Fequal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 20 frames হিন্ত (এই)
  - Keep some as free frame buffer pool
- Proportional allocation Allocate according to the size of process আপোটিশে (ম্যু) but দ্বিকাপু কুমেছ দে হন্
  - Dynamic as degree of multiprogramming, process sizes change

$$s_i = \text{size of process } p_i$$
  $m = 64$   
 $S = \sum s_i$   $s_2 = 127$   
 $m = \text{total number of frames}$   $a_1 = \frac{10}{137} \times 62 \approx 4$   
 $a_i = \text{allocation for } p_i = \frac{s_i}{S} \times m$   $a_2 = \frac{127}{137} \times 62 \approx 57$ 

## Priority Allocation

- Use a proportional allocation scheme using priorities rather than size
- If process Pi generates a page fault,
  - select for replacement one of its frames
  - select for replacement a frame from a process with lower priority number

#### Global vs. Local Allocation


- Global replacement process selects a replacement frame from m the set of all frames; one process can take a frame from an other
  - But then process execution time can vary greatly
  - But greater throughput so more common
- - More consistent per-process performance
  - But possibly underutilized memory

## 8.6 Thrashing

- If a process does not have "enough" pages, the page-fault rate is very high
  - Page fault to get page
  - Replace existing frame
  - But quickly need replaced frame back
- This leads to:
  - Low CPU utilization
  - Operating system thinking that it needs to increase the degree of multiprogramming
  - Another process added to the system

 $\mathcal{F}$ Thrashing = a process is busy swapping pages in and out


## Thrashing (Cont.)



#### Demand Paging and Thrashing


3/2/9/2 1924 (350) 374.

- Why does demand paging w ork?
  - Locality model
    - Process migrates from one loc ality to another
    - Localities may overlap
- Why does thrashing occur?
   Σ size of locality > total me mory size




### Working-Set Model

•  $\Delta \equiv$  working-set window  $\equiv$  a fixed number of page references Example: 10,000 instructions



- if  $\Delta$  too small will not encompass entire locality
- if  $\Delta$  too large will encompass several localities
- if  $\Delta = \infty \Rightarrow$  will encompass entire program
- D =  $\Sigma$  WSi = total demand frames
  - Approximation of locality
- if D > m  $\Rightarrow$  Thrashing
- Policy if D > m, then suspend or swap out one of the processes




## Keeping Track of the Working Set

- Approximate with interval timer + a reference bit
- Example:  $\Delta = 10,000$ 
  - Timer interrupts after every 5000 time units
  - Keep in memory 2 bits for each page
  - Whenever a timer interrupts copy and sets the values of all reference bits to 0
  - If one of the bits in memory =  $1 \Rightarrow$  page in working set
- Why is this not completely accurate?
- Improvement = 10 bits and interrupt every 1000 time units


### Page-Fault Frequency

- More direct approach than WSS
- Establish "acceptable" page-fault frequency (PFF) rate and use local replacement policy
  - If actual rate too low, process loses frame
  - If actual rate too high, process gains frame



## Working Sets and Page Fault Rates

- Direct relationship between working set of a process and its page-fault rate
- Working set changes over time
- Peaks and valleys over time



Peak: Mes locality) 言語,


#### 8.7 Memory-Mapped Files

- Memory-mapped file I/O allows file I/O to be treated as routine memory y access by mapping a disk block to a page in memory
- A file is initially read using demand paging
  - A page-sized portion of the file is read from the file system into a physical page
  - Subsequent reads/writes to/from the file are treated as ordinary memory accesses
- Simplifies and speeds file access by driving file I/O through memory rat her than read() and write() system calls
- Also allows several processes to map the same file allowing the pages in memory to be shared
- But when does written data make it to disk?
  - Periodically and / or at file close() time
  - For example, when the pager scans for dirty pages


#### Memory-Mapped File Technique for all I/O

- Some OSes uses memory mapped files for standard I/O
- Process can explicitly request memory mapping a file via mmap() s ystem call
  - Now file mapped into process address space
- For standard I/O (open(), read(), write(), close()), mmap anyway
  - But map file into kernel address space
  - Process still does read() and write()
    - Copies data to and from kernel space and user space
  - Uses efficient memory management subsystem
    - Avoids needing separate subsystem
- Memory mapped files can be used for shared memory (although again via separate system calls)

## Memory Mapped Files



# Shared Memory via Memory-Mapped I/O




### 8.8 Allocating Kernel Memory

- Treated differently from user memory poselist
- Often allocated from a free-memory pool = hernel
  - Kernel requests memory for structures of varying sizes
  - Some kernel memory needs to be contiguous
    - I.e. for device I/O

### Buddy System


- Allocates memory from fixed-size segment c onsisting of physically-contiguous pages
- Memory allocated using power-of-2 allocator
  - Satisfies requests in units sized as power of 2
  - Request rounded up to next highest power of 2
  - When smaller allocation needed than is available, current chunk split into two buddies of next-lowe r power of 2
    - Continue until appropriate sized chunk available
- For example, assume 256KB chunk available, kernel requests 21KB
- Advantage quickly coalesce unused chunks into larger chunk
- 🕥 Disadvantage fragmentation

physically contiguous pages



#### Slab Allocator

- Slab is one or more physically contiguous pages
- Cache consists of one or more slabs
- Single cache for each unique kernel data structure
  - Each cache filled with objects instantiations of the data structure
- When cache created, filled with objects marked as free
- When structures stored, objects marked as used
- If slab is full of used objects, next object allocated from empty slab
  - · If no empty slabs, new slab allocated
- Benefits include no fragmentation, fast memory request satisfaction



#### Slab Allocator in Linux

- For example process descriptor is of type struct task\_struct
- Approx 1.7KB of memory
- New task -> allocate new struct from cache
  - Will use existing free struct task\_struct
- Slab can be in three possible states
  - Full all used
  - Empty all free
  - Partial mix of free and used
- Upon request, slab allocator
  - Uses free struct in partial slab
  - If none, takes one from empty slab
  - If no empty slab, create new empty

## 8.9 Other Considerations -- Prepaging

DELO MAS SIPOLED

- Prepaging
  - To reduce the large number of page faults that occurs at process startup
  - Prepage all or some of the pages a process will need, before they are referenced
  - But if prepaged pages are unused, I/O and memory was wasted
    - Assume s pages are prepaged and  $\alpha$  of the pages is used
      - Is cost of s \*  $\alpha$  save pages faults > or < than the cost of prepaging s \*  $(1-\alpha)$  unnecessary pages?
      - $\alpha$  near zero  $\Rightarrow$  prepaging loses

### Other Issues – Page Size

- Page size selection must take into consideration:
  - Fragmentation ↓
  - Page table size ↑
  - I/O overhead ↑
  - Resolution ▶
  - Number of page faults ↑
  - Locality *√*
- Always power of 2, usually in the range 2<sup>12</sup> (4,096 bytes) to 2<sup>2</sup> (4,194,304 bytes)
- On average, growing over time

#### Other Issues – TLB Reach

- TLB Reach The amount of memory accessible from the TLB
- TLB Reach = (TLB Size) X (Page Size)
- Ideally, the working set of each process is stored in the TLB
  - Otherwise there is a high degree of page faults
- Increase the Page Size
  - This may lead to an increase in fragmentation as not all applications require a large page size
- Provide Multiple Page Sizes
  - This allows applications that require larger page sizes the opportunity to use them with out an increase in fragmentation

#### Other Issues – Program Structure

```
Program structure
                                                                                     page
    • int[128,128] data;
                                                       128
    · Each row is stored in one page

    Program 1

               for (j = 0; j <128; j++)
for (i = 0; i < 128; i++)
                                    data[i,j] = 0;
                                                                       128
      128 \times 128 = 16,384 page faults
```

for (i = 0; i < 128; i++) for (j = 0; j < 128; j++) data[i,j] = 0;128

128 page faults

Program 2

page

#### Other Issues – I/O interlock

- I/O Interlock Pages must s ometimes be locked into me mory
- Consider I/O Pages that are used for copying a file from a device must be locked fro m being selected for eviction by a page replacement algor ithm

