

Program Directory for IBM Database 2 Universal Database Server for OS/390 and z/OS DB2 Rexx Language Support

Version 07 Release 01, Modification Level 00 Program Number 5675-DB2

FMID JDB771H

for Use with OS/390 and z/OS

Document Date: January 2001

Note!
Before using this information and the product it supports, be sure to read the general information under "Notices" on page v.
A form for reader's comments appears at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.
© Copyright International Business Machines Corporation 1982, 2000. All rights reserved. US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

	ices	
	Introduction	1
1.1	Rexx Language Support Description	1
1.2	Rexx Language Support FMID	2
	Program Materials	3
	Basic Machine-Readable Material	
	Optional Machine-Readable Material	
	2.2.1 Basic Program Publications	
	2.2.2 Optional Program Publications	
	Program Source Materials	
2.4	Publications Useful During Installation	4
	Program Support	
	Program Services	
	Preventive Service Planning	
3.3	Statement of Support Procedures	5
4.0	Program and Service Level Information	6
4.1	Program Level Information	6
4.2	Service Level Information	6
5.0	Installation Requirements and Considerations	7
	Driving System Requirements	
5	i.1.1 Machine Requirements	7
5	i.1.2 Programming Requirements	7
	Target System Requirements	8
	5.2.1 Machine Requirements	
5	5.2.2 Programming Requirements	
	5.2.2.1 Mandatory Requisites	
	5.2.2.2 Functional Requisites	
	5.2.2.3 Toleration/Coexistence Requisites	
	5.2.2.4 Incompatibility (Negative) Requisites	
	5.2.3 DASD Storage Requirements	
	FMIDs Deleted	
5.4	Special Considerations	11
	Installation Instructions	12
	Installing Rexx Language Support	
6	5.1.1 SMP/E Considerations for Installing Rexx Language Support	12

6 6 6	.1.2 SMP/E Options Subentry Values .1.3 Unload the Sample JCL from the Product Tape .1.4 Perform SMP/E RECEIVE .1.5 Perform SMP/E APPLY .1.6 Perform SMP/E ACCEPT	12 13 14
6.2	Activating Rexx Language Support	15
Rea	der's Comments	16
Fig	gures	
1.	Basic Material: Program Tape	3
2.	Publications Useful During Installation	4
3.	PSP Upgrade and Subset ID	
4.	Component IDs	5
5.	Driving System Software Requirements	
6.	Mandatory Requisites	8
7.	Functional Requisites	8
8.	Total DASD Space Required by Rexx Language Support	9
9.	Storage Requirements for Rexx Language Support Target Libraries	
10.	Storage Requirements for Rexx Language Support Distribution Libraries	
11.	SMP/E Options Subentry Values	
12.	Sample Installation Jobs	13

Notices

References in this document to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe on any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, is the user's responsibility.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing IBM Corporation North Castle Drive Armonk, New York 10504-1785 USA

For online versions of this book, we authorize you to:

- Copy, modify, and print the documentation contained on the media, for use within your enterprise, provided you reproduce the copyright notice, all warning statements, and other required statements on each copy or partial copy.
- Transfer the original unaltered copy of the documentation when you transfer the related IBM product (which may be either machines you own, or programs, if the program's license terms permit a transfer). You must, at the same time, destroy all other copies of the documentation.

You are responsible for payment of any taxes, including personal property taxes, resulting from this authorization.

THERE ARE NO WARRANTIES, EXPRESS OR IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

Some jurisdictions do not allow the exclusion of implied warranties, so the above exclusion may not apply to you.

Your failure to comply with the terms above terminates this authorization. Upon termination, you must destroy your machine readable documentation.

Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries or both:

CBPDO Rexx IBM® OS/390

Database 2 (DB2)

1.0 Introduction

This program directory is intended for the system programmer responsible for program installation and maintenance. It contains information concerning the material and procedures associated with the installation of DB2 Rexx Language Support. This publication refers to DB2 Rexx Language Support as Rexx Language Support. You should read all of this program directory before installing the program and then keep it for future reference.

The program directory contains the following sections:

- 2.0, "Program Materials" on page 3 identifies the basic and optional program materials and documentation for Rexx Language Support.
- 3.0, "Program Support" on page 5 describes the IBM support available for Rexx Language Support.
- 4.0, "Program and Service Level Information" on page 6 lists the APARs (program level) and PTFs (service level) incorporated into Rexx Language Support.
- 5.0, "Installation Requirements and Considerations" on page 7 identifies the resources and considerations for installing and using Rexx Language Support.
- 6.0, "Installation Instructions" on page 12 provides detailed installation instructions for Rexx Language Support. It also describes the procedures for activating the functions of Rexx Language Support, or refers to appropriate publications.

Before installing Rexx Language Support, read 3.2, "Preventive Service Planning" on page 5. This section tells you how to find any updates to the information and procedures in this program directory.

Do not use this program directory if you are installing Rexx Language Support with a SystemPac or ServerPac. When using these offerings, use the jobs and documentation supplied with the offering. This documentation may point you to specific sections of the program directory as required.

If you are installing Rexx Language Support using the MVS Custom-Built Product Delivery Offering (CBPDO, 5751-CS3), a softcopy program directory is provided on the CBPDO tape which is identical to the printed copy shipped with your order. Your CBPDO contains a softcopy preventive service planning (PSP) upgrade for this product. All service and HOLDDATA for Rexx Language Support are included on the CBPDO tape.

1.1 Rexx Language Support Description

This feature provides Rexx Language Support for DB2 access from REXX programs running either in a standard MVS Rexx procedure environment or for stored procedures written to use as a Rexx language.

1.2 Rexx Language Support FMID

Rexx Language Support consists of the following FMID: JDB771H

2.0 Program Materials

An IBM program is identified by a program number and a feature number. The program number for Rexx Language Support is 5675-DB2.

Basic Machine-Readable Materials are materials that are supplied under the base license and feature code, and are required for the use of the product. Optional Machine-Readable Materials are orderable under separate feature codes, and are not required for the product to function.

The program announcement material describes the features supported by Rexx Language Support. Ask your IBM representative for this information if you have not already received a copy.

2.1 Basic Machine-Readable Material

The distribution medium for this program is 9-track magnetic tape (written at 6250 BPI), 3480 cartridge, or 4mm cartridge. The tape or cartridge contains all the programs and data needed for installation. It is installed using SMP/E, and is in SMP/E RELFILE format. See 6.0, "Installation Instructions" on page 12 for more information about how to install the program.

Figure 1 describes the tape or cartridge.

Figure 1. Basic Material: Program Tape							
Feature Physical Medium Number Volume External Label Identification VOL							
6250 tape	5962	1	Rexx Language Supt	DB771H			
3480 tape	5963	1	Rexx Language Supt	DB771H			
4mm cart	6011	1	Rexx Language Supt	DB771H			

2.2 Optional Machine-Readable Material

No optional machine-readable materials are provided for Rexx Language Support.

2.2.1 Basic Program Publications

No basic publications are provided for Rexx Language Support.

2.2.2 Optional Program Publications

No optional publications are provided for Rexx Language Support.

2.3 Program Source Materials

No program source materials or viewable program listings are provided for Rexx Language Support.

2.4 Publications Useful During Installation

The publications listed in Figure 2 may be useful during the installation of Rexx Language Support. To order copies, contact your IBM representative.

Figure 2. Publications Useful During Installation	
Publication Title	Form Number
OS/390 SMP/E User's Guide	SC28-1740
OS/390 SMP/E Commands	SC28-1805
OS/390 SMP/E Reference	SC28-1806
OS/390 SMP/E Messages and Codes	SC28-1738

3.0 Program Support

This section describes the IBM support available for Rexx Language Support.

3.1 Program Services

Contact your IBM representative for specific information about available program services.

3.2 Preventive Service Planning

Before installing Rexx Language Support, you should review the current Preventive Service Planning (PSP) information. If you obtained Rexx Language Support as part of a CBPDO, there is HOLDDATA and PSP information included on the CBPDO tape.

If you obtained Rexx Language Support on a product tape, or if the CBPDO is more than two weeks old when you install it, you should contact the IBM Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

PSP Buckets are identified by UPGRADEs, which specify product levels, and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for Rexx Language Support are:

Figure 3. PSP Upgrade and Subset ID				
UPGRADE SUBSET		Description		
DB2710 JDB771H		DB2 Rexx Language Support		

3.3 Statement of Support Procedures

Report any difficulties you have using this program to your IBM Support Center. If an APAR is required, the Support Center will provide the address to which any needed documentation can be sent.

Figure 4 identifies the component IDs (COMPID) for Rexx Language Support.

Figure 4. Component IDs					
FMID COMPID		Component Name	RETAIN Release		
JDB771H	5740XYR00	DB2 Rexx Language Support	71H		

4.0 Program and Service Level Information

This section identifies the program and any relevant service levels of Rexx Language Support. The program level refers to the APAR fixes incorporated into the program. The service level refers to the PTFs integrated.

4.1 Program Level Information

No APARs have been incorporated into Rexx Language Support.

4.2 Service Level Information

No PTFs against this release of Rexx Language Support have been incorporated into the product tape.

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating Rexx Language Support. The following terminology is used:

- Driving system: the system used to install the program.
- · Target system: the system on which the program is installed.

In many cases, the same system can be used as both a driving system and a target system. However, you may want to set up a clone of your system to use as a target system by making a separate IPL-able copy of the running system. The clone should include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Some cases where two systems should be used include the following:

- When installing a new level of a product that is already installed, the new product will delete the old
 one. By installing onto a separate target system, you can test the new product while still keeping the
 old one in production.
- When installing a product that shares libraries or load modules with other products, the installation can
 disrupt the other products. Installing onto a test system or clone will allow you to assess these
 impacts without disrupting your production system.

5.1 Driving System Requirements

This section describes the environment of the driving system required to install Rexx Language Support.

5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

5.1.2 Programming Requirements

Figure 5. Driving System Software Requirements				
Program Number	Product Name and Minimum VRM/Service Level			
5647-A01	OS/390 SMP/E Version 2 Release 7 or higher			

© Copyright IBM Corp. 1982, 2000

5.2 Target System Requirements

This section describes the environment of the target system required to install and use Rexx Language Support.

Rexx Language Support installs in the DB (P115) SREL.

5.2.1 Machine Requirements

The target system can run in any hardware environment that supports the required software.

5.2.2 Programming Requirements

5.2.2.1 Mandatory Requisites: A mandatory requisite is defined as a product that is required without exception; this product either **will not install** or **will not function** unless this requisite is met. This includes products that are specified as REQs or PREs.

Figure 6. Mandatory Requisites				
Program Number	Product Name and Minimum VRM/Service Level			
5647-A01	OS/390 Version 2 Release 7 Base Services			
5675-DB2	IBM Database 2 Universal Database Server for OS/390 and z/OS			

5.2.2.2 Functional Requisites: A functional requisite is defined as a product that is **not** required for the successful installation of this product or for the basic function of the product, but **is** needed at run time for a specific function of this product to work. This includes products that are specified as IF REQs.

Figure 7. Functional Requisites					
Program Number	•				
5675-DB2	IBM Database 2 Universal Database Server for OS/390 and z/OS	DB2 Base Services			

5.2.2.3 Toleration/Coexistence Requisites: A toleration/coexistence requisite is defined as a product which must be present on a sharing system. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD at different time intervals.

Rexx Language Support has no toleration/coexistence requisites.

5.2.2.4 Incompatibility (Negative) Requisites: A negative requisite identifies products which must *not* be installed on the same system as this product.

Rexx Language Support has no negative requisites.

5.2.3 DASD Storage Requirements

Rexx Language Support libraries can reside on 3380 or 3390 DASD.

Figure 8 lists the total space required for each type of library.

Figure 8. To	Figure 8. Total DASD Space Required by Rexx Language Support				
Library Type Total Space Required					
Target	40 tracks of 3390 DASD				
Distribution	28 tracks of 3390 DASD				

Notes:

- 1. IBM recommends use of system determined block sizes for efficient DASD utilization for all non-RECFM U data sets. For RECFM U data sets, IBM recommends a block size of 32760, which is the most efficient from a performance and DASD utilization perspective.
- 2. Abbreviations used for the data set type are:
 - U Unique data set, allocated by this product and used only by this product. In order to determine the correct storage needed for this data set, this table provides all required information; no other tables (or program directories) need to be referenced for the data set size.
 - S Shared data set, allocated by this product and used by this product and others. In order to determine the correct storage needed for this data set, the storage size given in this table needs to be added to other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
 - Existing shared data set, used by this product and others. This data set is NOT allocated by Ε this product. In order to determine the correct storage needed for this data set, the storage size given in this table needs to be added to other tables (perhaps in other program directories). This existing data set must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old one and reclaim the space used by the old release and any service that had been installed. You can determine whether or not these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

3. All target and distribution libraries listed have the following attributes:

- The default name of the data set may be changed
- The default block size of the data set may be changed
- The data set may be merged with another data set that has equivalent characteristics
- The data set may be either a PDS or a PDSE
- 4. All target libraries listed have the following attributes:
 - The data set may be SMS managed
 - It is not required for the data set to be SMS managed
 - The data set may be in the LPA
 - It is not required for the data set to be in the LPA
 - · The data set may be in the LNKLST
 - It is not required for the data set to be APF authorized
 - It is not required for the data set to reside on the IPL volume
 - The values in the "Member Type" column are not necessarily the actual SMP/E element types identified in the SMPMCS.

The following figures describe the target and distribution libraries required to install Rexx Language Support. The storage requirements of Rexx Language Support must be added to the storage required by other programs having data in the same library or path.

Note: The data in these tables should be used when determining which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

Figure 9. Storage Requirements for Rexx Language Support Target Libraries								
Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR BIks
SDSNLOAD	LMOD	any	Е	PDS	U	0	16	10
SDSNSAMP	Sample	any	Е	PDS	FB	80	6	3
SDSNDBRM	Data	any	Е	PDS	FB	80	6	3

Figure 10. Storage Requirements for Rexx Language Support Distribution Libraries							
Library DDNAME	T Y P E	O R G	R E C F	L R E C	No. of 3390 Trks	No. of DIR BIks	
ADSNMACS	_	PDS	FB	80	6	3	
ADSNLOAD	E	PDS	U	0	16	10	

5.3 FMIDs Deleted

Installing Rexx Language Support may result in the deletion of other FMIDs. To see what FMIDs will be deleted, examine the ++VER statement in the product's SMPMCS.

If you do not wish to delete these FMIDs at this time, you must install Rexx Language Support into separate SMP/E target and distribution zones.

Note: These FMIDs will not automatically be deleted from the Global Zone. Consult the SMP/E manuals for instructions on how to do this.

5.4 Special Considerations

Rexx Language Support has no special considerations for the target system.

6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of Rexx Language Support.

Please note the following:

- If you want to install Rexx Language Support into its own SMP/E environment, consult the SMP/E manuals for instructions on creating and initializing the SMPCSI and the SMP/E control data sets.
- Sample jobs have been provided to help perform some or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries required for SMP/E execution have been defined in the appropriate zones.
- The SMP/E dialogs may be used instead of the sample jobs to accomplish the SMP/E installation steps.

6.1 Installing Rexx Language Support

6.1.1 SMP/E Considerations for Installing Rexx Language Support

This release of Rexx Language Support is installed using the SMP/E RECEIVE, APPLY, and ACCEPT commands. The SMP/E dialogs may be used to accomplish the SMP/E installation steps.

6.1.2 SMP/E Options Subentry Values

The recommended values for some SMP/E CSI subentries are shown in Figure 11. Use of values lower than these may result in failures in the installation process. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. Refer to the SMP/E manuals for instructions on updating the global zone.

Figure 11. SMP/E Options Subentry Values						
SUB-ENTRY	Value	Comment				
DSSPACE	200,200,600	3390 DASD Tracks				
PEMAX	SMP/E Default	IBM recommends using the SMP/E default for PEMAX.				

6.1.3 Unload the Sample JCL from the Product Tape

The following sample installation jobs are provided on the distribution tape to help you install Rexx Language Support:

Figure 12. Sample Installation Jobs							
Job Name	Job Type	Description	RELFILE				
DSNTTJRC	RECEIVE	Sample RECEIVE job	IBM.JDB771H.F3				
DSNTTJAP	APPLY	Sample APPLY job	IBM.JDB771H.F3				
DSNTTJAC	ACCEPT	Sample ACCEPT job	IBM.JDB771H.F3				

You may copy the jobs from the tape by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
EXEC PGM=IEBCOPY
//STEP1
//SYSPRINT DD SYSOUT=*
//IN
           DD DSN=IBM.JDB771H.F3,UNIT=tunit,VOL=SER=DB771H,
           LABEL=(4,SL),DISP=(OLD,KEEP)
//
//OUT
           DD DSNAME=jcl-library-name,
//
           DISP=(NEW, CATLG, DELETE),
//
           VOL=SER=dasdvol, UNIT=SYSALLDA,
//
           DCB=*.STEP1.IN,SPACE=(TRK,(10,10,5))
//SYSUT3
           DD UNIT=SYSALLDA, SPACE=(CYL, (1,1))
//SYSIN
           DD *
    COPY INDD=IN,OUTDD=OUT
    SELECT MEMBER=(DSNTTJAC,DSNTTJAP,DSNTTJRC)
/*
```

where tunit is the unit value matching the product tape or cartridge, jcl-library-name is the name of the data set where the sample jobs will reside, and dasdvol is the volume serial of the DASD device where the data set will reside.

You can also access the sample installation jobs by performing an SMP/E RECEIVE for FMID JDB771H, and then copying the jobs from data set hlq.IBM.JDB771H.F3 to a work data set for editing and submission. Note: "hlq" is the high-level qualifier specified as the DSPREFIX value in the SMPTLIB DDDEF or the OPTIONS entry of the global zone.

6.1.4 Perform SMP/E RECEIVE

Edit and submit sample job DSNTTJRC to perform the SMP/E RECEIVE for Rexx Language Support. Consult the instructions in the sample job for more information.

NOTE: If you obtained Rexx Language Support as part of a CBPDO, you can use the RCVPDO job found in the CBPDO RIMLIB data set to RECEIVE the Rexx Language Support FMIDs as well as any service, HOLDDATA, or preventive service planning (PSP) information included on the CBPDO tape. For more information, refer to the documentation included with the CBPDO.

Expected Return Codes and Messages: This job should complete with return code 0.

6.1.5 Perform SMP/E APPLY

Edit and submit sample job DSNTTJAP to perform an SMP/E APPLY CHECK for Rexx Language Support. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do not bypass the following on the APPLY CHECK: PRE, ID, REQ, and IFREQ. This is because the SMP/E root cause analysis identifies the cause only of ERRORS and not of WARNINGS (SYSMODs that are bypassed are treated as warnings, not errors, by SMP/E).

Once you have taken any actions indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Note: The GROUPEXTEND operand indicates that SMP/E apply all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from APPLY CHECK: This job should complete with return code 0.

Expected Return Codes and Messages from APPLY: You should complete with return code 0.

6.1.6 Perform SMP/E ACCEPT

Edit and submit sample job DSNTTJAC to perform an SMP/E ACCEPT CHECK for Rexx Language Support. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do not bypass the following on the ACCEPT CHECK: PRE, ID, REQ, and IFREQ. This is because the SMP/E root cause analysis identifies the cause only of ERRORS and not of WARNINGS (SYSMODs that are bypassed are treated as warnings, not errors, by SMP/E).

Before using SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. This will cause entries produced from JCLIN to be saved in the distribution zone whenever a SYSMOD containing inline JCLIN is ACCEPTed. For more information on the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E manuals.

Once you have taken any actions indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Note: The GROUPEXTEND operand indicates that SMP/E accept all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from ACCEPT CHECK: This job should complete with a return code 0.

Expected Return Codes and Messages from ACCEPT: This job should complete with return code 0.

If PTFs containing replacement modules are being ACCEPTed, SMP/E ACCEPT processing will linkedit/bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder may issue messages documenting unresolved external references, resulting in a return code of 4 from the ACCEPT step. These messages can be ignored, because the distribution libraries are not executable and the unresolved external references will not affect the executable system libraries.

6.2 Activating Rexx Language Support

Rexx Language Support is fully operational once the SMP/E installation is complete and the execution of job DSNTIJRX is complete (to bind packages).

Expected Return Codes and Messages: This job should complete with a return code 0.

Reader's Comments

Program Directory for DB2 Rexx Language Support

You may use this form to comment about this document, its organization, or subject matter with the understanding that IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you.

For each of the topics below please indicate your satisfaction level by circling your choice from the rating scale. If a statement does not apply, please circle N.

ſ	RATING SCALE									
	very satisfied	<=====	=======	:====>	very dissatisfied	not annlicable				
	1	2	3	4	5	N				

			Satis	sfactio	n	
Ease of product installation	1	2	3	4	5	N
Contents of program directory	1	2	3	4	5	Ν
Installation Verification Programs	1	2	3	4	5	Ν
Time to install the product	1	2	3	4	5	Ν
Readability and organization of program directory tasks	1	2	3	4	5	Ν
Necessity of all installation tasks	1	2	3	4	5	Ν
Accuracy of the definition of the installation tasks	1	2	3	4	5	Ν
Technical level of the installation tasks	1	2	3	4	5	Ν
Ease of getting the system into production after	1	2	3	4	5	N

Ease of installat	f getting the system into production after tion	1	2	3	4	5	N	
How d	id you order this product?							
	CBPDO CustomPac ServerPac Independent Other							
Is this	the first time your organization has installed	this pro	oduct	?				
_	Yes No							
Were t	the people who did the installation experience Yes	ed with	the i	nstall	ation	of MV	S produ	cts?

	No	
If yes, I	now many years?	
	have any comments to make about your ratings above, or any other aspen below:	ect of the product installation, please
_		
_		
_		
_		
_		
_		
Please	provide the following contact information:	
Nai	me and Job Title	
Org	ganization	
Add	dress	
Tel	ephone	

Thank you for your participation.

Please send the completed form to (or give to your IBM representative who will forward it to the DB2 Rexx Language Support Development group):

IBM Corporation PO Box 49023 San Jose, CA 95161

Attn: DB2 Test and Systems Services, W68/B373

FAX Number: (408) 463-2614

E-Mail: jfigone@us.ibm.com

IBM

Program Number: 5675-DB2 5962

5963 6011

Printed in U.S.A.

GI10-8219-00