How to write simple CICS MAP And associate it with simple COBOL-CICS program

- 1. Design the screen using BMS
- 2. Compile the BMS screen code using Job and it creates:
 - a. Physical Map
 - i. Load Module
 - ii. Attribute values
 - b. Symbolic Map
 - i. Source code module
 - ii. Variable declaration
- 3. Make entry in PPT
 - a. CESN to sign on CESF to sign off. RACF setting and can be off or on
 - b. CEDA DEF MAP (Define Mapset)
 - i. Fill MAPSET NAME AND GROUP fields
 - ii. (Group name is defined in resource definition file and CICS admin needs to set this group)
 - iii. F3 to come out of screen and Pause-break to come back to CICS region
 - c. CEDA INS MAP (Install map/load the map)
 - i. Fill MAPSET, GROUP
 - ii. Success message: Installed successfully
 - d. CECI SEND MAP('MAPNAME') MAPSET('MAPSETNAME') (See the map to test)
 - e. CECI: Command level interpretor.
 - f. CECI READQ TD (QID)
 - g. CEDA DEL MAP (To remove the entry from PPT table)
 - i. Delete Successful
 - h. CEDA ALTER MAP (To use the same name in case you are getting name already exists)
 - CEDA DEF TRANS < ENTER > (PPT entry for transaction)
 - i. Fill TRANSACTION, PROGRAM, GROUP
 - ii. Success message: 'Define successful'
 - j. CEDA INS TRANS <ENTER> (Install trans/load trans)
 - i. Fill TRANSACTION, GROUP
 - ii. Success message: 'Install successful'
 - k. CEDA DEF PROG <ENTER> (PPT entry for program)
 - i. Fill PROGRAM, LANGUAGE, GROUP
 - ii. Success message: 'Define successful'
 - 1. CEDA IN PROG <ENTER> (Install Prog/Load prog)
 - i. Fill PROGRAM, GROUP
 - ii. Success message: 'Install successful'
 - m. CEMT ITA (others)
 - n. CEDC DIS GR(GRP NAME) (others)
 - o. CEDA have define, delete, alter access, CEDB has define and alter access, CEDC has display access
- 4. Write COBOL-CICS program

- Compile COBOL-CICS program
 Make entries in PCT, PPT (using CEDA DEF...)
 Load tables in memory (using CEDA INS ...)
 Enter CICS run-time environment
 Execute transaction by specifying trans-id

- - a. TRANID <ENTER>

BMS Code

BMS code when compiled leads to symbolic map and physical map generation.

DFHMSD Options (Mapset definition)

<-72

MSEMP1 DFHMSD TYPE=&SYSPARM, LANG=COBOL, MODE=INOUT,

*

CTRL=(FREEKB,ALARM), STORAGE=AUTO, TIOAPFX=YES,

MAPATTS=(COLOR,HILIGHT), DSATTS=(COLOR,HILIGHT)

UTIME DFHMSD TYPE=FINAL

* in 72 column is continuation character and it can be any alphanumeric character

TIOAPFX : Terminal Input output area prefix

If lang=cobol than TIOAPFX=yes is a must

(It will insert 12 byte field after every field, which will be used by CICS internally)

Storage=Auto for multiple map under one mapset condition, optional for 1-mapset, 1-map condition

TYPE=\$SYSPARM options are MAP, DSECT, \$SYSPARM, FINAL based on option you have selected either Physical Map (MAP), Symbolic map (DSECT), both (\$SYSPARM), End of BMS Code (FINAL) is generated

MAPATT=(COLOR,HILIGHT) in physical map attributes get stored based on this value. If you specify color, it will just have color attribute you assigned, highlight option of blink will be ignored specified through program.

LANG=COBOL, PL1, ASM

DSATTS=(COLOR,HILIGHT) variables for color and highlight in symbolic map gets generated based on this.

MODE=INOUT,IN,OUT

EXTATT=YES/NO in newer version of CICS. It replaces MAPATTS and DSATTS option.

DFHMDI options (Map definition)

MAPEMP DFHMDI SIZE=(24,80), LINE=1, COLUMN=1, JUSTIFY=RIGHT

SIZE=(24,80) for single map or any map size you want. For multiple maps you need to be extra careful with this option.

DFHMDF option (Field definition)

Display field

PTITLE DFHMDF POS=(2,30), LENGTH=9,ATTRB=(NORM,PROT), *
INITIAL='DODO LOVE YOU',HILIGHT=BLINK,COLOR=BLUE

POS=(2,30) Position of the field on the map. Its map specific for multiple map condition. Its relative position and not the actual.

LENGTH=9 Field length

ATTRB=(NORM,PROT,IC) Attribute of field Options are

Set 1: NORM, DRK, BRT

Set 2: PROT, UNPROT, ASKIP

Set 3: This is option and can have value "IC" and sets the cursor to this by default when screen is thrown out first time. Or "FSET" meaning field value returned irrespective if it is changed or not (Refer DFHMDT functionality for further details). NUM is data entry for numeric field and user will not be able to type non-numeric data. (See edit field), position of sets is not important, it can be in any order.

INITIAL='ACC': length has to be less or equal. Only one quote mark allowed, double quote not acceptable.

HILIGHT=BLANK/REVRSE

COLOR=BLUE/WHITE/RED etc etc...

Stopper field

AENO DFHMDF POS(5,34), LENGTH=1, ATTRB=(NORM,ASKIP)

Askip field or stopper field is placed at the end of all *editable fields* to stop the text from edit fields running into other MAP areas.

Editable field

UENO DFHMDF POS=(5,30), LENGTH=3, ATTRB=(NORM,UNPROT,IC,NUM,FSET), * PICIN='X(3)', PICOUT='X(3)',HILIGHT=REVERSE

PICIN and PICOUT are field definition to pass it onto how it gets displayed on map.

Complete BMS example

MSEMP1 DFHMSD TYPE=&SYSPARM, LANG=COBOL, MODE=INOUT,	*
CTRL=(FREEKB,ALARM), STORAGE=AUTO, TIOAPFX=YES,	*
MAPATTS=(COLOR,HILIGHT), DSATTS=(COLOR,HILIGHT)	
MAPEMP DFHMDI SIZE=(24,80), LINE=1, COLUMN=1	
PTITLE DFHMDF POS=(2,30), LENGTH=39,ATTRB=(NORM,PROT), *	
INITIAL='DODO LOVEs YOU',HILIGHT=BLINK,COLOR=BLUE	Ξ.
UENO DFHMDF POS=(5,30), LENGTH=3, ATTRB=(NORM,UNPROT,IC,NUM,FSET),	4
PICIN='X(3)', PICOUT='X(3)',HILIGHT=REVERSE	
AENO DFHMDF POS(5,34), LENGTH=1, ATTRB=(NORM,ASKIP)	
UTIME DFHMSD TYPE=FINAL	
END	