
Computer Architecture (Practical Class) Introduction to Assembly

Luís Nogueira Raquel Faria

Departamento de Engenharia Informática Instituto Superior de Engenharia do Porto

{lmn,arf}@isep.ipp.pt

2020/2021



Computing systems and programs

- Computing systems are composed of hardware and system software (the Operating System) that work together to execute programs (user applications)
- A program can be seen as a cooking recipe. It has a list of ingredients (the *variables*) and a list of steps (the *instructions*) that tell the computer what to do with the variables. Variables can represent numbers, text, sounds, images, etc.

Program = Data + Instructions

 A combination of computer instructions and data allow the hardware to execute computing tasks

3 / 36

The CPU is a Digital Machine (1/3)

- Q: What type of data can be used?
- A: Binary data

Modern CPUs process binary data

- In order to be manipulated, all data, such as instructions, numbers, symbols, pictures, etc, must be represented as binary digits
- A binary digit is called a bit and represents either a 0 or a 1

Note: A previous course (Princípios da Computação) detailed several numeric representation systems (such as binary, hexadecimal or octal). Please review these materials as needed

LMN et al. (ISEP) Assembly 2020/2021 4/36

The CPU is a Digital Machine (2/3)

- Q: What instructions are supported by the CPU?
- A: Depends on the particular CPU. It is necessary to read the CPU manual!

Machine code

- The CPU instructions are called machine code because they are specific to a CPU type or model
- Are usually very simple since they are implemented in hardware and must be executed fast
- Machine code instructions are also represented as binary data!
- They usually include instructions to perform:
 - logic and arithmetic;
 - read/write from I/O devices;
 - flow control;
 - moving data around.

5 / 36

LMN et al. (ISEP) Assembly 2020/2021

The CPU is a Digital Machine (3/3)


C code example

Program = Data + Instructions

```
int sum ( int a, int b ) {
    return a + b;
}
```

• The same example in machine code for an Intel CPU

Program = Binary Data + Machine Code Instructions



6 / 36

Machine-level coding

One can think of developing at machine-level in several ways; For example:

 Read the CPU manual and toggle switches to positions corresponding to the desired microprocessor instruction operation code (opcode) in binary.

• Example: Altair 8800 (1975)

 Read the CPU manual and used a keyboard to enter the desired microprocessor instruction opcodes in hexadecimal.

• Example: Kim-1 (1976)

 Define a name (mnemonic) for each instruction, write the instructions in a file, and use a program that generates the corresponding machine code.

Program: Assembler

Language: Assembly

LMN et al. (ISEP)

Assembly example

Listing 1: Simple Assembly Example

```
# section identifier: initialized data
.section .data
                       # variable identifier (mvint)
mvint:
    .int 5
                       # integer, initialized to 5
                       # section identifier: code
.section .text
funcao:
                       # function definition (funcao)
   movl myint, %eax
                       # copy variable to register
    addl $1, %eax
                       # add 1 to register
    movl %eax, myint
                       # copy value from register to variable
   ret
```

8 / 36

Why study machine-level programming?

- Clarify and help understand how:
 - high-level language code gets translated into machine language;
 - a program interfaces with the hardware (processor, memory, external devices) and operating system;
 - data is represented and stored in memory and on external devices;
 - the processor accesses and executes instructions and how instructions access and process data.
- While most new software is developed in high-level languages, which are easier to write and maintain, assembly can be used, for example:
 - to recode in assembly language sections that are performance-critical;
 - to debug/understand the behaviour of programs for which no source code is available (for example, malware).

9 / 36

Assembly

- Based in instructions, registers and labels
 - Instructions recognized by the processor
 - Registers of the processor
 - Labels that assume the memory address of where they are defined
- Special characters:
 - . starts an assembler directive
 - # starts a comment
 - % starts a register name
 - \$ starts a value

LMN et al. (ISEP)

Listing 2: Basic Assemly program example

```
# the data section allows to declare initialized variables
.section .data # the ".section" can be ommitted
        .equ LINUX_SYS_CALL, 0x80
                                      # the .equ directive defines a
                                       # constant
output int:
        .asciz "imprimir inteiro:" #definition of a string
# the bss section is used to define uninitialized memory areas
.section .bss
        .comm buffer, 10000 # global array of 10000 bytes
        .lcomm buffer2, 500 # array of 500 bytes, only visible in
                               # current module (source file)
# the text section has the assembly instructions
.section .text
       .global sum
                       #defines the function as global
sum:
          # start of the function
         # instructions
   ret
```

Variable declaration

- Variable declarations can be made in the .data section
- The data type must be defined
- To avoid memory alignment issues, integer types (that occupy the most), should be declared first, then declare other variable types that occuppy less, and then defined the strings

LMN et al. (ISEP) Assembly 2020/2021 12 / 36

```
.octa – 128 bits (16 bytes) integer
 .quad - 64 bits (8 bytes) integer
.double - floating point number with double precision (8 bytes)
  .long - 32 bits (4 bytes) integer
   .int - 32 bits (4 bytes) integer
  .float - floating point number (4 bytes)
 .short - 16 bits (2 bytes) integer
  .byte - 8 bits
  .ascii - string
 .asciz - string automatically terminated by zero
```

LMN et al. (ISEP)

Variable declaration examples (1/2)

• Declaring an integer using the .int directive

```
number: # variable name
.int 5 # initialization value
```

• Declaring a string with the .asciz directive

```
message: # variable name
.asciz 'mensagem de teste' # initialization value
```


```
.section .data

factors:
    .double 37.45, 45.33, 12.30

height:
    .int 54

length:
    .int 62, 35, 47

msg:
    .asciz "This is a test message"
```



Defining constants

- The .data section can also be used to define constants
 - Constants are replaced by their value during the generation of the code. They make code easier to read and to maintain
- Note that defining a constant does not result in reserving memory space in the final program.
- Declaration example:
 - .equ FACTOR, 3
 - .equ LINUX_SYS_CALL, 0x80
- Usage example:

movl \$LINUX_SYS_CALL, %eax

Reserving generic memory areas

 The .bss (Block Started by Symbol) can be used to reserve uninitialized memory areas or arbitrary size

Directive	Description
.comm	Declares a global memory area
.lcomm	Declares a local memory area

Example Declaration

```
.section .bss .lcomm buffer, 10000
```

The above declares a memory area of 10000 bytes with the identifier buffer. The
identifier buffer can only be referenced by code belonging to the same module, as
it was declared with .lcomm

2020/2021

17 / 36

LMN et al. (ISEP)

Assembly

Processor registers

- The 32-bit registers EAX, EBX, ECX, EDX, EBP, ESP, EDI and ESI are generic registers for temporary usage
- The 16-bit registers AX, BX, CX, DX, BP, SP, DI and SI are contained in the corresponding 32-bit registers and represent their 16 less significant bits
- The 8-bit registers AH, BH, CH, DH are contained in the corresponding 16-bit registers (AX, BX, CX, DX) and represent their 8 most significant bits
- The 8-bit registers AL, BL, CL, DL are contained in the corresponding 16-bit registers (AX, BX, CX, DX) and represent their 8 less significant bits



The MOV Instruction

- The MOV instruction is used as a way to copy data
- Usage: mov origin, destination
- origin can be a memory address, a constant value or a register
- destination can be a memory address or a register
- The size of the data to be copied must be indicated by adding a character at the end of the instruction
- The MOV instruction can copy numbers of 8(b), 16(w) or 32(l) bits

Important notes

- Two memory addresses cannot be used simultaneously
- Origin and destination must be of the same size

LMN et al. (ISEP)

Listing 3: Assignment of constant value

Listing 4: Copying the contents of a variable to a register and vice-versa

```
#declare a variable called 'myinteger'
myinteger:
    .int 5
...

movl myinteger, %eax # copy value of variable to register
    ... # do something with the value...
movl %eax, myinteger # copy register value to variable
...
```

Important note about the \$ sign

Using the \$ in the text section requires some care

```
122 – the content of memory address 122
$122 – the number 122
```

variable - the contents pointed by memory address in variable
\$variable - the memory address of the label

Arithmetic operations: ADD

- The ADD instruction adds two integers
- Usage: add origin, destination
- Performs the operation destination = destination + origin (the result is placed in destination
- origin can be a memory address, a constant value or a register
- destination can be a memory address or a register
- a memory address for *origin* and *destination* cannot be used simultaneously
- the ADD instruction can add numbers of 8(b), 16(w) or 32(l) bits

23 / 36

LMN et al. (ISEP) Assembly 2020/2021

ADD instruction examples

Listing 5: Adding bytes, words, and longs

```
addb $10, %al  # adds 10 to the 8-bit AL register; AL=AL+10

addw %bx, %cx  # adds the value of BX to CX (16 bits); CX=CX+BX

addl var1, %eax  # adds the 32-bit value in var1 to EAX; EAX=EAX+var1

addl %eax, %eax  # adds EAX to itself; EAX=EAX+EAX
```

Arithmetic operations: SUB

- The SUB instruction subtracts two integers
- Usage: sub origin, destination
- performs the operation destination = destination origin (the result is placed in destination
- origin can be a memory address, a constant value or a register
- destination can be a memory address or a register
- a memory address for *origin* and *destination* cannot be used simultaneously
- the SUB instruction can add numbers of 8(b), 16(w) or 32(l) bits

LMN et al. (ISEP) Assembly 2020/2021 25 / 36

SUB instruction examples

Listing 6: Subtracting bytes, words, and longs

```
subl $10, %eax  # subtract 10 to the current value of EAX; EAX=EAX-10

subw %bx, %cx  # subtract the value of BX to CX (16 bits); CX=CX-BX

subl var1, %eax  # subtract the 32-bit value in var1 to EAX; EAX=EAX-var1

subl %ecx, %eax  # subtract ECX to EAX; EAX=EAX-ECX
```

Arithmetic Operations: INC and DEC

- The INC and DEC instructions increment (INC) and decrement (DEC) an integer by one, respectively
- Usage: inc destination
- performs the operation destination = destination + 1;
- destination can be a memory address or a register
- ullet the INC and DEC instructions can be used in numbers of 8(b), 16(w) or 32(l) bits

LMN et al. (ISEP) Assembly 2020/2021 27/36

INC/DEC instructions examples

Listing 7: Increment/Decrement bytes, words, and longs

```
incl %eax  # EAX=EAX+1 (32 bits)
incw %bx  # BX=BX+1 (16 bits)
decb %cl  # CL=CL-1 (8 bits)
```

Sharing variables between Assembly and C (1/3)

- We will (for now) write functions in Assembly that receive no parameters
- Then, we write programs in C that call our Assembly functions as if they were native C functions
- \bullet To share global variables between C and Assembly we will use the extern C keyword
 - It declares to the compiler that a variable is defined (the memory is reserved) in another source file (in our case, in the Assembly source file(s))
- To make our Assembly functions return:
 - a 32-bit value, leave that return value in the %eax register
 - a 64-bit value, leave the return value in the %edx:%eax registers

29 / 36

LMN et al. (ISEP) Assembly 2020/2021

Sharing variables between Assembly and C (2/3)

The extern C Keyword can be used in different ways to share variables between C and Assembly. The following is a recommended practice, that avoids common problems

- On the C source, we:
 - ② Declare the functions and variables implemented in Assembly and used in C in a separate .h file (often called asm.h). Declare Assembly variables using the extern C keyword (functions are extern by default):

Listing 8: asm.h

```
int asm_function();
extern int asm_integer;
```

② Use the keyword #include to include the previous .h file in the C source files (.c files) that use the Assembly functions or variables, and use the Assembly functions/variables like native C functions/variables:

Listing 9: main.c

```
#include "asm.h"
...
int main() {
...
asm_integer=10;
asm_function();
...
}
```

Sharing variables between Assembly and C (3/3)

- On the Assembly source, we:
 - Declare the variables and functions used by the C sources and define them as visible using the .global directive, and
 - Leave the return value on the "keax register to return a 32-bit value, or in the "kedx: "keax registers for a 64-bit value.

Listing 10: asm.s

```
.section .data
asm integer:
                       # variable declaration
    .int. 5
.global asm_integer
                       # define variable as global
.section .text
.global asm_function
                       # define function as global
asm function:
                       # start of the function
    . . .
    mov1 $0. %eax
                       # reaching here, will return 0
                       # (eax will not be changed until ret)
    . . .
    ret
```

Important note on writing Assembly functions

- When a function executes, it needs to perform some setup/cleanup code that we call
 prologue (at the beginning) and epilogue (at the end). Later, we will see why they
 are needed
- While some functions *may* behave correctly with no epilogue and prologue, **you** should have a prologue and epilogue in all functions you write.

Listing 11: Prologue/Epilogue example (http://codepad.org/fwYPhvOn)

```
function_label:
# prologue
    pushl %ebp  # save previous stack frame pointer
    movl %esp, %ebp  # the stack frame pointer for our function

# body of the function
    # here we implement our function...
# epilogue
    movl %ebp, %esp  # restore the stack pointer ("clear" the stack)
    popl %ebp  # restore the stack frame pointer

#return from the function
    ret
```

Listing 12: main.c (http://codepad.org/wnUhIpuK)

```
#include <stdio.h>
#include "asm.h" // defines op1, op2 and sum_op1_op2(void)
int main(void) {
   int res=0;
    printf("Value of op1?:");
    scanf("%d",&op1);
   printf("Value of op1?:");
   scanf("%d",&op2);

   /* res = op1 + op2; */
   res = sum_op1_op2();

   printf("%d = %d + %d\n", res, op1, op2);
   return 0;
}
```

Listing 13: asm.h (http://codepad.org/lvHvUwSK)

```
int sum_op1_op2(void);
extern int op1, op2;
```

Listing 14: asm.s (http://codepad.org/Ode8SKIa)

```
.section .data
                    # declare op1, op2
op1:
        .int 0
op2:
        .int 0
.global op1
                    # define op1, op2 as globals
.global op2
.section .text
.global sum_op1_op2
                      # define global function int sum_op1_op2(void)
sum_op1_op2:
# prologue
    pushl %ebp
                     # save previous stack frame pointer
   movl %esp, %ebp
                      # the stack frame pointer for our function
# body of the function
    movl op1, %ebx
                      # place op1 in ebx
   movl op2, %eax
                     # place op2 in eax
    addl %ebx, %eax
                      # add ebx to eax: the result is in eax
                      # and will be our return value
# epilogue
    movl %ebp, %esp
                     # restore the stack pointer ("clear" the stack)
    popl %ebp
                      # restore the stack frame pointer
                      # return from the function
    ret
```

Example: Sum two variables - Makefile

Listing 15: Makefile (http://codepad.org/8BfSoSR8)

```
main: main.o asm.o
gcc -Wall -g main.o asm.o -o main

main.o: main.c asm.h
gcc -Wall -g -c main.c

asm.o: asm.s
gcc -Wall -g -c asm.s

run: main
_/ main

clean:
rm *.o main
```

• Note: We are always using the compiler flags -g and -Wall.

LMN et al. (ISEP)

Practice

- Write a C program that calls increment(), a function implemented in Assembly
- Function increment() increments the value of the global integer variable g_number and returns the this value (after the increment)
- The C program should assign a test value to g_number, call increment() and then print both g_number and the value returned by the function
- Write a Makefile to compile your program

36 / 36

LMN et al. (ISEP) Assembly