


MondShield database ERD

Entity-relationship diagram — 7 tables, generated from the current EF Core model.



PK primary key · FK foreign key · 1—1 one-to-one · 1—N one-to-many · accent header = central hub table

Table & field reference

Plain-language description of every table and column.

users

The login account — one per person, regardless of role.

- `id` — primary key.
- `email` — unique login identifier.
- `full_name` — display name.
- `password_hash` — PBKDF2 hash; the raw password is never stored.
- `role` — `User` (trader) or `Admin` (broker staff).
- `refresh_token` / `refresh_token_expires_at_utc` — the current rotating refresh token, null once logged out or expired.
- `created_at_utc` — sign-up timestamp.

shield_accounts (the hub)

One MondShield account per user — the account's place on the stage ladder plus its local balance breakdown.

- `id` — primary key.
- `user_id` — the owning user (unique — one account per person).
- `status` — onboarding stage: `PendingKyc` → `KycApproved` → `Provisioned` → `Active` → `Exited` .
- `current_stage` — position on the six-level ladder (Revival/Rebuild/Stage1/2/3/VIP); null until active.
- `mt5_login` — the MT5 account number, assigned once provisioned.
- `activated_at_utc` — when the admin confirmed the \$2,000 activation deposit.
- `first_trade_at_utc` — anchors the 30-day level-up window.
- `created_at_utc` — account creation timestamp.
- `ins_capital` / `compensation` / `profit` / `commission` — the four balance buckets MT5's single balance number is split into locally (insured deposit money, broker-paid compensation, trading profit, commission paid) — the same `BalanceComposition` value object from the domain math layer, stored inline.

compensation_cap_trackers

One row per person, tracking the \$5,000 lifetime compensation cap — keyed by user (not account) so the cap still applies if someone exits and re-onboards.

- `user_id` — primary key and the link to `users` .
- `lifetime_compensation_paid` — running total paid out so far.
- `updated_at_utc` — last time it changed.

compensation_requests

A trader's loss-compensation request; one per stage per account (enforced by a unique index).

- `id` , `account_id` — identity and owning account.
- `stage_at_request` — which stage's coverage % applied.
- `loss_at_request` / `commission_excluded` — the reported loss and the commission subtracted from it.
- `computed_coverage` — stage % × coverable loss, before the cap.

- `capped_amount` — what's actually payable after the \$5,000 cap.
- `cap_reached` — true if the cap reduced the payout.
- `status` — Submitted → UnderReview → Approved/Rejected → Paid .
- `submitted_at_utc` / `scheduled_payout_date_utc` / `paid_at_utc` — the review/payout timeline (payout always lands on the 27th/28th).
- `reviewer_note` — optional admin comment.

ledger_entries

The append-only audit trail behind every balance change — every deposit, payout, profit accrual, commission, and withdrawal writes one of these.

- `id` , `account_id` — identity and owning account.
- `bucket` — which of the four balance buckets it touches.
- `reason` — Deposit / Compensation / TradingProfit / Commission / Withdrawal .
- `amount` — signed: positive = credit, negative = debit.
- `occurred_at_utc` — when it happened.
- `related_request_id` — optional link back to the `CompensationRequest` or `ProfitWithdrawal` that caused it.
- `note` — optional free text.

profit_withdrawals

A manual-withdrawal worklist item — an admin executes it in the MT5 terminal, then marks it done.

- `id` , `account_id` — identity and owning account.
- `requested_amount` — what the trader asked to withdraw.
- `profit_portion` / `non_profit_portion` — the split between shareable profit and untouched capital/compensation.
- `broker_share_amount` — the broker's cut of the profit portion only.
- `net_to_trader` — requested amount minus the broker's share.
- `status` — Requested → Completed .
- `requested_at_utc` / `completed_at_utc` — timeline.

stage_transitions

The immutable audit log of every stage change (up or down).

- `id` , `account_id` — identity and owning account.
- `from` / `to` — the stage before and after (`to` is null when the trader exits entirely).
- `direction` — Up (level-up) or Down (compensation drop).
- `exited` — true only for a compensation taken at Revival, which removes the trader from the program.
- `reason` — human-readable explanation for the audit log.
- `occurred_at_utc` — when it happened.

Key relationships: `users` 1—1 `shield_accounts` , `users` 1—1 `compensation_cap_trackers` ; `shield_accounts` 1—N to each of `compensation_requests` , `ledger_entries` , `profit_withdrawals` , and `stage_transitions` . All foreign keys use `ON DELETE RESTRICT` so audit/ledger history can never be cascade-deleted.