1 The Fourier Transformation

First, we begin with a crucial first definition:

Definition 1.1:

Given a function $f: \mathbb{R} \longrightarrow \mathbb{R}$, its Fourier Transform is:

$$\mathcal{F}(f(x))(u) = \int_{-\infty}^{\infty} f(x) \cdot e^{-i2\pi ux} dx$$

That is, $\mathcal{F}(f)$ is a function mapping real numbers to complex numbers. (The complex unit is i: $i^2 = -1$).

Another way we can think of this is as \mathcal{F} being a function mapping functions $f: \mathbb{R} \longrightarrow \mathbb{R}$ to functions $\mathbb{R} \longrightarrow \mathbb{C}$. Not every function has a Fourier transformation, but for the sake of this summary, it doesn't matter.

Now what's crucial about the Fourier Transform is that it is *invertible*, that is there exists an inverse transformation \mathcal{F}^{-1} such that

$$\mathcal{F}^{-1}(\mathcal{F}(f(x))) = f(x), \quad \mathcal{F}(\mathcal{F}^{-1}(F(u))) = F(u)$$

And this inverse transformation is given by:

$$\mathcal{F}^{-1}(F(u))(x) = \int_{-\infty}^{\infty} F(u) \cdot e^{i2\pi ux} du$$

Let's take a moment to understand what this means. Suppose we have a function f(x) and we take its Fourier transformation $F(u) = \mathcal{F}(f(x))(u)$. Then by taking the inverse Fourier transformation of F we get that:

$$f(x) = \mathcal{F}^{-1}(F(u))(x) = \int_{-\infty}^{\infty} F(u)e^{i2\pi ux} du$$

Now recall that F(u) is a complex number, so it can be written as $A_u \cdot e^{i\theta_u}$, and this becomes:

$$f(x) = \int_{-\infty}^{\infty} A_u \cdot e^{i(x \cdot 2\pi u + \theta_u)} du$$

And we know that functions of the form $e^{i\theta}$ is a sinusoidal wave:

$$e^{i\theta} = \operatorname{cis}(\theta) = \sin(\theta) + i\cos(\theta)$$

And so

$$A_u e^{i(x \cdot 2\pi u + \theta_u)} = A_u \operatorname{cis}(x \cdot 2\pi u + \theta_u)$$

this is a sinusoidal wave of frequency u, phase θ_u , and amplitude A_u . Recall that the phase of a complex number is its argument, ie. the phase of $re^{i\theta}$ is θ and its amplitude is its magnitude (r). What this means is that we can write f as the integral of sinusoidal waves whose frequency is given by u, and the phase and amplitude are the phase and amplitude of F(u).

So the Fourier Transform of a function f gives us a decomposition of f into sinusoidal waves.

Furthermore, we can extend the definition of the Fourier Transformation to multivariable functions quite elegantly:

Definition 1.2:

Given a function $f(x_1,\ldots,x_n)\colon\mathbb{R}^n\longrightarrow\mathbb{R}$, we define its Fourier Transform to be:

$$\mathcal{F}(f(x_1,\ldots,x_n))(u_1,\ldots,u_n) = \int_{-\infty}^{\infty} \cdots \int_{-\infty}^{\infty} f(x_1,\ldots,x_n) \cdot e^{-i2\pi(u_1x_1+\cdots+u_nx_n)} dx_1 \cdots dx_n$$

Or more compactly:

$$\mathcal{F}(f(\vec{x}))(\vec{u}) = \int_{\mathbb{R}^n} f(\vec{x}) \cdot e^{-i2\pi \vec{u} \cdot \vec{x}} d\vec{x}$$

where the product $\vec{u} \cdot \vec{x}$ is the dot product of two vectors.

Notice that $\mathcal{F}(f(\vec{x}))$ is a function $\mathbb{R}^n \longrightarrow \mathbb{C}$.

Similarly, the inverse multidimensional Fourier Transformation of $F(\vec{u})$ is:

$$\mathcal{F}^{-1}(F(\vec{u}))(\vec{x}) = \int_{\mathbb{R}^n} F(\vec{u}) \cdot e^{i2\pi \vec{u} \cdot \vec{x}} d\vec{u}$$

The significance of this is similar to that of the single dimension case: this decomposes $f(\vec{x})$ into multidimensional sinusoidal waves whose amplitude and phase are given by $F(\vec{u})$. But here sinusoidal waves are multidimensional, they are of the form:

$$A_u e^{i(u_1 x_1 + \dots + u_n x_n + \theta_u)} = A_u \operatorname{cis}(u_1 x_1 + \dots + u_n x_n + \theta_u)$$

(this is multidimensional since there are n inputs: x_1, \ldots, x_n). The sinusoidal waves in multiple dimensions are a bit more complicated, but fundamentally are very similar to the one dimension case.

It may be worthwhile to explicitly write the Fourier Transform and its inverse for two dimensions:

$$\mathcal{F}(f(x,y))(u,v) = \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} f(x,y) \cdot e^{-i2\pi(ux+vy)} dxdy$$

and

$$\mathcal{F}^{-1}(F(u,v))(x,y) = \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} F(u,v) \cdot e^{i2\pi(ux+vy)} dudv$$

Let's now discuss a few important traits of the Fourier Transform.

(1) The Fourier Transformation is *linear*: for every two functions $f, g: \mathbb{R}^n \longrightarrow \mathbb{R}$:

$$\mathcal{F}(f(\vec{x}) + g(\vec{x}))(\vec{u}) = \mathcal{F}(f(\vec{x}))(\vec{u}) + \mathcal{F}(g(\vec{x}))(\vec{u})$$

and for every $\alpha \in \mathbb{R}$:

$$\mathcal{F}(\alpha f(\vec{x}))(\vec{u}) = \alpha \mathcal{F}(f(\vec{x}))(\vec{u})$$

(2) The Fourier Transformation also *scales*: for $\alpha_1, \ldots, \alpha_n$ real numbers:

$$\mathcal{F}(f(\alpha_1 x_1, \dots, \alpha_n x_n))(u_1, \dots, u_n) = \frac{1}{|\alpha_1 \cdots \alpha_n|} \mathcal{F}(f(x_1, \dots, x_n)) \left(\frac{u_1}{\alpha_1}, \dots, \frac{u_n}{\alpha_n}\right)$$

In two dimensions, given α and β this becomes:

$$\mathcal{F}(f(\alpha x, \beta y))(u, v) = \frac{1}{|\alpha \beta|} \mathcal{F}(f(x, y)) \left(\frac{u}{\alpha}, \frac{v}{\beta}\right)$$

- (3) In two dimensions, the Fourier Transformation of the rotation of f(x,y) is equal to the rotation of the Fourier Transformation of f(x,y) with the same angle.
- (4) If the Fourier Transformation of $f(\vec{x})$ is $F(\vec{u})$ then the Fourier Transformation of $f(\vec{x} \vec{x}_0)$ is:

$$\mathcal{F}(f(\vec{x} - \vec{x}_0))(\vec{u}) = \int_{\mathbb{R}^n} f(\vec{x} - \vec{x}_0) \cdot e^{-i2\pi(\vec{u} \cdot \vec{x})} d\vec{x} = \int_{\mathbb{R}^n} f(\vec{x}) \cdot e^{-i2\pi(\vec{u} \cdot (\vec{x} + \vec{x}_0))} d\vec{x} = e^{-i2\pi\vec{u} \cdot \vec{x}_0} \cdot F(\vec{u})$$

Finally we get the following important theorem:

Theorem 1.3 (The Convolution Theorem):

If f and g are functions, whose Fourier Transformations are F and G respectively, then:

$$\mathcal{F}(f * q(x))(u) = F(u) \cdot G(u)$$

and

$$\mathcal{F}(f(x) \cdot g(x))(u) = F * G(u)$$

where f * g denotes the convolution of f and g.

2 Sampling and the Discrete Fourier Transformation

Suppose we have a signal f and we'd like to investigate it. That is, we'd like to figure out its decomposition into frequencies, ie. its Fourier Transformation. This is not always possible; for example, suppose we're receiving a radio signal. We don't have the actual formula for the signal, we just have values of the signal which we've sampled at (constant) intervals of time.

In order to understand this, we first we begin with an important mathematical object:

Definition 2.1:

The Dirac Delta Function is a mathematical object denoted $\delta(x)$ where for every real function f:

$$\int_{-\infty}^{\infty} f(x) \cdot \delta(x) \, dx = f(0)$$

In multiple dimensions, the multidimensional Diract Delta Function, $\delta(\vec{x})$ satisfies:

$$\int_{\mathbb{R}^n} f(\vec{x}) \cdot \delta(\vec{x}) \, d\vec{x} = f(\vec{0})$$

The Dirac Delta Function allows us to sample an input signal at a specific time.

Notice that if we shift the Diract Delta Function, we get:

$$\int_{-\infty}^{\infty} f(x) \cdot \delta(x - x_0) \, dx = \int_{-\infty}^{\infty} f(x + x_0) \cdot \delta(x) \, dx = f(0 + x_0) = f(x_0)$$

And in multiple dimensions:

$$\int_{\mathbb{R}^n} f(\vec{x}) \cdot \delta(\vec{x} - \vec{x}_0) \, dx = f(\vec{x}_0)$$

Specifically, in two dimensions:

$$\int_{-\infty}^{\infty} \int_{-\infty}^{\infty} f(x,y) \cdot \delta(x - x_0, y - y_0) \, dx dy = f(x_0, y_0)$$

As one final trait, notice that for $\alpha > 0$:

$$\int_{-\infty}^{\infty} f(x) \cdot \delta(\alpha x) \, dx = \frac{1}{\alpha} \int_{-\infty}^{\infty} f\left(\frac{x}{\alpha}\right) \cdot \delta(x) \, dx = \frac{1}{\alpha} \cdot f(0)$$

and if $\alpha < 0$:

$$\int_{-\infty}^{\infty} f(x) \cdot \delta(\alpha x) \, dx = -\frac{1}{\alpha} \int_{-\infty}^{\infty} f\left(\frac{x}{\alpha}\right) \cdot \delta(x) \, dx = \frac{1}{\alpha} \cdot f(0)$$

and so $\delta(\alpha x)$ acts the same as $\frac{1}{|\alpha|}\delta(x)$, so we say

$$\delta(\alpha x) = \frac{1}{|\alpha|}\delta(x)$$

Notice that the Fourier Transform of the delta function is:

$$\mathcal{F}(\delta(\vec{x}))(\vec{u}) = \int_{\mathbb{R}^n} \delta(\vec{x}) \cdot e^{-2i\pi \vec{u} \cdot \vec{x}} d\vec{x} = e^{-2i\pi \vec{u} \cdot \vec{0}} = e^0 = 1$$

This allows us to define another important function:

Definition 2.2:

The Sha function is defined as:

$$\mathrm{III}(x) = \sum_{n = -\infty}^{\infty} \delta(x - n)$$

This can of course be generalized to multiple dimensions, but for the sake of this summary, we will focus on the one dimensional case.

Notice that for a real $\tau > 0$:

$$\operatorname{III}\left(\frac{x}{\tau}\right) = \sum_{n = -\infty}^{\infty} \delta\left(\frac{x}{\tau} - n\right) = \sum_{n = -\infty}^{\infty} \tau \delta(x - \tau n) = \tau \sum_{n = -\infty}^{\infty} \delta(x - \tau n)$$


Thus we can use the III function to *sample* an input signal f: suppose we'd like to sample an input signal at intervals of τ units of time, that is we'd like to sample it at times ..., -2τ , $-\tau$, 0, τ , 2τ , Recall that the Dirac Delta Function can give us the measurement of the function at a specific time, so we define the *sampled function* of f, to be:

$$f_s(x) = f(x) \cdot \coprod \left(\frac{x}{\tau}\right)$$


Suppose that $F(u) = \mathcal{F}(f(x))(u)$. Recall that by **The Convolution Theorem**, the Fourier Transform of a product is the convolution of the convolution of the Fourier Transforms. Applying that here, we get that

$$\mathcal{F}(f_s(x))(u) = \sum_{n=-\infty}^{\infty} F\left(u - \frac{n}{\tau}\right)$$


Let's take a moment to understand the significance of this. Suppose we have a signal whose Fourier Transform, F looks like:



Then the Fourier Transform of f_s becomes:



And this continues in both directions for infinity. But this assumes that $\frac{n}{\tau}$ is spaced out enough that the $F(u-\frac{n}{\tau})$ don't overlap. If τ is too large, and thus $\frac{n}{\tau}$ too small, we get instead something which looks like:



The overlaps here actually mean that the values are added up, but in any case this causes inaccuracies in our sampled Fourier Transform. This phenomenon is called *undersampling*. But if τ is small enough, using a discrete sampling of the signal, we can reconstruct the Fourier Transform of the original signal, or at least a good approximation. But what τ is small enough? Suppose that largest frequency in the decomposition of f(x) is f_0 , that is for every $f_1 > f_0$, $F(f_0) = 0$. Then we must have that $f_0 - \frac{1}{\tau} \le -f_0$ ($-f_0$ is the leftmost point in F(u) in the sampled Fourier Transformation, and $f_0 - \frac{1}{\tau}$ is the rightmost point in $F(u - \frac{n}{\tau})$, and so

$$2f_0 \le \frac{1}{\tau} \implies \tau \le \frac{1}{2f_0}$$

Recall that the period of the wave of frequency f_0 is $\frac{1}{f_0}$, so we must sample at least twice for each period of the wave of the highest frequency in order to sample without causing undersampling. This maximum frequency is called the *Nyquist Frequency*:

Definition 2.3:

The Nyquist Frequency of a signal f(x) is the largest frequency of sampling (we sample at ..., $-\tau$, 0, τ , ... where τ is the Nyquist frequency) in order to not cause undersampling. The Nyquist frequency is equal to $\frac{1}{2f_0}$ where f_0 is the largest frequency in the decomposition of f(x) into waves (the smallest value where F(u) = 0 afterward).

Let's now see now how we can actually find a discrete decomposition of f(x). Recall that:

$$f_s(x) = f(x) \cdot \coprod \left(\frac{x}{\tau}\right) = \tau \cdot \sum_{n=-\infty}^{\infty} f(x) \cdot \delta(x - \tau n)$$

And so we can find another formula for the Fourier Transformation of the sampled function directly using the definition of the Fourier Transformation:

$$\mathcal{F}(f_s(x))(u) = \sum_{n=-\infty}^{\infty} \int_{-\infty}^{\infty} f(x) \cdot \delta(x - \tau n) \cdot e^{-2\pi u x} dx = \sum_{n=-\infty}^{\infty} f(\tau n) \cdot e^{-i2\pi u \tau n}$$

Now suppose instead of sampling an infinite number of times, we take N samples at times $0, \Delta x, \dots, (N-1)\Delta x$, so $\tau = \Delta x$ and this becomes:

$$\sum_{n=0}^{N-1} f(n \cdot \Delta x) \cdot e^{-i2\pi nu\Delta x}$$

We can create a sequence $x[0], \ldots, x[N-1]$ of the samples of f(x), ie. $x[n] = f(n\Delta x)$. Now suppose that we only care about sampling this Fourier Transformation at N points with frequency Δu , that is we only care about $X[k] = F(k \cdot \Delta u)$, then

$$X[k] = \sum_{n=0}^{N-1} x[n] \cdot e^{-i2\pi nk\Delta x\Delta u}$$

If we further require that $\Delta x \cdot \Delta u = \frac{1}{N}$ we get that

$$X[k] = \sum_{n=0}^{N-1} x[n] \cdot e^{-i\frac{2\pi}{N}nk}$$

This is called the *Discrete Fourier Transformation* of f:

Definition 2.4:

Given a signal f which we sample N times with frequency Δx , sampling the Fourier Transformation N times with frequency $\frac{1}{\Delta x}$ gives:

$$X[k] = \sum_{n=0}^{N-1} x[n] \cdot e^{-i\frac{2\pi}{N}nk}, \qquad k = 0, \dots, N-1$$

where x[n] is the nth sample of f(x) and X[k] is the kth sample of the Fourier Transformation of f.

X is called the Discrete Fourier Transformation (DFT) of x.

The inverse Discrete Fourier Transformation (IDFT) of X should not be too surprising:

$$x[n] = \frac{1}{N} \sum_{k=0}^{N-1} X[k] \cdot e^{-i\frac{2\pi}{N}nk}, \qquad n = 0, \dots, N-1$$

Some conventions multiply the DFT by $\frac{1}{N}$ instead of the IDFT. This has the benefit that X[0] is equal to the average of $x[0], \ldots, x[N-1]$ (as opposed to the sum), X[0] is called the DC component.

We can generalize this to more dimensions, but we do just two here:

Definition 2.5:

Given a matrix $x[0,\ldots,N-1;0,\ldots,M-1]$ its Discrete Fourier Transformation is:

$$X[u,v] = \sum_{j=0}^{M-1} \sum_{t=0}^{N-1} x[t,j] \cdot e^{-i2\pi \left(\frac{vt}{N} + \frac{vj}{M}\right)}, \qquad u = 0, \dots, N-1$$

$$v = 0, \dots, M-1$$

Similarly, the inverse Discrete Fourier Transformation of X is:

$$x[t,j] = \frac{1}{NM} \sum_{v=0}^{M-1} \sum_{u=0}^{N-1} X[u,v] \cdot e^{i2\pi \left(\frac{ut}{N} + \frac{vj}{M}\right)}, \qquad t = 0, \dots, N-1 \\ j = 0, \dots, M-1$$

Some conventions multiply the DFT by $\frac{1}{NM}$ instead of the IDFT.

Notice that in order to compute X, we can first find the DFT of each row of x and the find the DFT of each of the columns in that new matrix (or find the DFT of the columns first, and then the rows).

What's important about the DFT is that it (and the IDFT) can be computed in $O(N \log N)$ time (as opposed to $O(N^2)$ time naively), algorithms which do this are called Fast Fourier Transform (FFT) algorithms.

3 Frequency Filters

A special type of noise in a signal is *periodic noise*. Periodic noise is of course periodic. In order to deal with it, we use Fourier Transformations in order to find the suspect frequencies of the noise, set them to 0 and then find the inverse Fourier Transformation of this. This gives a signal where these suspect frequencies no longer exist, hopefully getting rid of the periodic noise. Using FFT, this can be done with relative efficiency. An important related function for this is FFTShift, which takes the DFT of the signal and shifts it so that the center of the output corresponds to $X[\vec{0}]$; the DC component. This makes it easier for us to see the frequencies, since the higher frequencies are at the edges, and the lower frequencies are near the center.

Also, we are mostly concerned with the amplitudes of the frequencies, so given a DFT of an image, we are more concerned with the magnitude of each complex number. The phase of each complex number is still very important as it gives the phase of the frequency, but it's harder for us to understand how each phase affects the image. Furthermore, since the dynamic range of the amplitudes is quite large, to us the DFT would like almost dark with a bright speck in the center (the DC component). So we take a logarithmic scale of the DFT; $\log(1 + |X|)$ (|X| since we are concerned with the amplitudes).

Another use of the Fourier Transform (and FFT) is convoluting the image. Recall that convolutions in the image are equivalent to elementwise products in the frequency space. So instead of convoluting an image, we can find the DFT of the image and the mask, multiply them together elementwise, and then find the IDFT of this new image. For very large masks, this may be more efficient than convoluting the image. More specifically: suppose we have an image $x[0,\ldots,N-1\,;\,0,\ldots,M-1]$ and a mask $k[0,\ldots,N-1\,;\,0,\ldots,M-1]$. Suppose the DFT of x is X and the DFT of k is K. Then:

$$x * k = IDFT(X \cdot K)$$

where the product is element-wise.

Relative to frequencies, there are three types of filters:

- (1) **High Pass Filters** (HPFs) are filters which preserve or amplify higher frequencies, and significantly reduce (set to 0) lower frequencies. The most simple HPF is a filter H(u,v) = 0 if $\sqrt{u^2 + v^2} \le t$ for some threshold t (since (u,v) corresponds to the frequency of the sinusoidal wave $\operatorname{cis}(ux + vy + \theta)$, which has relatively low frequency), and H(u,v) = 1 if $\sqrt{u^2 + v^2} > t$.
- (2) Low Pass Filters (LPFs) are filters which preserve or amplify lower frequencies, and set higher frequencies to 0. The most simple LPF is a filter is a filter H(u,v)=1 if $\sqrt{u^2+v^2} \le t$ and H(u,v)=0 otherwise.
- (3) **Bandpass Filters** (BPFs) are filters which preserve or amplify frequencies within a certain interval/band, and set other frequencies to 0. The most simple BPF is a filter H(u, v) = 1 if $t_1 \le \sqrt{u^2 + v^2} \le t_2$ for thresholds t_1 and t_2 and H(u, v) = 0 otherwise.

Notice that in order to approximate a discontinuity, it requires many high frequencies. So HPFs show us areas of discontinuity (or high rates of change), which correspond closely to the edges of an image. And since LPFs get rid of areas of high rate of change, they correspond to blurring the image.

A **High Frequency Emphasis** filter (HFE) is a filter of the form:

$$k_0 + k_1 H(u, v)$$

where H is a HPF. Its purpose is to preserve lower frequencies (which is the purpose of adding k_0) and emphasizes higher frequencies (the purpose of k_1H). HFEs are usually used in conjunction with histogram equalization (after filtering the image, equalize the histogram).