5 Loading airportdb into MySQL HeatWave

See Manage Data in HeatWave with Workspaces for how to load the `airportdb` database from a MySQL DB System into MySQL HeatWave on AWS.

The following procedure describes how to load the `airportdb` database from a MySQL DB System into MySQL HeatWave on OCI.

Before you begin:

- The `airportdb` database must be loaded in the MySQL DB System. If you have not done so, see Section 4, “Installation”.
- A MySQL HeatWave Cluster must be enabled for use with your MySQL DB System. For information about adding a MySQL HeatWave Cluster to a DB System, see Adding a HeatWave Cluster to a DB System.

To load the `airportdb` into MySQL HeatWave:

1. SSH to the Compute instance from your local machine using the opc user and the public IP address of the compute instance. For additional information about connecting to a Compute instance, see Connecting to an Instance.

   ```
   ssh opc@computeInstancePublicIP
   ```

2. Start MySQL Shell and connect to the MySQL DB System's Endpoint (its private IP address). For additional information about connecting to a DB System, see Connecting to the MySQL DB System with SSH and MySQL Shell.

   ```
   mysqlsh Username@IPAddressOfMySQLDBSystemEndpoint
   ```

   > **Note**
   >
   > Alternatively, you can connect to the DB System using a MySQL Client:
   >
   > ```
   > mysql --host IPAddressOfMySQLDBSystemEndpoint -u Username -p
   > ```

3. Change the MySQL Shell execution mode to SQL and run the following Auto Parallel Load command to load the `airportdb` tables into MySQL HeatWave.

```
MySQL>JS> \sql
MySQL>SQL> CALL sys.heatwave_load(JSON_ARRAY('airportdb'), NULL);
```

Tables can be unloaded from MySQL HeatWave using the following statements:

```
USE airportdb;

ALTER TABLE booking SECONDARY_UNLOAD;
ALTER TABLE flight SECONDARY_UNLOAD;
ALTER TABLE flight_log SECONDARY_UNLOAD;
ALTER TABLE airport SECONDARY_UNLOAD;
ALTER TABLE airport_reachable SECONDARY_UNLOAD;
ALTER TABLE airport_geo SECONDARY_UNLOAD;
ALTER TABLE airline SECONDARY_UNLOAD;
ALTER TABLE flightschedule SECONDARY_UNLOAD;
ALTER TABLE airplane SECONDARY_UNLOAD;
ALTER TABLE airplane_type SECONDARY_UNLOAD;
ALTER TABLE employee SECONDARY_UNLOAD;
ALTER TABLE passenger SECONDARY_UNLOAD;
ALTER TABLE passengerdetails SECONDARY_UNLOAD;
ALTER TABLE weatherdata SECONDARY_UNLOAD;
```

© 2026 Oracle