

TRUSTONIC

TTP API

Trustonic Telecom Platform API Specification v2.0

VERSION NUMBER	2.2
DATE	19 June 26
DRAFT OR RELEASED	Released - Final

Preface

This document is the confidential and proprietary information of Trustonic ("Confidential Information"). This document is protected by copyright and the information described therein may be protected by one or more EC patents, foreign patents, or pending applications. No part of the document may be reproduced or divulged in any form by any means without the prior written authorization of Trustonic. Any use of the document and the information described is forbidden (including, but not limited to, implementation, whether partial or total, modification, and any form of testing or derivative work) unless written authorization or appropriate license rights are previously granted by Trustonic.

TRUSTONIC MAKES NO REPRESENTATIONS OR WARRANTIES ABOUT THE SUITABILITY OF SOFTWARE DEVELOPED FROM THIS DOCUMENT, EITHER EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. TRUSTONIC SHALL NOT BE LIABLE FOR ANY DAMAGES SUFFERED BY LICENSEE AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THIS DOCUMENT OR ITS DERIVATIVES.

Table of Contents

Overview	9
URI Method and Definition	9
Common Data Types	9
Rate limiting of API	10
Batch Processing	11
1 Authorization	12
1.1 Get Access Token.....	12
1.1.1 REQUEST.....	12
1.1.2 RESPONSE.....	12
2 Inventory Management.....	13
2.1 Upload Devices.....	13
2.1.1 REQUEST.....	13
2.1.2 EXAMPLE.....	14
2.1.3 RESPONSE.....	15
2.2 Upload Status	16
2.2.1 REQUEST.....	16
2.2.2 RESPONSE.....	16
2.3 Transfer Devices	17
2.3.1 REQUEST.....	17
2.3.2 EXAMPLE.....	18
2.3.3 RESPONSE.....	18
2.4 Transfer Status	18
2.4.1 REQUEST.....	19
2.4.2 RESPONSE.....	19
3 Service Management.....	20
3.1 Activate.....	20
3.1.1 REQUEST.....	20
3.1.2 EXAMPLE.....	22
3.1.3 RESPONSES	22
3.2 Deactivate.....	23
3.2.1 REQUEST.....	23
3.2.2 EXAMPLE.....	24

3.2.3	RESPONSES	24
3.3	Update	25
reloadDays3.3.2	EXAMPLE.....	26
3.3.3	RESPONSES	26
3.4	Status	27
3.4.1	REQUEST.....	27
3.4.2	RESPONSE.....	28
4	Device Management.....	29
4.1	Message Device	29
4.1.1	REQUEST.....	29
4.1.2	EXAMPLE.....	29
4.1.3	RESPONSES	30
4.2	Lock Device	30
4.2.1	REQUEST.....	30
4.2.2.1	EXAMPLE OF LOCK.....	31
4.2.2.2	EXAMPLE OF TEMPORARY LOCK	31
4.2.3	RESPONSES	32
4.3	Unlock Device.....	32
4.3.1	REQUEST.....	32
4.3.2	EXAMPLE.....	33
4.3.3	RESPONSES	33
4.4	PIN Unlock	34
4.4.1	REQUEST.....	34
4.4.2	EXAMPLE.....	35
4.4.3	RESPONSES	35
4.5	Release Device	35
4.5.1	REQUEST.....	35
4.5.2	EXAMPLE.....	36
4.5.3	RESPONSES	36
4.6	Archive Device.....	37
4.6.1	REQUEST.....	37
4.6.2	EXAMPLE.....	37
4.6.3	RESPONSES	37
4.7	Reload Device.....	38
4.7.1	REQUEST.....	38
4.7.2	EXAMPLE.....	38

4.7.3	RESPONSES	39
4.8	Update Custom Property	39
4.8.1	REQUEST.....	39
4.8.2	EXAMPLE.....	40
4.8.3	RESPONSES	40
4.9	Update Device IMEI2	40
4.9.1	REQUEST.....	41
4.9.2	EXAMPLE.....	41
4.9.3	RESPONSES	41
4.10	Report/Cancel Stolen.....	42
4.10.1	REQUEST.....	42
4.10.2	EXAMPLE.....	43
4.10.3	RESPONSES	43
4.11	Lock Message	43
4.11.1	REQUEST.....	43
4.11.2	EXAMPLE.....	44
4.11.3	RESPONSES	44
4.12	Disable Sim Control	45
4.12.1	REQUEST.....	45
4.12.2	EXAMPLE.....	45
4.12.3	RESPONSES	45
4.13	Assign Sim Control.....	46
4.12.1	REQUEST.....	46
4.12.2	EXAMPLE.....	46
4.12.3	RESPONSES	47
4.14	ISMI Swap Device.....	47
4.14.1	REQUEST.....	47
4.14.2	EXAMPLE.....	47
4.14.3	RESPONSES	48
4.15	Update Expiration Time	48
4.15.1	REQUEST.....	48
4.15.2	EXAMPLE.....	49
4.15.3	RESPONSES	49
4.16	BLOCK ADB COMMAND.....	50
4.16.1	REQUEST.....	50
4.17	BLOCK AE PROVISION.....	51

4.18 BLOCK FACTORY RESET	52
4.19 Blink Reminder	54
4.19.1 REQUEST.....	54
4.19.2 EXAMPLE.....	55
4.19.3 RESPONSES	55
5 Query Management	56
5.1 Tenant Info	56
5.1.1 REQUEST.....	56
5.1.2 RESPONSES	57
5.2 Inventory Info	57
5.3.1 REQUEST.....	57
5.3.2 RESPONSES	58
5.3 Service Summary Info	58
5.3.1 REQUEST.....	58
5.3.2 RESPONSE.....	59
5.4 Device Info	59
5.4.1 REQUEST.....	59
5.4.2 EXAMPLE.....	60
5.4.3 RESPONSES	60
5.7 User Info.....	62
5.7.1 REQUEST.....	62
5.7.2 RESPONSE.....	63
5.8 State Info.....	63
5.8.1 REQUEST.....	63
5.8.2 RESPONSE.....	64
5.9 Message Template	64
5.9.1 REQUEST.....	65
5.9.2 RESPONSE.....	65
5.10 Batch Action Status.....	66
5.10.1 REQUEST.....	66
5.10.2 RESPONSE.....	66
5.11 Tac Info	67
5.11.1 REQUEST.....	67
5.10.2 RESPONSE.....	67
5.12 Sim control rule Info.....	68
5.11.1 REQUEST.....	68
5.10.2 RESPONSE.....	69

6	User Management.....	69
6.1	Add	69
6.1.1	REQUEST.....	69
6.1.2	EXAMPLE.....	70
6.1.3	RESPONSE.....	70
6.2	Deactivate.....	70
6.2.1	REQUEST.....	70
6.2.2	RESPONSE.....	71
6.3	Modify	71
6.3.1	REQUEST.....	71
6.3.2	EXAMPLE.....	72
6.3.3	RESPONSE.....	72
7	Webhook Notification API.....	73
	Callback Method	73
7.1	Create Subscription	74
7.1.1	REQUEST.....	74
7.1.2	EXAMPLE.....	75
7.1.3	RESPONSES	75
7.2	GET Subscription	75
7.2.1	REQUEST.....	76
7.2.2	RESPONSES	76
7.3	GET ALL Subscription	76
7.3.1	REQUEST.....	77
7.3.2	RESPONSES	77
7.4	Delete Subscription	77
7.4.1	REQUEST.....	77
7.4.2	RESPONSES	78
8	Contract Management.....	78
8.1	Add Contract	78
8.1.1	REQUEST.....	78
8.1.2	EXAMPLE.....	79
8.1.3	RESPONSES	79
8.2	Exit Contract	80
8.2.1	REQUEST.....	80
8.2.2	EXAMPLE.....	80
8.2.3	RESPONSES	80

8.3	Get Contract List	81
8.3.1	REQUEST.....	81
8.3.2	RESPONSES	81
8.4	Get List Device Billing Cycles.....	82
8.4.1	REQUEST.....	82
8.4.2	RESPONSES	83
8.5	Update Device Payment.....	83
8.5.1	REQUEST.....	84
8.5.2	RESPONSES	84
9	Workflow Management.....	85
9.1	Add Workflow.....	85
9.1.1	REQUEST.....	85
9.1.2	EXAMPLE.....	85
9.1.3	RESPONSES	86
9.2	Exit Workflow	86
9.2.1	REQUEST.....	86
9.2.2	EXAMPLE.....	87
8.2.3	RESPONSES	87
9.3	Get Workflow List	87
9.3.1	REQUEST.....	87
9.3.2	RESPONSES	88
10	APPENDIX.....	88
	API ERROR.....	88

Overview

This document describes the Telecoms Platform public API method and its specifications. It is intended for operators who intend to integrate with the Telecoms Platform system to manage the devices within the Telecoms Platform system. The API is designed to be simple to integrate with and provide the necessary operations to register and manage the devices within the Trustonic Telecoms platform.

URI Method and Definition

RESTful uses standard HTTP methods to operate resources. The standard HTTP methods are as follows:

Parameter	Description
HTTP Method	The following enumerated values are supported: POST: Create resources. PUT: Replace resources. PATCH: Modify resource attributes. GET: Query resources. DELETE: Delete resources.

Common Data Types

Data Type	Description
boolean	Boolean. This type applies to the service parameter/entity XML type. Only sets use the Boolean type (Boolean objects).
date	Date. Example: date in the format YYYY-MM-DD

date-time	Date and time. Example: date and time in the format YYYY-MM-DDTHH:MM:SS
list[<i>data type(length)</i>]	Data object list.
number-decimal	Decimal integer value with immutable precision, containing more than 16 significant bits. The decimal length ranges from 0 to 20.
integer	Decimal integer that consists of 0 to 10 digits.
number-long	Long decimal integer that consists of 10 to 20 digits.
number-float	Single-precision floating-point decimal number that consists of 0 to 10 digits. Enter two numbers separated by a comma (.). The two numbers indicate precision and scale, respectively. For example, 6,4 indicates number-float(6,4).
number-double	Double-precision floating-point number, which contains 10 to 20 digits. Enter two numbers separated by a comma (.). The two numbers indicate precision and scale, respectively. For example, 20,4 indicates number-double(20,4).
text / string	Text type. For example, text(50) indicates that the text contains a maximum of 50 characters.
time	Time. Example, time in the format HH:MM:SS

Rate limiting of API

A "rate limit" is the number of API calls that can be made within a given time period.

It helps us provide reliable and scalable API services to protect your operation from erratic and unpredictable spikes in the rate of requests.

Telecoms Platform sets the rate limit such that an API can be called up to **100 times/minute** using the single API token.

If your application exceeds the request limits detailed above, the Telecoms Platform will return a 429 — "Too Many Requests" error message and the new API calls will need to be made again.

Batch Processing

The Device management APIs support Batch Processing and it is designed to handle bulk requests efficiently. Depending on the size of the list in the request body, the processing is handled either synchronously or asynchronously.

- **Synchronous Processing:**
If the request contains a list with fewer than or equal to 100 items, the system processes the request synchronously and returns a response with the result directly.
- **Asynchronous Processing:**
If the request contains a list with more than 100 items, the system processes the request asynchronously. In this case, the API returns additional parameter batchActionId and batchActionStatus. batchActionId can be used to query the status of the batch operation status using Batch Action status (GET /api/v2/query/batchAction) API.

1 Authorization

1.1 Get Access Token

API-Key will be used to get the Access/Bearer Token from Telecoms Platform. API-Key is unique per user account in Telecoms Platform. Depends on the user access role in Telecoms Platform, Access/Bearer Token can be used for multiple tenants. User can use the tenantId in request header to perform the API Operation for specific tenant. When tenantId is not included in the Header, API operation will be performed on the users default tenant account.

POST api/v2/authorization/token

1.1.1 REQUEST

Request Header

apiKey	API-Key from Telecoms Platform
--------	--------------------------------

1.1.2 RESPONSE

[Response Header](#)

Response Body

token	Token generated for authentication.
expireTime	Date of expiration of token in ISO 8601 format in UTC timezone YYYY-MM-DDTHH:MM:SS.ssssss±HH:MM Example : 2024-08-20T16:50:15.764436+00:00

Token received must be used as **Authorization bearer** in all API Method's Header.

2 Inventory Management

2.1 Upload Devices

To upload devices to Telecoms Platform Inventory. Single or Multiple devices can be uploaded into Telecoms Platform.

POST `api/v2/inventory/upload`

2.1.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

deviceList	Array of objects (deviceList)
*required	A list of devices to be uploaded. List size min = 1, max = 10,000
* deviceUid	IMEI or serial number used to uniquely identify a device.
* idType	Type of the Device Unique Identifier Enum {imei, serialNo}
* deviceType	Type of the Device Enum {tablet, smartphone}
additionalInfo <i>Json Object</i>	[optional] Additional information such as custom properties can be specified in Key Value pair Ex : { "imei2": "352887771751553", "expiry": 1711731594000}

	reloadDays	[optional] Number of days to extend the prepaid service validity. Applicable only for DeviceFinancing when paymentMethod is prepaid
	contractId	[Optional] Sequence number of contract to be assigned to the device.
	assignedContractDate	[Conditional] The start date of the contract. Required If contractId is assigned to Device
	workflowId	[Optional] Sequence number of workflow to be assigned to the device.
	reloadTime	[Optional] The reload time for prepaid workflows. Accepted values 1 to 1095
	reloadTimeUnit	[Optional] Unit of the reload time. Supported values hour, day, week, month, year
	simControlRuleId	Sim Control Rule ID to be applied to the device
	serviceList	Service Object List [optional] If serviceName is not provided, device will be loaded only in Inventory
	* serviceName	Enum {supplyChain, deviceFinancing, simControl, theftProtection, subsidyProtection} Name of service to be deactivated from the device.
	serviceTenure	String The length of the service in Months of the services
	paymentMethod	Enum {prepaid, postpaid} Default is postpaid Payment mode of the contract. Required when serviceType is deviceFinancing.

2.1.2 EXAMPLE

```
{
  "deviceList":[
    {
      "deviceUid":"453700000000106",
      "idType":"imei",
      "deviceType":"smartphone",
      "additionalInfo":{
        "imei2":"352887771751553",
        "expiry":"1711731594000"
      }
    }
  ]
}
```

```

    }
  },
  {
    "deviceUid":"453700000000107",
    "idType":"imei",
    "deviceType":"smartphone",
    "serviceList":[
      {
        "serviceName":"deviceFinancing"
      }
    ]
  }
]
}

```

2.1.3 RESPONSE

Response Header

Response Body

uploadId	upload id for the device upload
tenantName	Name of the Tenant
uploadChannel	Channel used to upload request. i.e., API or GUI
uploadStatus	Status of the upload. For asynchronous (batch) request, the status will most likely be in progress when the API returns its result.
totalDeviceCount	Total number of devices in the request
validDeviceCount	Number of valid devices for upload
invalidDeviceCount	Number of rejected devices
deviceList	Device Object List Details of all devices processed in this request. Device Object list will be populated for each serviceType activated for the device
deviceUid	Device Unique ID
uploadStatus	Status of the device upload [COMPLETED/ INPROGRESS / FAILED]
serviceName	Name of the service
serviceStatus	Status of the service activation [COMPLETED/ INPROGRESS / FAILED]
resultCode	Result Code when upload is failed
resultMessage	Result Message when upload is failed

2.2 Upload Status

To check the status of the device upload request.

```
GET api/v2/inventory?uploadId={uploadId}
```

2.2.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Parameter

uploadId *required	Upload id of the device upload operation.
pageNum [Optional]	Default: 1 The page number to get, which must be >= 1.
pageSize [Optional]	Default: 1000, Maximum = 1000 The number of items in a page, which must be >0 and <= 1000.

2.2.2 RESPONSE

[Response Header](#)

Response Body

uploadId	upload id for the device upload
tenantName	Name of the Tenant
uploadChannel	Channel used to upload request. i.e., API or GUI

uploadStatus	Status of the upload. For asynchronous (batch) request, the status will most likely be in progress when the API returns its result.
totalDeviceCount	Total number of devices in the request
validDeviceCount	Number of valid devices for upload
invalidDeviceCount	Number of rejected devices
deviceList	Device Object List Details of all devices processed in this request. Device Object list will be populated for each serviceType activated for the device
deviceUid	Device Unique ID
uploadStatus	Status of the device upload [COMPLETED/ INPROGRESS / FAILED]
serviceName	Name of the service activated for device
serviceStatus	Status of the service activation [COMPLETED/ INPROGRESS / FAILED]
resultCode	Result Code when upload is failed
resultMessage	Result Message when upload is failed

2.3 Transfer Devices

To move the devices from a inventory to other child workspace inventory. Moving devices between workspaces is only permitted when the devices are in an Idle state.

POST api/v2/inventory/transfer

2.3.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed. Parent tenant ID

Request Body

*	targetTenantId	Tenant ID of the child workspace to move the devices
	transferDeviceList	Array of objects (deviceList)
	*required	A list of devices to be uploaded. List size min = 1, max = 10,000
*	deviceUid	IMEI or serial number used to uniquely identify a device.

2.3.2 EXAMPLE

```
{
  "targetTenantId": "tenant-1"
  "transferDeviceList": [
    {
      "deviceUid": "453700000000106"
    },
    {
      "deviceUid": "453700000000107"
    }
  ]
}
```

2.3.3 RESPONSE

Response Header

Response Body

transferId		Transfer ID of the device transfer operation
tenantName		Name of the Root Tenant
targetTenantName		Name of the child Tenant
transferStatus		Status of the transfer. For asynchronous (batch) request, the status will most likely be in progress when the API returns its result.
transferResponseList		Device Object List
		Details of all devices processed in this request.
	deviceUid	Device Unique ID
	resultCode	Result Code when upload is failed
	resultMessage	Result Message when upload is failed

2.4 Transfer Status

To check the status of the device upload request.

GET api/v2/inventory/transfer?transferId={transferId}

2.4.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Parameter

transferId	Transfer id of the device transfer operation.
*required	

2.4.2 RESPONSE

Response Header

Response Body

transferId	transfer ID of the device transfer operation
tenantName	Name of the Root Tenant
targetTenantName	Name of the child Tenant
transferStatus	Status of the transfer. For asynchronous (batch) request, the status will most likely be in progress when the API returns its result.
totalDeviceCount	Total number of devices in the request
transferResponseList	Device Object List Details of all devices processed in this request.
deviceUid	Device Unique ID
resultCode	Result Code when upload is failed
resultMessage	Result Message when upload is failed

3 Service Management

3.1 Activate

To activate new service for the device which is successfully uploaded in Telecoms Platform inventory. Below is the list of services device can be enrolled.

1. Device Financing
2. Supply chain
3. SIM Control
4. Theft Protection
5. Subsidy Protection

POST api/v2/service/activate

3.1.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

deviceList	Device Object List
*required	A list of devices to be uploaded. List size min = 1, max = 10,000
* deviceUid	String IMEI or serial number used to uniquely identify a device.

		Sales channel type. The options are as follows:- POS CRM APP
	accessChannelType additionalInfo Json Object	Additional information such as custom properties can be specified in Key Value pair Ex : {"expiry": 1711731594000}
	reloadDays	[optional] Number of days to extend the prepaid service validity. Applicable only for DeviceFinancing when paymentMethod is prepaid
	contractId	[Optional] Sequence number of contract (Ex: 1, 2, 3,). [Required] If user want to assign workflow to device via upload
	assignedContractDate	[Conditional] The start date of the contract. [Required] If user want to assign workflow to device via upload
	workflowId	[Optional] Sequence number of workflow (Ex: 1, 2, 3,).
	reloadTime	[Optional] The reload time for prepaid workflows. Accept values from 1 to 1095 days.
	reloadTimeUnit	[Optional] The reload time unit for prepaid workflows. ENUM { hour, day, week, month, year }
	simControlRuleId	Sim Control Rule ID to be applied to the device
*	serviceList	Service Object List
	* serviceName	Enum {supplyChain, deviceFinancing, simControl, theftProtection, subsidyProtection} Type of service to be activated for the device.
	serviceTenure	String The length of the service in Months of the services

		paymentMethod	Enum {prepaid, postpaid} Default is postpaid Payment mode of the contract. Required when serviceType is deviceFinancing.
--	--	---------------	---

3.1.2 EXAMPLE

```
{
  "deviceList":[
    {
      "deviceUid":"453700000000101",
      "serviceList":[
        {
          "serviceName":"deviceFinancing",
          "serviceTenure":12,
          "paymentMethod":"postpaid"
        }
      ]
    },
    {
      "deviceUid":"453700000000102",
      "reloadDays":30,
      "serviceList":[
        {
          "serviceName":"deviceFinancing",
          "serviceTenure":12,
          "paymentMethod":"prepaid"
        }
      ]
    }
  ]
}
```

3.1.3 RESPONSES

Response Header

Response Body

serviceOrderId	order id for the service activate request
serviceOrderStatus	Status of the service order request. For asynchronous request the status will most likely be in progress when the API returns its result.
tenantName	Name of the Tenant
deviceList	Device Object List
deviceUid	String IMEI or serial number used to uniquely identify a device.

	serviceList	Service Object List
	serviceName	Name of Financing service activated for the device.
	resultCode	Result Code
	resultMessage	Result Message

3.2 Deactivate

To remove the device from the service after completion of service tenure or to withdraw the device from the service.

DELETE api/v2/service

3.2.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

deviceList	Device List Object
*required	A list of devices to be uploaded. List size min = 1, max = 10,000
* deviceUid	String IMEI or serial number used to uniquely identify a device.
* serviceList	Service List Object

	*	serviceName	Enum {supplyChain, deviceFinancing, simControl, theftProtection, subsidyProtection} Name of service to be deactivated from the device.
		paymentMethod	ENUM {prepaid, postpaid} Default is postpaid Payment mode of the contract. Required when serviceType is deviceFinancing.
	*	deactivateReason	Reason for deactivation the device from service. ENUM {tenureEnd, soldForCash, cancel, lost, stolen, other}
		additionalRemarks	Additional remarks for the releasing the device from the service

3.2.2 EXAMPLE

```
{
  "deviceList":[
    {
      "deviceUid":"453700000000101",
      "serviceList":[
        {
          "serviceName":"deviceFinancing",
          "deactivateReason":"soldForCash",
          "additionalRemarks":"Customer paid for the device"
        },
        {
          "serviceName":"simControl",
          "deactivateReason":"soldForCash",
          "additionalRemarks":"Customer paid for the device "
        }
      ]
    },
    {
      "deviceUid":"453700000000101",
      "serviceList":[
        {
          "serviceName":"deviceFinancing",
          "deactivateReason":"tenureEnd",
          "additionalRemarks":"Customer paid for the device"
        }
      ]
    }
  ]
}
```

3.2.3 RESPONSES

Response Header

Response Body

serviceOrderId	order id for the service deactivate request	
serviceOrderStatus	Status of the service order request. For asynchronous request the status will most likely be in progress when the API returns its result.	
tenantName	Name of the Tenant	
deviceList	Device Object List	
	deviceUid	String IMEI or serial number used to uniquely identify a device.
	serviceList	Service Object List
	serviceName	Name of Financing service to be deactivated from the device.
	resultCode	Result Code
	resultMessage	Result Message

3.3 Update

To update the service details of the device.

PATCH api/v2/service/

3.3.1.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token>
	Token generated using Authorization API Call.
tenantId	Tenant ID
	Tenant ID in which API Method operation to be performed

Request Body

deviceList	Device Object List
*required	A list of devices to be uploaded. List size min = 1, max = 10,000

*	deviceUid	String IMEI or serial number used to uniquely identify a device.
	additionalInfo	[optional] Additional information such as custom prosperities of the device in Key Value pair
	reloadDays	[optional] Number of days to extend the prepaid service validity
*	serviceList	Service Object List
	serviceName	Enum {supplyChain, deviceFinancing, simControl, theftProtection, subsidyProtection} Type of Financing Contract to be applied for the device. More than one contract can be applied to device
	serviceTenure	String The length of the service in Months of the services
	paymentMethod	ENUM {prepaid, postpaid} Default is postpaid Payment mode of the contract

3.3.2 EXAMPLE

```
{
  "deviceList":[
    {
      "deviceUid":"453700000000101",
      "additionalInfo": {},
      "reloadDays": 1,
      "serviceList":[
        {
          "serviceName":"deviceFinancing",
          "serviceTenure":"36",
          "paymentMethod":"prepaid"
        }
      ]
    }
  ]
}
```

3.3.3 RESPONSES

Response Header

Response Body

serviceOrderId	order id for the service activate request
serviceOrderStatus	Status of the service order request. For asynchronous request the status will most likely be in progress when the API returns its result.
tenantName	Name of the Tenant
deviceList	Device Object List
deviceUid	String IMEI or serial number used to uniquely identify a device.
serviceList	Service Object List
serviceName	Name of Financing service activated for the device.
resultCode	Result Code
resultMessage	Result Message

3.4 Status

To check the status of the service activation/deactivation request.

```
GET api/v2/service?serviceOrderId={serviceOrderId}
```

3.4.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Parameter

serviceOrderId	int
*required	Order id for the service request.

pageNum	Default: 1
[Optional]	The page number to get, which must be ≥ 1 .
pageSize	Default: 1000, Maximum = 1000
[Optional]	The number of items in a page, which must be >0 and ≤ 1000 .

3.4.2 RESPONSE

Response Header

Response Body

tenantName	Name of the Tenant
orderChannel	Channel used to upload request. i.e., API or GUI
orders	Number of service request.
orderStatus	Status of the service request.
totalServiceCount	Total number of Service in the request
successServiceCount	Number of valid Service for the devices
failedServiceCount	Number of rejected Service
deviceList	Device Object List Details of all devices processed in this request.
deviceUid	Device Unique ID
serviceName	Name of the service activated for the device
serviceType	Type of Service
resultCode	Result Code
resultMessage	Result Message

4 Device Management

4.1 Message Device

To send Notification or warning message to the device

POST api/v2/device/notify/

4.1.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

messageList	Message Object List
* deviceUid	Device Unique ID
notificationType	ENUM {headsUp, fullscreen} Type of Notification Message, Default headsUp
messageTemplateId	ID of the message template to be send to device in <i>DPC/DLC solution</i>
notificationTitle	Title of the Notification Message <i>For DPC/DLC solution, notification title should match the title pre-configured in UI. Title details can be queried using Message Template API.</i>
notificationContent	Notification Message Content
<i>Note : Either messageTemplateId or notificationTitle must be provided in the request. At least one of these parameters is required to send the Notification message to the device.</i>	

4.1.2 EXAMPLE

```

{
  "messageList": [
    {
      "deviceId": "453700000000101",
      "notificationType": "headsip",
      "notificationTitle": "Payment Reminder-1",
      "notificationContent": "Reminder for the Payment"
    }
  ]
}

```

4.1.3 RESPONSES

Response Header

Response Body

batchActionId [optional]	Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
batchActionStatus [optional]	Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}
messageResponseList	Message Response Object List
* deviceId	Device Unique ID
resultCode	Result Code
resultMessage	Result Message

4.2 Lock Device

To lock the device.

POST api/v2/device/lock/

4.2.1 REQUEST

Request Header

Parameter	Parameter Description
-----------	-----------------------

Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

lockList		Lock Object List
*	deviceId	Device Unique ID
	lockType [Optional]	It is an optional parameter and default value is lock ENUM {lock, temporaryLock}
	lockDuration [*required if lockType is temporaryLock]	Duration for temporary lock.
	lockDurationTimeUnit [*required if lockType is temporaryLock]	This field allows specifying the time unit for lockDuration, default value is minute. ENUM {minute, hour}
	lockMsgTitle	Title of the Lock Message. *Not applicable for all OEMs
	lockMsgContent	Lock Message Content

4.2.2.1 EXAMPLE OF LOCK

```
{
  "lockList":[
    {
      "deviceId":"453700000000101",
      "lockType":"lock",
      "lockMsgTitle":"Payment Due",
      "lockMsgContent":"Payment is Due"
    }
  ]
}
```

4.2.2.2 EXAMPLE OF TEMPORARY LOCK

```
{
  "lockList":[
    {
```

```

        "deviceUid":"453700000000101",
        "lockType":"temporaryLock",
        "lockDuration": 15,
        "lockDurationTimeUnit": "minute",
        "lockMsgTitle":"Payment Due",
        "lockMsgContent":"Payment is Due"
    }
]
}

```

4.2.3 RESPONSES

Response Header

Response Body

batchActionId [optional]		Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
batchActionStatus [optional]		Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}
lockResponseList		Lock Response Object List
*	deviceUid	Device Unique ID
	resultCode	Result Code
	resultMessage	Result Message

4.3 Unlock Device

To unlock the device from locking state after the successful payment

POST api/v2/device/unlock/

4.3.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token>
	Token generated using Authorization API Call.

tenantId	Tenant ID Tenant ID in which API Method operation to be performed
----------	--

Request Body

unLockList	UnLock Object List
* deviceId	Device Unique ID
validityDays	Number of days for applying next lock, applicable only for prepaid.
nextDue	Timestamp to extend the service validity, format UNIX timestamp.
	nextDue or validityDays is mandatory for PAYG device unlock.

4.3.2 EXAMPLE

```
{
  "unLockList": [
    {
      "deviceId": "453700000000101"
    },
    {
      "nextDue": 1706703215,
      "deviceId": "453700000000102"
    },
    {
      "deviceId": "453700000000103",
      "validityDays": 1
    }
  ]
}
```

4.3.3 RESPONSES

Response Header

Response Body

batchActionId [optional]	Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
batchActionStatus [optional]	Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}

unlockResponseList	Unlock Response Object List
deviceUid	Device Unique ID
resultCode	Result Code
resultMessage	Result Message

4.4 PIN Unlock

To unlock a device using unlock pin in offline mode by requesting the unlock PIN.

To release a device using release pin in offline mode by requesting the release PIN. (Only support Postpaid service and DLC/DPC devices)

POST api/v2/device/pinunlock/

4.4.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

pinUnlockList	pinUnlock Object List
* deviceUid	Device Unique ID
challenge	Code display on the device when it is locked. Code is used as part of the security to verify the device user provided a PIN to unlock the device. This is applicable to selected OEMs.
validity	Expiry Time of Unlock PIN. Unit days This is applicable to selected OEMs.

	userSerial	Unique identifier on multi-user devices. This parameter allows to identify the users when multiple user profiles exist on the device. It is optional parameter. If omitted, the system assumes a single-user context by default.
--	------------	--

4.4.2 EXAMPLE

```
{
  "pinUnlockList":[
    {
      "deviceUid":"453700000000101"
    },
    {
      "challenge":"123456",
      "deviceUid":"453700000000102",
      "validity":"1"
    }
  ]
}
```

4.4.3 RESPONSES

[Response Header](#)

Response Body

pinUnlockResponseList		PinUnlock Object List
	deviceUid	Device Unique ID
	challengePin	Offline Unlock Pin to unlock the device.
	resultCode	Result Code
	resultMessage	Result Message

4.5 Release Device

To Release device from Telecoms Platform. Device cannot be re-enrolled into any services after it is released.

PUT api/v2/device/release/

4.5.1 REQUEST

Request Header

Parameter	Parameter Description
-----------	-----------------------

Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

deviceReleaseList	Release Object List
* deviceUid	Device Unique ID
reason	The Reason for releasing the device

4.5.2 EXAMPLE

```
{
  "deviceReleaseList": [
    {
      "deviceUid": "453700000000101"
    },
    {
      "reason": "End of Tenure",
      "deviceUid": "453700000000101"
    }
  ]
}
```

4.5.3 RESPONSES

Response Header

Response Body

batchActionId [optional]	Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
batchActionStatus [optional]	Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}
releaseResponseList	Release Response Object List

*	deviceId	Device Unique ID
	resultCode	Result Code
	resultMessage	Result Message

4.6 Archive Device

To archive the device from inventory. After device is archived, it cannot be assigned to any services.

POST api/v2/device/archive/

4.6.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

archiveList		Archive Object List
*	deviceId	Device Unique ID

4.6.2 EXAMPLE

```
{
  "archiveList": [
    {
      "deviceId": "453700000000101"
    },
    {
      "deviceId": "453700000000102"
    }
  ]
}
```

4.6.3 RESPONSES

Response Header

Response Body

archiveResponseList	Archive Response Object List
deviceUid	Device Unique ID
resultCode	Result Code
resultMessage	Result Message

4.7 Reload Device

To update the active PAYG device next payment due date.

POST api/v2/device/reload/

4.7.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to e performed

Request Body

reloadList	Reload Object List
* deviceUid	Device Unique ID
nextDue	Timestamp to extend the service validity, format UNIX timestamp.
reloadDays	Number of days to extend the service validity.
	Note : Either nextDue or reloadDays is mandatory to apply reload action.

4.7.2 EXAMPLE

```
{  
  "reloadList":[
```

```

    {
      "nextDue":1706703215,
      "deviceId":"453700000000101"
    },
    {
      "deviceId":"453700000000102",
      "reloadDays":30
    }
  ]
}

```

4.7.3 RESPONSES

Response Header

Response Body

batchActionId [optional]	Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
batchActionStatus [optional]	Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}
reloadResponseList	Reload Response Object List
deviceId	Device Unique ID
resultCode	Result Code
resultMessage	Result Message

4.8 Update Custom Property

To update the custom property of the device. Custom property will be added to device if does not exists for the device.

PUT api/v2/device/customproperty/

4.8.1 REQUEST

Request Header

Parameter	Parameter Description
-----------	-----------------------

Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to e performed

Request Body

customList	Custom Object List
* deviceUid	Device Unique ID
* customProperty	Custom prosperities to be updated. Value should be in Key Value pair Ex : { "Account number": "123456", "Eligibility Check" : True }

4.8.2 EXAMPLE

```
{
  "customList": [
    {
      "deviceUid": "453700000000101",
      "customProperty": {
        "Account number": "123456"
      }
    }
  ]
}
```

4.8.3 RESPONSES

Response Header

Response Body

customResponseList	Custom Response Object List
deviceUid	Device Unique ID
resultCode	Result Code
resultMessage	Result Message

4.9 Update Device IMEI2

To update or add the IMEI2 of the device.

PUT api/v2/device/info/

4.9.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

deviceList		Device Object List
*	deviceUid	Device Unique ID
*	imei2	IMEI2 number of the Device

4.9.2 EXAMPLE

```
{
  "deviceList": [
    {
      "deviceUid": "453700000000106",
      "imei2": "453700000000107"
    }
  ]
}
```

4.9.3 RESPONSES

Response Header

Response Body

batchActionId [optional]	Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
-----------------------------	--

batchActionStatus [optional]	Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}
deviceResponseList	Device Response Object List
deviceUid	Device Unique ID
resultCode	Result Code
resultMessage	Result Message

4.10 Report/Cancel Stolen

To Report or Reset the device stolen status.

POST api/v2/device/theft/

4.10.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

theftDeviceList	Theft Device Object List
* deviceUid	Device Unique ID
* action	Type of action to be applied. ENUM { report, reset } report – Reported Stolen, can be applied only for Protected devices. reset – Reset to Protected, can be applied only for locked devices.

4.10.2 EXAMPLE

```
{
  "theftDeviceList":[
    {
      "deviceId":"453700000000101",
      "action":"report"
    },
    {
      "deviceId":"453700000000102",
      "action":"reset"
    }
  ]
}
```

4.10.3 RESPONSES

Response Header

Response Body

theftResponseList		Lock Response Object List
*	deviceId	Device Unique ID
	resultCode	Result Code
	resultMessage	Result Message

4.11 Lock Message

To send message to the locked device

POST api/v2/device/lockMessage/

4.11.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

lockMessageList		Message Object List
*	deviceId	Device Unique ID
	messageTemplateId	ID of the lock message template to be send to device in <i>DPC/DLC solution</i>
	messageTitle	Title of the Lock Message <i>For DPC/DLC solution, notification title should match the title pre-configured in UI. Title details can be queried using Message Template API.</i>
	messageContent	Lock Message Content
<i>Note : Either messageTemplateId or messageTitle must be provided in the request. At least one of these parameters is required to send a Lock message to the device. If both are missing, the system will return</i>		

4.11.2 EXAMPLE

```
{
  "LockMessageList": [
    {
      "deviceId": "453700000000101",
      "messageTitle": "Device Lock",
      "messageContent": "Please make payment to unlock the device"
    }
  ]
}
```

4.11.3 RESPONSES

[Response Header](#)

Response Body

batchActionId [optional]	Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
batchActionStatus [optional]	Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}

messageResponseList	Message Response Object List
* deviceUid	Device Unique ID
resultCode	Result Code
resultMessage	Result Message

4.12 Disable Sim Control

To disable the Sim Control rule of the device

POST api/v2/device/disableSimControlRule

4.12.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

deviceList	Message Object List
* deviceUid	Device Unique ID

4.12.2 EXAMPLE

```
{
  "deviceList":[
    {
      "deviceUid":"453700000000101"
    }
  ]
}
```

4.12.3 RESPONSES

Response Header

Response Body

simControlRuleResponseList		Sim Control Rule Disable Response Object List
*	deviceUid	Device Unique ID
	resultCode	Result Code
	resultMessage	Result Message

4.13 Assign Sim Control

To assign the Sim Control rule to the device

POST api/v2/device/assignSimControlRule

4.12.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token>
	Token generated using Authorization API Call.
tenantId	Tenant ID
	Tenant ID in which API Method operation to be performed

Request Body

deviceList		Message Object List
*	deviceUid	Device Unique ID
*	simControlRuleId	Id of sim control rule

4.12.2 EXAMPLE

```
{
  "deviceList": [
    {
      "deviceUid": "453700000000101",
      "simControlRuleId": "Postpaid_v3"
    }
  ]
}
```

4.12.3 RESPONSES

Response Header

Response Body

simControlRuleResponseList		Sim Control Rule Assign Response Object List
*	deviceUid	Device Unique ID
	resultCode	Result Code
	resultMessage	Result Message

4.14 ISMI Swap Device

To swap the IMSI SIM in device

POST api/v2/device/imsiSwap

4.14.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

imsiSwapList		Message Object List
*	deviceUid	Device Unique ID

4.14.2 EXAMPLE

```
{
  "imsiSwapList": [
    {
      "deviceUid": "453700000000101"
    }
  ]
}
```

```
}  
]
```

4.14.3 RESPONSES

Response Header

Response Body

batchActionId [optional]	Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
batchActionStatus [optional]	Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}
imsiSwapResponseList	IMSI Swap Response Object List
* deviceUid	Device Unique ID
resultCode	Result Code
resultMessage	Result Message

4.15 Update Expiration Time

To updates a device's expiration timestamp (and optional custom properties)

POST api/v2/device/updateExpiration

4.15.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

updateExpirationList		Update Expiration List
*	deviceUid	Device Unique ID (IMEI or Serial number of the device)
*	expiration	New expiration value (UNIX timestamp or ISO 8601 datetime).
	customProperty	Optional custom key–value pairs to update

4.15.2 EXAMPLE

```
{
  "updateExpirationList": [
    {
      "deviceUid": "350266809906657",
      "expiration": 1759925447,
      "customProperty": {
        "Account Number": "12321321311"
      }
    }
  ]
}
```

4.15.3 RESPONSES

Response Header

Response Body

batchActionId [optional]		Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
batchActionStatus [optional]		Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}
updateExpirationResponseList		Update Expiration Response Object List
*	deviceUid	Device Unique ID
	resultCode	Result Code
	resultMessage	Result Message

Response Example

```
{
  "updateExpirationResponseList": [
```

```

{
  "deviceUid": "350266809906657",
  "resultCode": "REQUEST_SUCCESS",
  "resultMessage": "Request is successful"
}
]
}

```

4.16 BLOCK ADB COMMAND

Enable/disable Block ADB Command on KG devices for a device UID.

POST api/v2/device/blockADB

4.16.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

ADBPropertyList		Message Object List
*	deviceUid	Device Unique ID
*	blockADB	Boolean

4.16.2 EXAMPLE

```

{
  "ADBPropertyList": [
    {
      "blockADB": true,
      "deviceUid": "string"
    }
  ]
}

```

4.16.3 RESPONSES

Response Header

Response Body

batchActionId [optional]	Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
batchActionStatus [optional]	Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}
blockADBResponseList	ADB Property Response Object List
* deviceUid	IMEI1 of The Device
resultCode	Result Code
resultMessage	Result Message

4.17 BLOCK AE PROVISION

Enable/disable Block AE Provision on KG devices for a device UID

POST api/v2/device/blockAEProvision

4.17.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

AE PROVISION PROPERTY LIST	Message Object List
* deviceUid	Device Unique ID

*	blockAEProvision	Boolean
---	------------------	---------

4.17.2 EXAMPLE

```
{
  "aeProvisionPropertyList": [
    {
      "blockAEProvision": true,
      "deviceUid": "string"
    }
  ]
}
```

4.17.3 RESPONSES

Response Header

Response Body

batchActionId [optional]	Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
batchActionStatus [optional]	Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}
blockAEProvisionResponseList	AE Provision Property Response Object List
* deviceUid	IMEI1 of The Device
resultCode	Result Code
resultMessage	Result Message

4.18 BLOCK FACTORY RESET

Enable/disable Block Factory Reset on KG devices for a device UID.

POST api/v2/device/blockFactoryReset

4.18.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

factoryResetPropertyList		Message Object List
*	deviceUid	Device Unique ID
*	blockfactoryReset	Boolean

4.18.2 EXAMPLE

```
{
  "factoryResetPropertyList": [
    {
      "blockFactoryReset": true,
      "deviceUid": "string"
    }
  ]
}
```

4.18.3 RESPONSES

Response Header

Response Body

batchActionId		Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
[optional]		
batchActionStatus		Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}
[optional]		
blockFactoryResetResponseList		Factory Reset Property Response Object List
*	deviceUid	IMEI1 of The Device

	resultCode	Result Code
	resultMessage	Result Message

4.19 Blink Reminder

To set the blinking reminder for sending the repeated notifications

POST /api/v2/device/blinkReminder

4.19.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

Parameter		Description
*	deviceId	IMEI or serial number used to uniquely identify a device
*	interval	integer <int64> [3 .. 86400] Time in seconds (max 24 hours) between notification reminders.
*	message	string Message to display on the device. Limit 200 characters.
*	title	string Title to display on the device. Limit 200 characters.

	timeLimit	Array of integers <int32> [items <int32 >] Set this value to [23, 7] when you want to disable the blinking reminder from 11 PM to 7 AM. If 'timeLimitEnable' or 'daysLimitEnable' is 'true', this field is mandatory. Array size must be 2, the values of timeLimit must be between 0 and 23.
	dayLimit	Array of integers <int32> [items <int32 >] Set this value to [0, 1] when you want to disable the blinking reminder from Sunday to Monday (0: Sunday, 1: Monday ... and 6:Saturday). If 'daysLimitEnable = true', this field is mandatory. Array size must be 2, the values of daysLimit must be between 0 and 6.
	timeLimitEnabled	boolean Used to disable the blinking reminder for a specific time. If this value is true, timeLimit field is required. Example: disable blinking reminder from 11PM - 7AM; timeLimitEnable:true, daysLimitEnable:false, timeLimit:[23,7], daysLimit:null
	dayLimitEnabled	boolean Used to disable the blinking reminder on specific days and hours. If this value is true, timeLimit and daysLimit fields are required. Example: disable blinking reminder from 6AM SUN- 7AM MON; timeLimitEnable:false, daysLimitEnable:true, timeLimit:[6,7], daysLimit:[0,1]

4.19.2 EXAMPLE

```
{
  "blinkReminderList": [
    {
      "deviceId": "device unique id",
      "interval": integer (from 3 to 86400 second),
      "timeLimit": [0, 23],
      "dayLimit": [0, 6],
      "timeLimitEnable": bool,
      "dayLimitEnable": bool,
      "message": "string"
    }
  ]
}
```

4.19.3 RESPONSES

Response Header

Response Body

batchActionId [optional]	Unique identifier for the batch action that is generated when the request body contains a list with more than 100 items. This ID can be used to track the status of the batch operation through Batch Action Status endpoints.
batchActionStatus [optional]	Indicates the current processing status of the batch action when the request body contains more than 100 items. ENUM {INPROGRESS, COMPLETED, FAILED}
updateExpirationResponseList	Update Expiration Response Object List
* deviceUid	Device Unique ID
resultCode	Result Code
resultMessage	Result Message

5 Query Management

5.1 Tenant Info

To get the list of tenant information can be accessed using the API Key.

GET api/v2/query/tenant/

5.1.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.

5.1.2 RESPONSES

Response Header

Response Body

tenantList	Tenant Object List
tenantId	Unique ID of the Tenant to be used on Header message
tenantName	Name of the Tenant

5.2 Inventory Info

To get the inventory information of the Tenant.

GET
api/v2/query/inventory?deviceType={deviceType}&deviceManufacturer={deviceManufacturer}&deviceModel={deviceModel}

5.3.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer Token.
	Token generated using Authorization API Call.
tenantId	Tenant ID
	Tenant ID in which API Method operation to be performed

Parameter (optional)

deviceType	Type of the Device
	Enum {smartphone, tablet}
deviceManufacturer	Device Manufacturer Name
deviceModel	Device Model Name

If parameter is not passed, all device will be considered in summary.

5.3.2 RESPONSES

Response Header

Response Body

tenantName	Name of the Tenant
totalDeviceCount	Number of Devices uploaded into telecoms platform
idleDeviceCount	Number of Idle Device in inventory which is not provisioned to any service.
serviceDeviceCount	Number of Devices provisioned with services.

5.3 Service Summary Info

To get the device summary of the services.

```
GET api/v2/query/service?serviceName={serviceName}
GET api/v2/query/service?serviceName={serviceName}&deviceType={deviceType}
GET
api/v2/query/service?serviceName={serviceName}&paymentMethod={paymentMethod}
```

5.3.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token>
	Token generated using Authorization API Call.
tenantId	Tenant ID
	Tenant ID in which API Method operation to be performed

Parameter

*	serviceName	Name of the Services
		Enum {supplyChain, deviceFinancing, simControl, theftProtection, subsidyProtection}

	deviceType	Type of the Device Enum {smartphone, tablet}
	paymentMethod	Enum {prepaid, postpaid} Default is postpaid Payment mode of the contract. Required when serviceType is DeviceFinancing.

5.3.2 RESPONSE

Response Header

Response Body

Parameter			Parameter Description
tenantName			Name of the Tenant
serviceSummaryList			Service Summary Object List
	serviceTypeList		Type of Financing service applied for the device.
		stateDeviceInfoList	Device State Info Object List
			Number of Devices in each state in the service. Key value Pair
		stateDeviceInfo	Example Ready for use:50

5.4 Device Info

To get details about the devices from Telecoms Platform.

POST api/v2/query/devices

5.4.1 REQUEST

Request Header

Parameter	Parameter Description
-----------	-----------------------

Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

Parameter	Parameter Description
deviceList	Array of objects (deviceList) A list of devices to be uploaded. List size min = 1, max = 10,000
* deviceUid	IMEI or serial number used to uniquely identify a device.

5.4.2 EXAMPLE

```
{
  "deviceList": [
    {
      "deviceUid": "453700000000101"
    },
    {
      "deviceUid": "453700000000102"
    }
  ]
}
```

5.4.3 RESPONSES

Response Header

Response Body

deviceResponseList	Array of Device objects
deviceUid	Device Unique ID
imei2	IMEI2 of the Device
tenantName	Name of the Tenant
currentPolicy	The current policy of the device
tac	TAC Information Object
lastCheckIn	Timestamp of Device Last checkin

lastChanged	Timestamp of last update to the device state
createdTimeStamp	Timestamp of Device Enrol
createdBy	Username used to enrol the device
deviceManufacturer	Device Manufacturer Name
deviceModel	Device Model Name
deviceMarketName	Device Marketing Name
stateInfo	Current State of the Device
serviceDetails	List of Services device is enrolled.
transitionState	Transition state of the Device ENUM {Idle, Ready For Use, Protected, Enrolled, Active, Locked, Released, Delivered}
transitionQueue	List of the last three pending transitions in the queue, ordered from earliest to latest. {transitionState_1,transitionState_2,transitionState_3}
expirationTime	Next Relock time of the prepaid device
additionalInfo <i>Json Object</i>	Additional information such as custom prosperities of the device in Key Value pair Ex : {"Account Number": "123456", "Amount owed": "10.00", "Retail Brand": "TTP3.0 QA Basic", "Due Date": "", "Amount owed": "", "Days past due": "", ... }
simControlRule	Current sim control rule name assigned to device
contractId	Current contract id assigned to device
workflowId	Current workflow id assigned to device
imsiInfo <i>Json Object</i> [optional]	IMSI information such as IMSI of the device in Key Value pair Ex : {"IMSI": "452050474429354", "IMSI Lock": true, "IMSI Last Changed": "2025-08-04 10:47:38"}
adbCommandStatus [optional]	Current Status of ADB command. ENUM {BLOCK,ENABLE} Applicable only for KG Devices

aeProvisioningStatus [optional]	Current Status of AE Provisioning. ENUM {BLOCK,ENABLE} Applicable only for KG Devices
factoryResetStatus [optional]	Current Status of Factory Reset option. ENUM {BLOCK,ENABLE} Applicable only for KG Devices
resultCode [optional]	Result Code. Contains error code when the request fails.
resultMessage [optional]	Result Message Contains error message when the request fails.

5.7 User Info

To get the user information of a user resource.

GET api/v2/query/users?username={username}

5.7.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Parameter (optional)

username	Username
----------	----------

If parameter is not passed, all user details will be returned.

5.7.2 RESPONSE

Response Header

Response Body

Parameter	Parameter Description
userList	User Object List
username	Username
firstName	First Name of the User
lastName	Last Name of the User
userType	User type. ENUM {viewer, user, operator, support, delivery, admin}
userRole	Name of the role assigned to user account
contactNumber	Contact Number of the User
accountValidity	Validity of the user in days.
department	Department Name of the User
organizationUnit	Organization Unit of the User
Status	Account Status 1. active 2. locked 3. expired

5.8 State Info

To get the device list of device from specific state.

```
GET api/v2/query/state?stateName={stateName}
```

5.8.1 REQUEST

Request Header

Parameter	Parameter Description
-----------	-----------------------

Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Parameter

Parameter	Parameter Description
stateName	Name of the State
*required	ENUM {idle, readyForUse, enrolled, active, locked, released, protected, delivered, all}
pageNum	Default: 1
[Optional]	The page number to get, which must be >= 1.
pageSize	Default: 1000, Maximum = 1000
[Optional]	The number of items in a page, which must be >0 and <= 1000.

5.8.2 RESPONSE

Response Header

Response Body

Parameter	Parameter Description
stateName	Name of the State
deviceObjectList	State Object List
deviceUid	List of Device Unique identifier under the state

5.9 Message Template

To get the list of notification message template configured in the tenant.

Note : The Message title from the response message can be used in send message api to send notification to the devices using pre-configured template in UI.

GET api/v2/query/messageTemplate

5.9.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed
messageType	Type of Message Templates to be queried ENUM { lock, notify }

5.9.2 RESPONSE

[Response Header](#)

Response Body

Parameter	Parameter Description
tenantName	Name of the State
messageObjectList	Message Object List
messageType	Type of Message Template ENUM { lock, notify }
serviceName	Name of the Service Enum {supplyChain, deviceFinancing, simControl, theftProtection, subsidyProtection}
paymentMethod	Payment mode of the contract. Enum {prepaid, postpaid}
messageTemplateId	Unique ID of the Message Template
notificationTitle	Notification message title
notificationContent	Notification message content

	notificationType	Type of the Notification • headsup • fullscreen
--	------------------	--

5.10 Batch Action Status

To check the status of the batch action request.

GET api/v2/query/batchAction

5.10.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Parameter

batchActionId	Batch Action id of the device operation.
*required	
pageNum	Default: 1
[Optional]	The page number to get, which must be >= 1.
pageSize	Default: 1000, Maximum = 1000
[Optional]	The number of items in a page, which must be >0 and <= 1000.

5.10.2 RESPONSE

Response Header

Response Body

Parameter	Parameter Description
batchActionId	Batch Action id of the device operation.
batchActionStatus	Status of the Batch Action ENUM {INPROGRESS, COMPLETED, FAILED}
deviceResponseList	Message Object List
deviceUid	Device Unique ID
resultCode	Result Code of the device operation.
resultMessage	Result Message of the device operation

5.11 Tac Info

Note this is internal API, no need to include in Product Brochure and swagger.

To get the list of TAC information can be accessed using the API Key.

GET api/v2/query/tac?tacId={tacId}

5.11.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Parameter

tacId	
*required	tacId of the device.

5.10.2 RESPONSE

Response Header

Response Body

Parameter	Parameter Description
tacId	Tac ID of the device
tenantName	Name of the Tenant
modelName	Message Object List
brandName	A device's brand name
marketingName	A device's marketing name
manufacturer	A device's manufacturer
provisioningType	The type of device
multiSim	Support multiSim
createTime	Timestamp of TAC's creation

5.12 Sim control rule Info

To get the list of sim control rule information can be accessed using the API Key.

GET api/v2/query/simControls

5.11.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token>
	Token generated using Authorization API Call.
tenantId	Tenant ID
	Tenant ID in which API Method operation to be performed

Parameter

serviceName	service name to list the sim control rule data
*required	

5.10.2 RESPONSE

Response Header

Response Body

Parameter		Parameter Description
simControlRuleList		Sim Control Rule Object List
*	simControlRuleId	Sim Control rule id
*	simControlRuleName	Sim Control rule name
*	tenantId	Id of the tenant
*	serviceName	Service type name ENUM {postpaid, simControl, prepaid, theftProtection, subsidyProtection}

6 User Management

6.1 Add

To creates new user account in Telecoms platform for the tenant.

POST api/v2/identity/users/add

6.1.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token>
	Token generated using Authorization API Call.
tenantId	Tenant ID
	Tenant ID in which API Method operation to be performed

Request Body

Parameter	Parameter Description
-----------	-----------------------

userList		User Object List
*	username	Username to login to the Telecoms Platform. Format: email Address
*	firstName	First Name of the User
*	lastName	Last Name of the User
*	userType	User type. ENUM {viewer, user, operator, support, delivery, admin}
*	userRole	Name of the role assigned to user account
	contactNumber	Contact Number of the User
	tenantIdList	List of Tenant ID to be accessed by User
	department	Department Name of the User
	organizationUnit	Organization Unit of the User

6.1.2 EXAMPLE

6.1.3 RESPONSE

Response Header

Response Body

Parameter	Parameter Description
userResultObject	User List Object
username	User Name Added
resultCode	Result Code
resultMessage	Result Message

6.2 Deactivate

This API delete user information for a user resource.

DELETE api/v2/identity/users/deactivate

6.2.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

userList	User List Object
* username	User Name to be deleted

6.2.2 RESPONSE

Response Header

Response Body

Parameter	Parameter Description
userResultObject	User List Object
username	User Name deleted
resultCode	Result Code
resultMessage	Result Message

6.3 Modify

This API Modifies user information for a user resource.

PATCH api/v2/identity/users/

6.3.1 REQUEST

Request Header

Parameter	Parameter Description
-----------	-----------------------

Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

Parameter	Parameter Description
userList	User List Object
firstName	First Name of the User
lastName	Last Name of the User
userType	User type. The options are as follows, ENUM {viewer, user, operator, support, delivery, admin}
tenantIdList	List of the Tenant to be accessed.
contactNumber	Contact Number of the User
accountValidity	Validity of the user in days.
department	Department Name of the User
organizationUnit	Organization Unit of the User
accountStatus	Status of the account {lock, unlock}
resultCode	Result Code
resultMessage	Result Message

6.3.2 EXAMPLE

6.3.3 RESPONSE

Response Header

Response Body

Parameter	Parameter Description
-----------	-----------------------

userResultObject	User List Object
username	User Name Modified
resultCode	Result Code
resultMessage	Result Message

7 Webhook Notification API

The Telecoms Platform Webhook Notification API allows to send change notifications to a subscribed client about the completion of any subscribed events or background processes. On completion, the operation results from the Telecoms Platform services API operations are shared with the requesting client as a change notification. The result-sharing process is based on an efficient asynchronous workflow that avoids locking computational resources and, therefore, prevents inefficient event dependencies.

A Webhook push is simply a HTTP POST request, sent to the URL of your choosing. The push is automatically triggered when data updates.

The following procedure summarizes the Webhook Notification API workflow:

1. The client can create an event with the Webhook Notification. For example, an event could be registering device into service or changing the device state such as locked, active, enrolled .
2. The webhook notification event is now registered. A database stores the event notification subscription and the associated event.
3. The client makes a call to inventory upload API or Activate/deactivate service API with list of devices. The API operation in Telecoms Platform triggers an asynchronous event for batch of devices.
4. Telecoms Platform performs a database lookup to get the Notification events and check the event status in configured intervals.
5. Based on event status, Notification will send to URL registered in the Webhook Notification request.

Callback Method

This webhook listens for state changes of devices and provides the real-time webhook notifications to web application:

```
POST {$request.body#/url}
```

Callback Payload

The webhook notification will return one of the following status:

actionCompleted: Indicates that the action has been completed successfully, and the device state has changed or has been successfully

actionFailed: Indicates that the action has failed and the device state change is failed.

Payload:

Body		
	deviceUid	Device Unique Identifier
	eventType	Specifies the name of the transition state. ENUM {idle, readyForUse, enrolled, active, locked, released}
	actionName	Specifies the action being performed on the device (e.g., upload, register, deregister, lock, unlock, reload, release).
	status	Provides the status of the action (actionCompleted, actionFailed).
	serviceType	Indicates the type of service associated with the device Enum {inventory, supplyChain, deviceFinancing, simControl, theftProtection, subsidyProtection}
	updatedAt	The date and time of when the action was completed or failed.
	failedReason	Describes the reason for failure when an action or upload does not complete successfully (e.g., 1st party error).

7.1 Create Subscription

Creates a subscription assigning an endpoint to an event. This endpoint will be triggered whenever the expected event happens.

POST api/v2/webhook/subscription

7.1.1 REQUEST

Request Header

Parameter	Parameter Description
-----------	-----------------------

Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

eventType	The actions that trigger an callback. The subscription endpoint is called when the below subscribed state transition has been completed or failed. ENUM {idle, readyForUse, enrolled, active, locked, released}
url	Callback URL of the entity to be Notified

7.1.2 EXAMPLE

```
{
  eventType: "locked",
  url: "https://app.userback.io/viewer/123456/98765/2007850MSNv8n6f/"
}
```

7.1.3 RESPONSES

Response Header

Response Body

id	ID of the Webhook Notification (WN) subscription
url	Callback URL of the entity to be Notified
eventType	The type of entity that was targeted by the action. ENUM {idle, readyForUse, enrolled, active, locked, released}
createdAt	The time of webhook registration in ISO 8601 format.
resultCode	Result Code
resultMessage	Result Message

7.2 GET Subscription

To retrieve a webhook subscription based on WN subscription Id.

GET api/v2/webhook/subscription?subscriptionId={subscriptionId}

7.2.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Parameter

subscriptionId	ID of the Webhook Notification (WN) subscription
----------------	--

7.2.2 RESPONSES

Response Header

Response Body

id	ID of the Webhook Notification (WN) subscription
url	Callback URL of the entity to be Notified
eventType	The actions that trigger an callback. The subscription endpoint is called when the below subscribed state transition has been completed or failed. ENUM {idle, readyForUse, enrolled, active, locked, released}
createdAt	The time of webhook registration in ISO 8601 format.
resultCode	Result Code
resultMessage	Result Message

7.3 GET ALL Subscription

To retrieve a webhook subscription based on WN subscription Id.

GET api/v2/webhook/subscriptions/

7.3.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

7.3.2 RESPONSES

[Response Header](#)

Response Body

subscriptionList	Subscription Object List
id	subscriptionId, the id of the subscription.
url	callback registered URL
eventType	The set of actions that trigger an callback. The subscription endpoint is called when the below subscribed state transition has been completed or failed. ENUM {idle, readyForUse, enrolled, active, locked, released}
createdAt	The time of webhook registration in ISO 8601 format.

7.4 Delete Subscription

To deletes a webhook notification subscription from Telecoms platform.

DELETE api/v2/webhook/subscription?subscriptionId={subscriptionsId}

7.4.1 REQUEST

Request Header

Parameter	Parameter Description
-----------	-----------------------

Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Parameter

subscriptionId	ID of the Webhook Notification (WN) subscription
----------------	--

7.4.2 RESPONSES

Response Header

id	ID of the Webhook Notification (WN) subscription
url	Callback URL of the entity to be Notified
eventType	The actions that trigger an callback. The subscription endpoint is called when the below subscribed state transition has been completed or failed. ENUM {idle, readyForUse, enrolled, active, locked, released}
createdAt	The time of webhook registration in ISO 8601 format.
resultCode	Result Code
resultMessage	Result Message

8 Contract Management

8.1 Add Contract

To add the device into new contract

POST api/v2/contract/addContract/

8.1.1 REQUEST

Request Header

Parameter	Parameter Description
-----------	-----------------------

Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

addContractList		Add Contract Object List
*	deviceUid	Device Unique ID
*	contractId	Sequence number of contract to be assigned to the device.
*	assignedContractDate	The start date of the contract. Required If contractId is assigned to Device
	reloadTimeUnit	[Optional] The reload time unit for prepaid workflows. ENUM { hour, day, week, month, year }
	reloadTime	[Optional] The reload time for prepaid workflows. Accepting values from 1 to 1095 days.

8.1.2 EXAMPLE

```
{
  "addContractList": [
    {
      "deviceUid": "358285100032080",
      "contractId": "123",
      "assignedContractDate" : "2025-01-01 09:00:00"
    }
  ]
}
```

8.1.3 RESPONSES

Response Header

Response Body

addContractResponseList		Add Contract Response Object List
*	deviceUid	Device Unique ID
	resultCode	Result Code

	resultMessage	Result Message
--	---------------	----------------

8.2 Exit Contract

To exit workflow from device

PUT api/v2/contract/exitContract/

8.2.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

exitContractList	Exit Contract Object List
* deviceUid	Device Unique ID
* exitReason	The reason why exit workflow from device

8.2.2 EXAMPLE

```
{
  "exitContractList": [
    {
      "deviceUid": "358285100032080",
      "exitReason": "Device is out of contract length"
    }
  ]
}
```

8.2.3 RESPONSES

Response Header

Response Body

exitContractResponseList		Exit Contract Response Object List
*	deviceId	Device Unique ID
	resultCode	Result Code
	resultMessage	Result Message

8.3 Get Contract List

To list all contracts from TTP3.0 Platform

GET `api/v2/contract/contracts/`

8.3.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Parameter

serviceType (*required)	The service type used to filter contracts (postpaid, prepaid, simcontrol).
----------------------------	--

8.3.2 RESPONSES

[Response Header](#)

Response Body

contractList		Contract Object List
*	contractId	The unique ID of the contract.
	contractName	The name of the contract.

	contractMode	The mode of the contract (fixed or variable) used for prepaid service.
	workflowName	The workflow name associated with this contract.
	simControlPolicyName	The SIM control policy name associated with the contract.
	createdAt	The date and time when the contract was created.
	isActive	Indicates if the contract is active or inactive.

Example

```
{
  "contractList": [
    {
      "simControlPolicyName": "Sim restricted",
      "createdAt": "2025-01-01",
      "contractMode": "fixed",
      "contractId": "17",
      "contractName": "Dino",
      "workflowName": "Normal workflow",
      "isActive": true
    }
  ]
}
```

8.4 Get List Device Billing Cycles

To list all billing cycles of the device from TTP3.0 Platform

GET api/v2/contract/deviceBillingCycles/

8.4.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed
deviceUid (*required)	Device Uid The unique ID of the device to retrieve billing cycle information

8.4.2 RESPONSES

Response Header

Response Body

deviceBillingCyclesList		Billing Cycles Response Object List
*	deviceBillingCycleId	The unique ID of the billing cycle
	billingDate	The date on which the bill is generated
	startDate	The start date of the billing cycle
	endDate	The end date of the billing cycle
	dueDate	The due date for the payment of the bill
	deviceUid	The unique ID of the device
	paymentStatus	Status of payment (true, false)

Example

```
{
  "deviceBillingCyclesList": [
    {
      "deviceBillingCycleId": 1,
      "billingDate": "2025-01-10T01:00:00Z",
      "startDate": "2025-01-01T01:00:00Z",
      "endDate": "2025-01-10T01:00:00Z",
      "dueDate": "2025-01-11T01:00:00Z",
      "deviceUid": "123455678",
      "paymentStatus": true
    },
    {
      "deviceBillingCycleId": 2,
      "billingDate": "2025-02-10T01:00:00Z",
      "startDate": "2025-02-01T01:00:00Z",
      "endDate": "2025-02-10T01:00:00Z",
      "dueDate": "2025-02-11T01:00:00Z",
      "deviceUid": "123455678",
      "paymentStatus": false
    }
  ]
}
```

8.5 Update Device Payment

To Update the Billing Cycle Payment of the device

PUT api/v2/contract/updatePayment/

8.5.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token> Token generated using Authorization API Call.
tenantId	Tenant ID Tenant ID in which API Method operation to be performed

Request Body

updatePaymentList		Device payment Object List
*	deviceUid	Device Unique ID
*	deviceBillingCycles	The list cycle number of the device bill cycle during which the user makes the payment. This should accept multiple <code>cycleNumber</code> values
*	cycleNumber	The unique ID of the billing cycle
	reloadTime	[Optional] The reload time for prepaid workflows. Accepting values from 1 to 1095 days.
	reloadTimeUnit	[Optional] The reload time unit for prepaid workflows. ENUM { hour, day, week, month, year }

Example Request

```
{
  "updatePaymentList": [
    {
      "deviceUid": "358285100032080",
      "deviceBillingCycles": [
        {
          "cycleNumber": 1
        }
      ],
      "reloadTime": 1,
      "reloadTimeUnit": 'day'
    }
  ]
}
```

8.5.2 RESPONSES

Response Header

Response Body

updatePaymentResponseList		Update Payment Response Object List
*	deviceId	Device Unique ID
	resultCode	Result Code
	resultMessage	Result Message

9 Workflow Management

9.1 Add Workflow

To add the device into new workflow

POST api/v2/workflow/addWorkflow/

9.1.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token>
	Token generated using Authorization API Call.
tenantId	Tenant ID
	Tenant ID in which API Method operation to be performed

Request Body

addWorkflowList		Workflow Object List
*	deviceId	Device Unique ID
*	workflowId	Sequence number of workflow to be assigned to the device.

9.1.2 EXAMPLE

```
{  
  "addWorkflowList": [  

```

```
{
  {
    "deviceUid": "358285100032080",
    "workflowId": 123,
    "assignedWorkflowDate" : "2025-01-01 09:00:00"
  }
}
```

9.1.3 RESPONSES

Response Header

Response Body

addWorkflowResponseList		Add Workflow Response Object List
*	deviceUid	Device Unique ID
	resultCode	Result Code
	resultMessage	Result Message

9.2 Exit Workflow

To remove device from the workflow.

PUT api/v2/workflow/exitWorkflow/

9.2.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token>
	Token generated using Authorization API Call.
tenantId	Tenant ID
	Tenant ID in which API Method operation to be performed

Request Body

exitWorkflowList		Exit workflow Object List
*	deviceUid	Device Unique ID

*	exitReason	The reason for exiting the device from workflow.
---	------------	--

9.2.2 EXAMPLE

```
{
  "exitWorkflowList": [
    {
      "deviceUid": "358285100032080",
      "exitReason": "Device is out of contract length"
    }
  ]
}
```

8.2.3 RESPONSES

Response Header

Response Body

exitWorkflowResponseList		Exit workflow Response Object List
*	deviceUid	Device Unique ID
	resultCode	Result Code
	resultMessage	Result Message

9.3 Get Workflow List

To list all workflows from TTP3.0 Platform

GET api/v2/workflow/workflows

9.3.1 REQUEST

Request Header

Parameter	Parameter Description
Authorization	Bearer <Token>
	Token generated using Authorization API Call.
tenantId	Tenant ID
	Tenant ID in which API Method operation to be performed

Parameter

serviceType (*required)	The service type used to filter contracts (postpaid, prepaid, simcontrol).
----------------------------	--

9.3.2 RESPONSES

Response Header

Response Body

workflowList	Workflow Object List
* workflowId	The unique ID of the workflow.
workflowName	The name of the Workflow.
createdAt	The date and time when the workflow was created.
isActive	Indicates if the workflow is active or inactive.

Example

```
{
  "workflowList": [
    {
      "workflowId": "123",
      "workflowName": "Normal workflow",
      "createdAt": "2025-01-01",
      "isActive": true
    }
  ]
}
```

10 APPENDIX

API ERROR

resultCode : error (required)

resultMessage : *String* Verbose description of the reason behind this response

Example :

resultCode	UPLOAD_ID_NOT_FOUND
------------	---------------------

resultMessage	Upload ID is not found in the system
---------------	--------------------------------------

No.	Type	Error Code	Result Message
1	General	UPLOAD_ID_NOT_FOUND	Upload ID is not found in the system
2		DEVICE_UID_NOT_VALID	This {device_type_title} [{device_uid}] is invalid
3		IMEI2_INVALID	IMEI2 {imei2} is not valid
4		IMEI1_BLANK	The device cannot be added due to imei is invalid of imei1 [{device_uid}]
5		IMEI2_BLANK	The device cannot be added due to imei is invalid of imei2 [{device_uid}]
6		DEVICE_UID_DUPLICATE	This imei [{request}] is duplicated
7		INVALID_TENANT	Specified target tenant is invalid or not found
8		ASSIGNED_ACTION_INVALID	This {device_type_title} [{imei or serial number}] is in State transition, please wait for the Action complete
9		PROVISIONING_TYPE_UNSUPPORTED	Device [{device_uid}] fail to add IMEI2 due to wrong provisioning type
10		PROVISIONING_TYPE_MISMATCH	This [{imei}] differs from the provisioning type of [{imei2}]
11		IMEI2_ALREADY_EXISTED	This imei [{device_uid}] has already added imei2
12		DEVICE_UID_EXIST	This imei [{device_uid}] is already uploaded
13		INTERNAL_ERROR	An unexpected error occurred. Please try again later.
14		RELOAD_DAYS_NOT_APPLICABLE	Reload days is not applicable for the service {service_name}
15	Checking input	INVALID_RANGE	Please input {property}'s value and in range {minimum} to {maximum}
16		REQUIRED_PROPERTIES	Please input {property}
17		INVALID_ENUM_VALUE	{property} has a value of one of the following types: {options}
18		INVALID_MINIMUM	{property} has a value {value} is less than {minimum}
19		INVALID_DATA_TYPE	{property} has a value of type {data_type}
20		INVALID_PARAMS	One or more parameters in the request body are invalid
21		INVALID_RELOAD_DAYS	Reload days must be an integer value and in range {minimum} to {maximum}

22		INVALID_FORMAT_JSON	The request body contains invalid JSON.
23		INVALID_NEXT_DUE	nextDue timestamp is invalid. Expected 10 or 13 characters and timestamp in the past is not allowed
24		MAXIMUM_LEN_EXCEEDED	Maximum character for the device property is {maximum}
25		MAXIMUM_BATCH_SIZE_EXCEEDED	Maximum device for batch is {maximum}
26		MISSING_KEY_REQUEST	Missing key {key} request
27		INVALID_CHALLENGE	Challenge code must be number and {len_pin_valid} digits
28		URL_INVALID	URL is invalid
29		REQUIRED_PARAMS	Please input messageTemplateId or notificationTitle
30	Authenticate	AUTHENTICATION_REQUIRE_D_BEARER	Token is invalid or needs to be provided 'Bearer' prefix
31		AUTHENTICATION_MISMATCH	Authorized is mismatched!
32		AUTHENTICATION_INVALID_APIKEY	Unauthorized: API key is not available
33		AUTHENTICATION_INVALID_TENANT	User or tenant not exists
34		AUTHENTICATION_TOKEN_EXPIRED	Token is expired
35		AUTHENTICATION_INVALID_SIGNATURE	Unauthorized: Invalid Signature
36		AUTHENTICATION_INVALID_TOKEN	Unauthorized: invalid token
37		AUTHENTICATION	Authorized missing information!
38	Authorization	AUTHORIZATION	token does not have sufficient permissions to access this resource
39	Device	DEVICE_UID_NOT_FOUND	Not found the device with {device_type} [{device_uid}]
40		DEVICE_IS_ASSIGNED	This {device_type} [{device_uid}] is in State transition, please wait for the Action complete
41		DEVICE_UID_ARCHIVED	This {device_type} [{device_uid}] has been archived
42		DEVICE_IS_IDLE_RELEASE_STATE	Device {device_uid} must be in Idle or Release state
43		DEVICE_UNSUPPORTED_OEM	Unsupported OEM
44		DEVICE_STATE_SERVICE_NOT_VALID	Device must be in Locked state and in Prepaid or Postpaid service

45		DEVICE_UID_NOT_PRIMARY	Please make sure this device uid [{device_uid}] with the correct value of 'imei (required)'
46		DEVICE_CANNOT_ASSIGN_ACTION	Cannot {action_name} to {state_name} device because current device is being applied with another action
47		DEVICE_UNABLE_UNLOCK	The device is unable to {action_name}
48		DEVICE_STATE_NOT_PERMIT_ACTION	The device is currently {state_name} and unable to be {action_name}
49		DEVICE_ACTION_NOT_VALID_SERVICE	Cannot find action {action_name} for this service {service_name}
50		DEVICE_NOT_ALLOWED_DEREGISTER	This {device_type_title} [{request}] cannot assign action Deregister because provision type of [{request}] doesn't support
51		WRONG_SERVICE_TYPE	Please make sure this {device_type_title} [{request}] is with the right Service
52		DEVICE_NEXT_DUE_MUST_BE_GREATER_THAN_EXPIRY	Please input greater value than the current expiration datetime
53		DEVICE_MAXIMUM_RELOAD_DATETIME	Reload fail due to reach maximum Expiry. Please check the expiration time first
54		DEVICE_VALIDATION_REQUIRED	validityDays is required for this device {device_uid}
55		DEVICE_UID_NOT_VALID_LUHN	This imei {deviceUID} is invalid luhn check
56		DEVICE_UNSUPPORTED_OEM	Unsupported OEM
57		SMARTPHONE_HAS_TAC_ARCHIVED	This smartphone [{device_uid}], TAC is archived
58		DEVICE_UID_OWNED_BY_OTHER	This {device_type} [{device_uid}] does not belong to this customer
59		DEVICE_IS_ALREADY_UNLOCKED	Device is already unlocked.
60		DEVICE_UNSUPPORTED_UPDATING_SERVICE	Update service is not allow for {device_uid} in {device_state_name} State
61		DEVICE_TYPE_HAS_THE_SAME_TYPE	Currently, we only support a single device type in batch actions
62		DEVICE_STATE_INVALID	The device is unable to assign Action, please check the device's state
63		DEVICE_UID_MAX_LENGTH_CHARACTER	Please keep the Serial Number within 32 characters
64		TAC_BLACKLISTED	This device {imei} uses a TAC that is not supported.
65		USER_NOT_FOUND	User is not found in the system

66	User and Service	SERVICE_NOT_FOUND	Service is disabled in the system
67		SERVICE_NOT_SUPPORT_ACTION	service {service_name} not support this action
68		SERVICE_NOT_ENABLED	Service is not enabled
69	Device Properties	PROPERTY_NOT_PERMIT_ACCESS	Please contact Admin to update the Global & System custom property
70		PROPERTY_NOT_VALID	{properties} is a invalid Custom Property, please input a valid Custom property
71		DEVICE_NOT_ELIGIBLE_FOR_UPDATE_PROPERTY	The device is not belong to {workspace_name} and unable to update device property
72	Generate Pin Unlock	PIN_DEVICE_INVALID_STATE	The device can't generate PIN in state {state_name}
73		DEVICE_STATE_NOT_GENERATE_PIN	Current state {state_name} can't generate Pin
74		PIN_SERVICE_NOT_VALID	The device can't generate Pin in service {service_name}
75		PIN_DEVICE_NOT_VALID	The device does not support generate PIN
76		PIN_GENERATE_FAILED	PIN generation fail, OEM system is currently unavailable. Please try again later.
77		PIN_UNLOCK_USERID_NOT_FOUND	The specified user code for PIN UNLOCK does not exist in the system.
78	Webhook	WEBHOOK_SUBSCRIPTION_NOT_FOUND	Subscription is not found in the system
79		WEBHOOK_DUPLICATE_SUBSCRIPTION	Subscription is already existed
80		WEBHOOK_SUBSCRIPTION_NOT_ALLOWED	Webhook is not enabled.
81		WEBHOOK_INVALID_EVENT_TYPE	Event Type is not supported by webhook
82	TAC	TAC_NOT_EXIST	This imei [{device_uid}], TAC is not in the database
83	Transfer	TRANSFER_ID_NOT_FOUND	Transfer ID is not found in the system
84		ACTION_NOT_ALLOWED	The device is not belong to {workspace_name} and unable to be {action_name}
85		DEVICE_NOT_ELIGIBLE_FOR_UPDATE_IMEI2	The device is not belong to {workspace_name} and unable to update IMEI2
86	Batch Action	BATCH_ACTION_ID_NOT_FOUND	Batch Action ID is not found in the system
87	Order Service	SYSTEM_ERROR	An unexpected error occurred. Please try again later.

88		SERVICE_NOT_FOUND	Service is disabled in the system
89		SERVICE_NOT_ENABLED	Service is not enabled
90		ORDER_ID_NOT_FOUND	Order ID is not found in the system
91	System	SYSTEM_HANDLER_NOT_FOUND	System handler is not found
92		SYSTEM_NOT_FOUND_HANDLER	The System didn't find the handler
93		SYSTEM_CAN_NOT_PARSE_VALUE	System can not parse {value} to {datatype} exist
94		SYSTEM_FEATURE_UNSUPPORTED	Currently, this feature does not support
95		SYSTEM_INVALID_ENDPOINT	Invalid endpoint. The requested resource could not be found.
96		REQUEST_SUCCESS	Request is successful
97		SYSTEM_INVALID_ENDPOINT_METHOD	Invalid Endpoint Method. The requested resource could not be found.
98	Contract & Workflow	WORKFLOW_IS_NOT_ACTIVATED	Workflow is not activated for this tenant.
99		DEVICE_BILLING_CYCLE_NOT_FOUND	Device bill cycle number {cycle_number} was not found for device with IMEI {imei}.
100		NO_CONTRACT_ASSIGNED	No contract is assigned to this device
101		NOT_FOUND_BILLING_CYCLE	Not found billing cycle data with cycle number {cycle_number} with device {imei}
102		NO_CONTRACT_ASSIGNED	No contract is assigned with this device
103		PREVIOUS_PAYMENT_NOT_PAID	The previous payment for cycle number {cycle_number} has not been completed
104		SERVICE_IS_NOT_VALID_FOR_TEMPORARY_LOCK	Temporary lock is only available for DeviceFinancing Postpaid
105		WORKFLOW_FIELD_REQUIRED	Field {field} is required
106		ACTION_DISABLED_FOR_WORKFLOW_DEVICE	Workflow is assigned to device and cannot assign {action}
107		API_ENDPOINT_DISABLED	The requested API endpoint is disabled and cannot be accessed at this time. Please contact support to enable it
108		EXIT_REASON_REQUIRED	Exit reason cannot be empty
109		SERVICE_IS_NOT_VALID_FOR_FLEXIBLE_WORKFLOW	Flexible Workflow is not supported for the service type {service_type}. Allowed services: Prepaid, Postpaid, Sim Control.

110		INCOMPATIBLE_SERVICE_WORKFLOW	Current device service {service_type} is incompatible with workflow {workflow_name}
111		WORKFLOW_ALREADY_ASSIGNED	Workflow {workflow_name} already exists for this {device_type} {device_uid}, Remove the existing workflow before adding new workflow.
112		ASSIGNED_CONTRACT_DATE_IN_PAST	Invalid assignedContractDate {assigned_contract_date}. It must be greater than or equal to the current date and time.
113		NO_FLEXIBLE_WORKFLOW_ASSIGNED	The device has no active flexible workflow, or the assigned flexible workflow has already ended.
114		CONTRACT_WORKFLOW_CONFLICT	Both Contract and workflow feature cannot be assigned to the {device_type} {device_uid}.
115		FLEXIBLE_WORKFLOW_OR_CONTRACT_NOT_ACTIVATED	Neither Contract nor Flexible Workflow is activated for this tenant
116		INCOMPATIBLE_SERVICE_CONTRACT	Current device service {service_type} is incompatible with contract {contract_name}
117		TEMP_LOCK_DURATION_TOO_SHORT	Temporary Lock duration must be at least {min_duration} minutes
118		INVALID_ASSIGNED_CONTRACT_DATE	Invalid assignedContractDate format. Expected format: YYYY-MM-DD HH:MM:SS
119		SERVICE_IS_NOT_VALID_FOR_CONTRACT	Contracts is not supported for the service type {service_type}. Allowed services: Prepaid, Postpaid, Sim Control.
120		WORKFLOW_NOT_FOUND	Workflow {workflow_id} not found
121		WORKFLOW_ALREADY_ASSIGNED	Workflow {workflow_name} already exists for this {device_type} {device_uid}.
122		CONTRACT_ALREADY_ASSIGNED	Contract {contract_name} already exists for this {device_type} {device_uid}.
123		INVALID_EXIT_REASON	Please key in valid value for the exit reason.
124		CONTRACT_NOT_FOUND	Contract {contract_id} not found
125		DEVICE_NOT_ELIGIBLE_FOR_DISABLING_SIM_CONTROL	The device is currently {state_name} and unable to be disabled sim control

126	Device level Sim Control Rule	DEVICE_NOT_ELIGIBLE_FOR_ASSIGNING_SIM_CONTROL	The device is currently {state_name} and unable to be assigned with sim control
127		SERVICE_NOT_ELIGIBLE_FOR_DISABLING_SIM_CONTROL	The current service is not allowed to use disable sim control feature
128		DEVICE_SIM_CONTROL_RULE_ALREADY_DISABLED	SIM control is already disabled for the device {imei}
129		DEVICE_SIM_CONTROL_RULE_ALREADY_ASSIGNED	SIM control {rule} is already assigned to the device {imei}
130		SIM_RULE_NOT_VALID	SIM control rule with ID {rule} Not found
131	Service Change	SERVICE_TRANSITION_BLOCKED_BY_CONFIG	Transition from :source_service to :target_service is not allowed due to configuration conflict.
132		SERVICE_TRANSITION_NOT_ALLOWED	Transition from :source_service to :target_service is not allowed.
133	IMSI Swap	PROVISION_TYPE_NOT_ALLOWED	This :device_type[:device_uid] cannot assign action :action_name because provision type of [:device_uid] doesn't support
134		SERVICE_NOT_SUPPORT_ACTION	Service [:service_name] not support this action
135		DEVICE_STATE_NOT_PERMIT_ACTION	The device is currently :state_name and unable to perform :action_name
136		DEVICE_CANNOT_ASSIGN_ACTION	Cannot :action_name device because current device is being applied with another action
137		SIM_CONTROL_NOT_ENABLED	The simControl is currently not enabled and unable to perform :action_name
138		IMSI_SWAP_IN_PROGRESS	The IMSI Swap is currently in progress and unable to perform :action_name
139	Block ADB Command	DEVICE_NOT_SUPPORT_BLOCK_ADB_COMMAND	Block ADB Command is only supported for Knox Guard devices
140	Block AE Provision	DEVICE_NOT_SUPPORT_BLOCK_AE_PROVISION	Block AE Provision is only supported for Knox Guard devices
141	Block Factory Reset	DEVICE_NOT_SUPPORT_BLOCK_FACTORY_RESET	Block Factory Reset is only supported for Knox Guard devices
142	SYSTEM	SYSTEM_FEATURE_UNSUPPORTED	The requested feature is currently not supported.