

# Clarion

# Template Language Reference

### COPYRIGHT SoftVelocity Inc. All rights reserved.

This publication is protected by copyright and all rights are reserved by SoftVelocity Inc. It may not, in whole or part, be copied, photocopied, reproduced, translated, or reduced to any electronic medium or machine-readable form without prior consent, in writing, from SoftVelocity Inc.

This publication supports Clarion. It is possible that it may contain technical or typographical errors. SoftVelocity Incorporated provides this publication "as is," without warranty of any kind, either expressed or implied.

### SoftVelocity Inc

www.softvelocity.com

### **Trademark Acknowledgements:**

SoftVelocity is a trademark of SoftVelocity Inc.

Clarion™ is a trademark of SoftVelocity Inc.

Microsoft®, Windows®, and Visual Basic® are registered trademarks of Microsoft Corporation.

All other products and company names are trademarks of their respective owners.

Printed in the United States of America (0409)

# **Table of Contents**

Table of Contents	i	
Template Language Reference	1	
Introduction	2 4 5 6	
Template Structure		
Template Source Format The Template Registry File Customizing Default Templates	10	
Complete Alpha Listing	13	
#! (template code comments)  #\$ (embeditor comment)  #? (conditional source line)  #< (aligned target language comments)  #ABORT (abort source generation)  #ACCEPT (section valid for use)  #ADD (add to multi-valued symbol)	14 15 16 17 18	
#ALIAS/#TRYALIAS (access a symbol from another instance) #APPEND (add to source file) #APPLICATION (source generation control section) #ASSERT (evaluate assumption) #ASSERT (evaluate assumption)	20 21 22 24	
#AT (insert code in an embed point)	27 28 28	
#BUTTON (call another page of prompts)	34 35 36	
#CLEAR (clear single-valued symbol) #CLOSE (close source file) #CODE (define a code template) #COMMENT (specify comment column) #CONTEXT (set template code generation context) #CONTEXT	38 39 41	
#CREATE (create source file)	43 44 44	
#DEFAULT (default procedure starting point)	47 49 50	
#DELETEALL (delete multiple multi-valued symbol instances)	52	

#EMPTYEMBED (generate empty embed point comments)	56
#ENABLE (enable/disable prompts)	
#EQUATE (declare and assign value to a user-defined symbol)	58
#ERROR (display source generation error)	
#EXPAND (expand a user defined macro)	
#EXPORT (export symbol to text)	
#EXTENSION (define an extension template)	62
#FIELD (control prompts)	
#FIND ("super-fix" multi-value symbols)	66
#FIX (fix a multi-value symbol)#FOR (generate code multiple times)	60
#FREE (free a multi-valued symbol)	
#GENERATE (generate source code section)	
#GLOBALDATA (default global data declarations)	
#GROUP (reusable statement group)	
#HELP (specify template help file)	
#IF (conditionally generate code)	
#IMAGE (display graphic)	
#IMPORT(import from text script)	78
#INCLUDE (include a template file)	
#INDENT (change indentation level)	80
#INSERT (insert code from a #GROUP)	
#INVOKE (insert code from a named #GROUP)	
#LOCALDATA (default local data declarations)	
#LOOP (iteratively generate code)	84
#MESSAGE (display source generation message)	
#MODULE (module area)	
#OPEN (open source file)	
#PDEFINE (add #pragma to project	
#POP (delete and re-fix a multi-value symbol)	
#POSTEMBED (generate ending embed point comments)	
#PREEMBED (generate beginning embed point comments)	92
#PREPARE (setup prompt symbols)	
#PRINT (print a source file)	
#PRIORITY (set new embed priority level)	
#PROCEDURE (begin a procedure template)	
#PROGRAM (global area)	
#PROJECT (add file to project)	99
#PROMPT (prompt for programmer input)1	01
#PROMPT Entry Types Alpha Listing1	05
CHECK (check box)1	
COLOR (call Color dialog)1	06
COMPONENT (list of KEY fields)1	
CONTROL (list of window fields)1	08
DROP (droplist of items)1	
DROP (droplist of items)1	
EMBED (enter embedded source)	
EMBED (enter embedded source)	
EMBEDBUTTON (call Embeds dialog)	
EMBEDBUTTON (call Embeds dialog)	
FILE (list of files)	15
FORMAT (call listbox formatter)	
FROM (list of symbol values)	
ICON (call Icon selection dialog)1	
KEY (list of keys)1	
KEYCODE (list of keycodes)1	20

	OPENDIALOG (call Open File dialog)	
	OPTFIELD (optional text or data field)	
	OPTION (display radio buttons)	
	PICTURE (call picture formatter)	
	PROCEDURE (add to logical procedure tree)	
	RADIO (one radio button)	
,	SAVEDIALOG (call Save File dialog)	127
,	SPIN (spin box)	128
-	TEXT (text box)	128
7	#PROTOTYPE (procedure prototype)	129
7	#PURGE (delete all single or multi-valued symbol instances)	130
7	#QUERY (conditionally generate source)	131
7	#READ (read one line of a source file)	132
7	#REDIRECT (change source file)	133
	#REJECT (section invalid for use)	
7	#RELEASE (commit conditional source generation)	135
	#REMOVE (delete a source file)	
7	#REPLACE (conditionally replace source file)	138
7	#REPORTS (default report structures)	139
7	#RESTRICT (define section use constraints)	140
	#RESUME (delimit conditional source)	
	#RETURN (return from #GROUP)	
	#RUN (execute program)	
	#RUNDLL (execute DLL procedure)	
	#SECTION (define code section)	
	Named #SECTIONS	
	#SELECT (fix a multi-value symbol)	
	#SERVICE (internal use only)	
	#SET (assign value to a user-defined symbol)	
	#SHEET (declare a group of #TAB controls)	
	#SUSPEND (begin conditional source)	
	#SYSTEM (template registration and load)	
	#TAB (declare a page of a #SHEET control)	
	#TEMPLATE (begin template set)	
	#TYPEMAP (map EQUATE to data type)	
	#UNFIX (unfix a multi-value symbol)	
	#UTILITY (utility execution section)	
	#VALIDATE (validate prompt input)	
	#WHERE (define #CODE embed point availability)	
	#WINDOWS (default window structures)	
	#WITH (associate prompts with a symbol instance)	
	,	
Bui	It-in Template Procedures 1	65
(	CALL (call a #GROUP as a function)	165
	EXTRACT (return attribute)	
i	EXISTS (return embed point existence)	167
	FILEEXISTS (return file existence)	
	FULLNAME (return file path)	
	NLIST (return item exists in list)	
	NSTANCE(return current instance number)	
	NVOKE (call a named #GROUP as a function)	
	TEMS (return multi-valued symbol instances)	
	LINKNAME (return mangled procedure name)	
	QUOTE (template - replace string special characters)	
	REGISTERED (return template registration)	
	REPLACE (replace attribute)	
	NET EACE HEDIAGE AUTDUICH	1//

SEPARATOR (return attribute string delimiter position) SLICE (return substring from string)	179 180 181 182 183
Template Symbols	189
Symbol Overview Expansion Symbols Symbol Hierarchy Overview	190
Built-in Symbols	193
Symbols Dependent on %Application Symbols Dependent on %File Symbols Dependent on %View Symbols Dependent on %Field Symbols Dependent on %Key Symbols Dependent on %Relation Symbols Dependent on %Module Symbols Dependent on %Procedure Window Control Symbols Report Control Symbols Formula Symbols File Schematic Symbols File Driver Symbols Miscellaneous Symbols	196 200 203 208 210 213 216 217 218 219
Annotated Examples	221
Procedure Template: Window  %StandardWindowCode #GROUP.  %StandardWindowHandling #GROUP.  %StandardAcceptedHandling #GROUP.  %StandardControlHandling #GROUP.  Code Template: ControlValueValidation.  %CodeTPLValidationCode #GROUP.  Control Template: DOSFileLookup.  Extension Template: DateTimeDisplay.  %DateTimeDisplayCode #GROUP.	223 230 231 233 235 237
Index	243

# Template Language Reference Introduction

Clarion for Windows' Template Language is a flexible script language complete with control structures, user interface elements, variables, file I/O, and more. The Template Language "drives" the Application Generator both at application design time and during source code generation.

- During application design, the programmer is asked for specific information about the application being generated. These prompts for information come directly from the templates.
- During source code generation, the template is in control of the source code statements generated for each procedure in the application, and also controls what source files receive the generated code.

This process makes the Templates completely in control of the Application Generator. The benefit to the programmer of this is the complete flexibility to generate code that is directly suited to the programmer's needs.

# What is a Template

Clarion templates are highly configurable, interactive, interpreted, code generation scripts. A template typically prompts you for information then generates a custom set of source code based on your responses. In addition to its prompts, many templates also add source code embed points to your application—points at which you can supply custom source code that is integrated into the template generated code. You may want to think of the template prompts as a way to define the static (compile time) characteristics of a program or procedure, and the embedded source as a way to define the changing (runtime) characteristics of a program or procedure.

### **Prompts**

A template typically prompts you for information at design time. The Application Generator interprets the template and presents a dialog with all the template's prompts. You fill in the prompts, with assistance from the on-line help, to define the static (compile time) characteristics of your program or procedure. For example, fill in the Record Filter prompt to establish a filter for a BrowseBox template.

### **Embed Points**

In addition to its prompts, many templates also add source code embed points to your application or procedure—points at which you can supply custom source code that is integrated into the template generated code. You can use these embed points to define the changing (runtime) characteristics of a program or procedure. For example, embed source code to hide a related listbox when there are no related records to display.

### **Advantages of Template Use**

Templates promote code reuse and centralized maintenance of code. They provide many of the same benefits of object oriented programming, especially reusability. In addition, templates can compliment and enhance the use of object oriented code by providing easy-to-use wrappers for complex objects. The ABC Templates and ABC Library are a prime example of this synergistic relationship between templates and objects.

You can modify templates to your specifications and store your modifications in the Template Registry. You may also add third party templates and use them in addition to, and along with, the Clarion templates. You may write your own templates too. The Template Language is documented in the *Template Language Reference* and in the on-line help.

# **What Templates Are**

A template is a complete set of instructions, both Template and "target" language statements, which the Application Generator uses to process the programmer's input for application customizations then generate "target" language (usually, but not limited to, Clarion language) source code.

Clarion's templates are completely reusable. They generate only the exact code required for each specific instance of its use; they do not inherit unused methods. The templates are also polymorphic, since the programmer specifies the features and functions of each template that are required for the procedure. This means one template can generate different functionality based upon the programmer's desires.

Some of the most important aspects of template functionality supported by the Template Language include:

- Support for controls (#PROMPT) that gather input from the developer, storing that input in user-defined template variables (symbols).
- Pre-defined template variables (Built-in Symbols) containing information from the data dictionary and Clarion for Windows' application development environment.
- Specialized #PROMPT entry types, which give the programmer a list of appropriate choices for such things as data file or key selection.
- Unconditional and conditional control structures (#FOR, #LOOP, #IF, #CASE) which branch source generation execution based on an expression or the contents of a symbol (variable). This allows the Application Generator to generate only the exact source code needed to produce the programmer's desired functionality in their application.
- Statements (#EMBED) that define specific points where the developer can insert (embed) or *not* insert their own source code to further customize their application.
- Support for code templates (#CODE), control templates (#CONTROL), and extension templates (#EXTENSION) that add their specific (extended) functionality to any procedure template. This makes any procedure type polymorphic, in that, the procedure can include functionality normally performed by other types of procedures.

Template code is contained in one or more ASCII files (\*.TPL or \*.TPW) which the Application Generator pre-compiles and incorporates into the TemplateRegistry.TRF file. It is this template registry file that the Application Generator uses during application design.

Once in the registry, the template code is completely reusable from application to application. It generates custom source code for each application based upon the application's data dictionary and the options selected by the programmer while working with the Application Generator.

The programmer can customize the templates in the registry (or in the \*.TP\* files) to fit their own specific standard design requirements. This means that each procedure template can be designed to appear exactly as the programmer requires as a starting point for their applications. Multiple "default" starting points can be created, so the programmer can have a choice of starting point designs for each procedure type.

When the programmer has customized the template source (\*.TP\* file), the Application Generator automatically updates the registry. When the programmer has customized the registry, the template source files can be re-generated from the registry, if necessary.

The Application Generator always makes a *copy* of the template, as stored in the registry, when creating a procedure or first populating a procedure with a code, control, or extension template. Once this copy is made, the programmer further customizes it to produce exactly the functionality required by the application for that procedure.

The template language can generate more than source code: it can even be used to create addin utilities (see #UTILITY).

# **Template Types**

There are four main types of templates: procedure, code, control, and extension templates.

- Procedure templates (#PROCEDURE) generate procedures in an application. This is the choice you make when asked to choose the starting point for a "ToDo" procedure in the Application Generator.
- Code templates (#CODE) generate executable code into a specific embed point. The
  developer can only insert them at an embed point within a procedure. A list of the
  available code templates appears from which to choose.
- Control templates (#CONTROL) place a related set (one or more) of controls on a
  procedure's window and generate the executable source code into the procedure's
  embed points to provide the controls' standard functionality.
- Extension templates (#EXTENSION) generate executable source code into one or more embed points to add specific functionality to a procedure that is not "tied" to any window control.

### **What Templates Do**

The template code files contain template language statements and standard "target" language source code which the Application Generator places in your generated source code files. They also contain the prompts for the Application Generator which determine the standard customizations the developer can make to the generated code.

The programmer's response (or lack of) to the prompts "drives" the control statements that process the template language code, and produces the logic that generates the source code. The templates also contain control statements which instruct the Application Generator how to process the standard code. The function of a template is to generate the "target" language source code, customized per the programmer's response to the prompts and design of the window or report.

There are some lines of code from templates that are inserted directly into your generated source code. For example, if you accept a default Copy command menu item in your application window, the following code is inserted in your generated source exactly as it appears in the template file:

```
ITEM('&Copy'), USE(?Copy), STD(STD:Copy), MSG('Copy item to Windows clipboard')
```

Some of the standard code in the template is a mix of "target" (Clarion) language statements and template language statements. For example, when the contents of a template variable (symbol) needs to be inserted in the generated source code, the Application Generator expands the symbol to the value the application will use, as it generates the source code for the application. Within the template code, the percent sign (%) identifies a variable (symbol). In the example below, the Application Generator will fill in the field equate label for the control as it writes the source code file, substituting it for the %Control variable:

```
SELECT (%Control)
```

To support customizing the template starting point at design time, Clarion's template language provides prompt statements that generate the template's user interface, so that the Application Generator can query the developer for the information needed to customize the application. The basic interface consists of command buttons, check boxes, radio buttons, and entry controls placed on the Procedure Properties dialog. These statements can also create custom dialog boxes to gather input from the developer. While working with the Application Generator, therefore, some of the dialogs and other interface elements the developer sees are not part of the Application Generator, rather they are produced by the template.

For example, the following statement displays a file selection dialog from the application's data dictionary, then stores the programmer's choice for a data file in a variable (symbol) called %MyFile:

```
#PROMPT('Pick a file',FILE),%MyFile
```

It makes no difference what the programmer names the files and fields, nor what database driver is selected. The programmer picks them from a file selection dialog.

The template also contains control structures to instruct the Application Generator on how to generate the code(e.g., #IF, #LOOP, #CASE). These control statements work in the same manner as Clarion language control structures.

# **Pre-Processing and Source Code Generation**

Before allowing you to create an application using the templates, the Application Generator preprocesses the template code (.TPL and .TPW) files. The Application Generator verifies the registry is up to date by testing the time stamps and file sizes of all the template source code files.

The Application Generator utilizes the templates as stored in binary form in the registry file, as it gathers customizations from the developer with the prompts and dialogs available through the Procedure Properties dialog. The Application Generator stores the template starting point for each procedure and the customization from the programmer in the .APP file.

At source code generation time, the Application Generator processes the application's procedures as stored in the .APP file against the template, a second time. Some of the more important steps it uses to produce the source code are:

- It executes the template language control statements to process the template and the procedure's customizations in the correct order.
- It resolves the template symbolsboth built-in and user-defined.
- It creates the source code files and writes the source code as generated by the template, line by line, including the previously evaluated symbols.
- It evaluates embed points and writes the source code, as embedded by the developer and stored in the .APP file, in the correct location within the generated source code.

### **Embed Points**

One of the most important template language statements is #EMBED, which defines an embed point. These extend the structure and functionality of the procedure template by allowing the programmer to add their own custom code. The embed points indicate "targets" at which the developer can add their own custom code to the generated source. These are also the "targets" for the source code generated by control and extension templates.

Each procedure template allows for a certain number of default points at which embeds are allowed. These are typically points which coincide with messages (events) from the operating environment (Windows), such as when the end user moves focus from or to a field. The template programmer can add to, or subtract from, the list.

When the developer customizes the template, pressing the Embeds button in the Procedure Properties dialog provides access to all the embed points available in a procedure. The Actions popup menu selection in the Window Formatter also provides access to the embed points for a specific control.

The developer adds custom code; either hand coded from scratch in the editor, or created with a code template at the embed point. The embed points are also the points into which control templates and extension templates generate executable code to support their functionality.

The Application Generator stores the embed point's code (no matter what its origination) in the .APP file. At code generation time, the Application Generator processes the template, producing source; when it reaches an embed point, it places the developer's code, line by line, into the generated source code document.

### **Template Prompts**

Input Validation Statements and Prompt Entry types place controls on the Procedure Properties window or Actions dialog which the developer sees when using the template to design an application. These range from a simple string telling the Developer what to do (#DISPLAY), to command buttons, check boxes, or radio buttons. There are also specialized entry types which provide the programmer a list of choices for input, such as the data fields in the dictionary.

Standard Windows controls can be used to get information from the programmer on the Procedure Properties window, the Actions dialog, or custom prompt dialogs. The common control types entry field, check box, radio button, and drop-down list are all directly supported via the #PROMPT statement.

#PROMPT places the prompt, the input control, and the symbol in a single statement. The general format is the #PROMPT keyword, the string to display the actual prompt, a variable type for the symbol, then the symbol or variable name. The Application Generator places the prompt and the control in the Procedure Properties or Actions dialog (depending on whether the prompt comes from a procedure template or a code, control, or extension template). When the developer fills the control with a value, then closes the dialog, the symbol holds the value.

The #BUTTON statement provides additional "space" for developer input when there is more developer input required than can fit in the one dialog. This places a button in the dialog, which displays an additional custom dialog when pressed. The additional dialogs are called "prompt pages."

#ENABLE allows prompts to be conditionally enabled based on the programmer's response to some other prompt. #BOXED supports logical grouping of related prompts. Once the programmer has input data into a prompt, the #VALIDATE statement allows the template to check its validity.

These tools provide a wide range of flexibility in the type of information a template can ask the programmer to provide. They also provide multiple ways to expedite the programmer's job, by providing "pick-lists" from which the programmer may choose wherever appropriate.

# **Template Structure**

### **Template Source Format**

The structure of the ASCII template source file is different than the structure of a Clarion source file. To read the ASCII source for a template, start out with the following guidelines:

- Any statement beginning with a pound symbol (#) identifies a template language statement.
- A percent sign (%) before an item within any statement (template or "target" language) identifies a template symbol (variable), which the Application Generator processes at code generation time.
- Any statement that begins without the pound (#) or percent (%) is a "target" language statement which is written directly into a source code file.

The template files are organized by code sections that terminate with the beginning of the next section or the end of the file. The template code generally divides into ten sections.

- #TEMPLATE begins a template set (template class). This is the first statement in the template set (required) which identifies the template set for the registry.
- #APPLICATION begins the source generation control section. This is the section of the template that controls the "target" language code output to source files, ready to compile. One registered template set must have a #APPLICATION section.
- #PROGRAM begins the global section of the generated source code, the main program module. One registered template set must have a #PROGRAM section.
- #MODULE begins a template section that generates the beginning code for a source code module other than the global (program) file. One registered template set must have a #MODULE section.
- #PROCEDURE begins a procedure template. This is the fundamental "target" language procedure generation template.
- #GROUP begins a reusable statement group containing code which may be #INSERTed into any other section of the template. This is the equivalent of a template language procedure.
- #CODE begins a code template section which generates executable code into a specific embed point. The developer can only insert them at an embed point within a procedure. A list of the available code templates appears from which to choose.
- #CONTROL begins a control template. Control templates place a related set (one or more) of controls on a procedure's window and generate the executable source code into embed points that provides the controls' standard functionality.
- #EXTENSION begins an extension template. Extension templates generate executable source code into one or more embed points of a procedure to add specific functionality to the procedure that is not "tied" to any window control.
- #UTILITY begins a utility execution section. This is an optional section of the template that
  performs a utility function, such as cross-reference or documentation generation. This is
  similar to #APPLICATION in that it generates output to ASCII files.

A template set must have a #TEMPLATE section to name the set for registration in the TemplateRegistry.TRF template registry file. At least one registered template set must have #APPLICATION, #PROGRAM, and #MODULE sections.

# The Template Registry File

The Template Registry file (TemplateRegistry.TRF) is a specialized data repository which stores template code and defaults in binary form. All the template elements available in the Application Generator come from the registry. As you add elements from the template into your application, the Application Generator retrieves the code from the registry then stores it along with your customizations, in the .APP file.

Storing the templates in a binary registry provides these advantages:

- Quick design-time performance.
- The ability to update the defaults in the registry using standard application development tools (such as the Window Formatter). For example, you can modify a procedure template's default window without writing template source code.

The sources for the TemplateRegistry.TRF are the template code files (.TPL and .TPW) which are installed in the TEMPLATE subdirectory. The Application Generator can read and register .TPL files, adding it to the template registry tree. The .TPW files usually contain additional procedure or code template source, which is processed along with the .TPL file by the #INCLUDE statement in the .TPL file. This allows the template author to logically separate disparate template components.

The default template file for the Clarion family is named *CW.TPL* (*ABCHAIN.TPL* for the ABC Family). This file uses the #INCLUDE statement to specify processing the the other .TPW files which appear in the \<*ClarionRoot*>\TEMPLATE directory.

# **Customizing Default Templates**

There are two methods for customizing the templates:

1. You can edit the template source code in the .TPL and .TPW files.

It is always a good idea to make a backup copy before making any modifications to the shipping templates.

When directly editing the template source code, you can change the type of source code it generates, or the logic it uses to generate the code. This is how you can make your templates generate source code the way you would write it if you were hand-coding the application.

You can also extend the functionality of the templates by adding your own features. For example, you may want to add prompts to each procedure template that allow you to generate a "comment block" at the beginning of each procedure containing procedure maintenance comments from the programmer maintaining the application.

Adding the following code to the end of any existing template set accomplishes this modification:

```
#EXTENSION(CommentBlock,'Add a comment block to the procedure'),PROCEDURE
    #PROMPT('Comment Line',@S70),%MyComment,MULTI('Programmer Comments')
#ATSTART
    #FOR(%MyComment)
    !%MyComment
#ENDFOR
#ENDAT
```

This code adds an extension template that is available for any procedure in the application. When you design your procedure, add the CommentBlock extension template to the procedure, then add comments to the Comment Line prompt each time you modify the procedure. At source generation time, each comment line will appear following an exclamation point (!). The block of comments appears in the code just before the PROCEDURE statement.

If you want this extension to be used in all the procedures you write, go into the Template Registry and add the extension to all the default procedures for each procedure template. This way, you can make sure it is always used, and you can even place its prompts on the Procedure Properties dialog by checking the Show on Properties box as you add the extension to the procedure template.

Once you make the changes, either choose the **Setup** Template Registry menu selection, open an existing application, or create a new application. Make sure the Re-register When Changed box is checked in the Registry Options dialog. The Application Generator automatically pre-processes the templates to update the registry when you have made changes to the template code files.

2. You can add to or edit the default user interface procedure template elements such as the standard window designs and report layouts, or your standard global and local data variables using the Template Registry.

When you highlight a procedure template in the Template Registry and press the Properties button, the Procedure Properties dialog appears, without all the custom prompts you would normally see when developing an application. Any button which is not dimmed in the Template Registry is available to you to create the default starting point for the procedure.

You can set up the procedure for the starting point that will get you furthest toward a complete procedure while requiring the least amount of customization from you at application design time. If the procedure allows it, you may use the window and report formatters, or define additional data, by pressing the appropriate buttons.

Once you've customized your template registry, you can also export your customizations to template source code files. This is useful for sharing your customizations with other developers.

To update the template source code with the customizations made in the Template Registry, press the Regenerate button in the Template Properties dialog. This updates the .TPL and .TPW files with the changes made.

# **Complete Alpha Listing**

# #! (template code comments)

#! comments

#! Initiates Template Language comments.

comments Any text.

#! initiates Template Language comments. All text to the right of the #! to the end of the text line is ignored by the Template file processor. #! comments are not included in the generated source code.

### Example:

- #! These are Template comments which
- #! will not end up in the generated code

# #\$ (embeditor comment)

#\$ embeditor text

#\$ Initiates a comment in the embeditor.

embededitor text Any comment text to display in the embeditor.

**#\$** initiates a text string which is displayed in the embeditor window only. This can be used to give the user more information about the generated procedure code and explain possibilities for embedded code within embed points.

### Example:

- #\$ More detailed information on embed point
- #\$ Field priming code (usually for Insert) goes here

# #? (conditional source line)

#?statement

#? Defines a single line of source code generated only if #RELEASE

commits the conditional source section.

statement A single line of target language code. This may contain template

symbols.

The #? statement defines a single line of source code that is generated only if a #RELEASE statement is encountered. This allows empty unnecessary "boiler-plate" code to be easily removed from the generated source.

A #EMBED that contains source to generate performs an implied #RELEASE. Any generated source output also performs an implied #RELEASE. Therefore, an explicit #RELEASE statement is not always necessary. The #? statement defines an individual conditional source line that does not perform the implied #RELEASE. When a #RESUME is executed without the output to the file being released, any conditional lines of code are un-done back to the matching #SUSPEND.

### **Example:**

```
ACCEPT
                               #!Unconditional source line
#SUSPEND
  #?CASE SELECTED()
                               #!Conditional source line
  #FOR(%ScreenField)
    #SUSPEND
  #?OF %ScreenField
                               #!Conditional source line
    #EMBED(%ScreenSetups, 'Control selected code'), %ScreenField
    #RESUME
  #?END
                               #!Conditional source line
#RESUME
#SUSPEND
  #?CASE EVENT()
                               #!Conditional source line
  #SUSPEND
  #?OF EVENT:AlertKey
                               #!Conditional source line
    #SUSPEND
    #?CASE KEYCODE()
                               #!Conditional source line
      #FOR %HotKey
        #RELEASE
    #?OF %HotKey
                               #!Conditional source line
      #EMBED(%HotKeyProc,'Hot Key code'),%HotKey
      #ENDFOR
                               #!Conditional source line
    #?END
    #RESUME
  #?END
                               #!Conditional source line
#RESUME
END
                               #!Unconditional source line
```

See Also: #SUSPEND, #RELEASE, #RESUME

# #< (aligned target language comments)</pre>

#<comments

#< Initiates an aligned target language comment.

comments Any text. This must start with the target language comment initiator.

**#<** initiates a target language comment which is included in the generated source code. The comment is generated at the column position specified by the #COMMENT statement. If the column position is occupied, the comment is appended one space to the right of the generated source code statement. Any standard target language syntax comments without a preceding #< are included in the generated code at whatever column position they occupy in the template.

#### **Example:**

#### #COMMENT (50)

#! This Template file comment will not be in the generated code
#<! This is a Clarion comment which appears in the generated code in column 50
! This Clarion comment appears in the generated code in column 2
#<// This is a C++ comment which appears in the generated code beginning in column 50
// This C++ comment appears in the generated code in column 2</pre>

See Also: #COMMENT

# **#ABORT** (abort source generation)

### #ABORT

The **#ABORT** statement immediately terminates source generation by the previous **#GENERATE** statement. **#ABORT** may be placed in any template section.

### Example:

```
#IF(%ValidRangeKey=%Null)
  #ERROR(%Procedure & ' Range Error: The range field is not in the primary key!')
#ABORT
#ENDIF
```

See Also: #GENERATE

# **#ACCEPT** (section valid for use)

**#ACCEPT** 

The **#ACCEPT** statement terminates #RESTRICT processing, indicating that the Template Code Section (#CODE, #CONTROL, #EXTENSION, #PROCEDURE, #PROGRAM, or #MODULE) is valid.

The #RESTRICT structure contains Template language *statements* that evaluate the propriety of generating the section's source code. The #ACCEPT statement may be used to explicitly declare the section as appropriate. An implicit #ACCEPT also occurs if the #RESTRICT *statements* execute without encountering a #REJECT statement. The #REJECT statement must be used to specifically exclude the section from use. Both the #ACCEPT and #REJECT statements immediately terminate processing of the #RESTRICT code.

### Example:

```
#CODE (ChangeControlSize, 'Change control size')
  #WHERE (%EventHandling)
  #RESTRICT
    #CASE (%ControlType)
    #OF 'LIST'
    #OROF 'BUTTON'
      #REJECT
    #ELSE
      #ACCEPT
    #ENDCASE
  #ENDRESTRICT
  #PROMPT('Control to change',CONTROL),%MyField,REQ
  #PROMPT('New Width',@n04),%NewWidth
  #PROMPT('New Height',@n04),%NewHeight
%MyField{PROP:Width} = %NewWidth
%MyField{PROP:Height} = %NewHeight
```

See Also: #RESTRICT,#REJECT

# **#ADD** (add to multi-valued symbol)

#ADD( symbol, expression [, position ] )

**#ADD** Adds a new instance to a multi-valued user-defined symbol.

symbol A multi-valued user-defined symbol.

expression An expression containing the value to place in the symbol's instance.

position An integer constant or symbol containing the instance number to add to the

*symbol.* Instance numbering begins with one (1). If the *position* is greater than the number of previously existing instances plus one, the new instance in

appended and no intervening instances are instantiated.

The **#ADD** statement adds a value to a multi-valued user-defined symbol. An implied #FIX to that symbol's instance occurs. If the symbol is not a multi-valued user-defined symbol then a source generation error is produced.

If the *symbol* has been declared with the UNIQUE attribute, then the #ADD is a union operation into the existing set of *symbol*'s values. Only one instance of the value being added may exist. Also, the UNIQUE attribute implies the #ADD is a sorted insert into the existing set of *symbol*'s values. After each #ADD, all of the *symbol*'s values will be in sorted order.

If the *symbol* has been declared without the UNIQUE attribute, duplicate values are allowed. The new value is added to the end of the list and may be a duplicate. If the *symbol* is a duplicate, then any dependent children instances are inherited.

### **Example:**

```
#DECLARE(%ProcFilesPrefix),MULTI,UNIQUE #!Declare unique multi-valued symbol
#FIX(%File,%Primary) #!Build list of all file prefiXEs in proc
#ADD(%ProcFilesPrefix,%FilePre) #!Start with primary file
#FOR(%Secondary) #!Then add all secondary files
#FIX(%File,%Secondary)
#ADD(%ProcFilesPrefix,%FilePre)
```

#### See Also:

#ENDFOR

#DECLARE

#FIX

#SELECT

# #ALIAS/#TRYALIAS (access a symbol from another instance)

```
#ALIAS( newsymbol , oldsymbol [, instance ] )
#TRYALIAS( newsymbol, oldsymbol [, instance])
```

#ALIAS / Declares a synonym for a user-defined symbol. **#TRYALIAS** 

newsymbol Specifies the new synonym for the oldsymbol.

The name of the symbol for which to declare a synonym. This must meet all the oldsymbol

requirements of a user-defined symbol. This must not be a #PROMPT symbol

or a variable in the same scope.

instance An expression containing the instance of the addition containing the oldsymbol.

The **#ALIAS** statement declares a synonym for the user-defined *oldsymbol* declared in a #CODE, #CONTROL, or #EXTENSION template prompt for use in another.

The **#TRYALIAS** statement is similar to **#ALIAS** except that the symbol is only defined by the template referred to by oldsymbol. If oldsymbol is not defined, no template error is posted.

#### **Example:**

```
#EXTENSION(GlobalSecurity, 'Global Password Check'), APPLICATION
 #DECLARE(%PasswordFile)
 #DECLARE (%PasswordFileKey)
#EXTENSION(LocalSecurity, 'Local Procedure Password Check'), PROCEDURE
  #ALIAS (%PswdFile, %PasswordFile, %ControlInstance)
 #ALIAS (%PswdFileKey,%PasswordFileKey,%ControlInstance)
#GROUP (%QueryHasLocator, %WhichInstance),AUTO
#TRYALIAS (%CurLocatorType, %LocatorType, %WhichInstance)
#IF (VAREXISTS(%CurLocatorType))
 #RETURN (%CurLocatorType)
#END
#RETURN ''
```

See Also: #CODE ,#CONTROL ,#EXTENSION

# **#APPEND** (add to source file)

#APPEND( file ) [, SECTION ]

**#APPEND** Adds the *file* contents to the end of the current source output

destination file.

file A string constant, template symbol, or expression containing a DOS

file specification. This may be a fully qualified DOS pathname.

**SECTION** Specifies the error position of embedded source code is correctly

patched to reflect the actual position in the generated code.

The **#APPEND** statement adds the complete contents of the *file* to the end of the current source output destination file. The contents of the *file* are NOT interpreted for source generation purposes. Therefore, the *file* should not contain any Template Language code.

If the file does not exist, #APPEND is ignored and source generation continues.

### **Example:**

```
#FOR(%Module)
 #SET(%TempModuleFile,(%Module & '.$$$'))
                                                     #!Set temp module file
 #CREATE(%TempModuleFile)
                                                     #!Create temp module file
 #FOR(%ModuleProcedure)
                                                     #!For all procs in module
    #FIX(%Procedure,%ModuleProcedure)
                                                     #!Fix current procedure
    #GENERATE (%Procedure)
                                                     #!Generate procedure code
  #ENDFOR
                                                     #!EndFor all procs in module
 #SET(%ModuleFile,(%Module & '.CLW'))
                                                     #!Set to current module file
 #CREATE(%ModuleFile)
                                                     #!Create module file
 #GENERATE (%Module)
                                                     #!Generate module header
  #APPEND(%TempModuleFile),SECTION
                                                     #!Add generated procedures
#ENDFOR
```

See Also: #SECTION

### **#APPLICATION** (source generation control section)

#APPLICATION( description ) [, HLP( helpid ) ] [ APPLICATION( [ child(chain) ]

**#APPLICATION** Begins source generation control section.

description A string constant describing the application section.

**HLP** Specifies on-line help is available.

helpid A string constant containing the identifier to access the Help system. This may

be either a Help keyword or "context string."

**APPLICATION** Tells the Application Generator to automatically place the named) child

template on every procedure.

child(chain) The name of a #EXTENSION with the PROCEDURE attribute to automatically

populate into every generated procedure when the #EXTENSION with the

APPLICATION attribute is populated.

The **#APPLICATION** statement marks the beginning of a source generation control section. The section is terminated by the next Template Code Section (#PROGRAM, #MODULE, #PROCEDURE, #CONTROL, #CODE, #EXTENSION, #UTILITY, or #GROUP) statement. The Template statements contained in this section control the source generation process. Only one #APPLICATION section is allowed in a single Template set. Actual source generation is done by the #GENERATE statement.

Any User-defined symbols defined in the #APPLICATION section are available for use in any Template Code Section that is generated. Any prompts in this section are placed on the Global Properties window and have global scope.

#### **Example:**

```
#APPLICATION('Example Application Section')
                                                   #!Generate entire application
#PROMPT('Enable &Shared Files',CHECK), %SharedFiles
#PROMPT('Close Unused &Files', CHECK), %CloseFiles, DEFAULT(1)
#BUTTON('.INI File Settings')
 #PROMPT('Use .INI file',CHECK),%INIActive,DEFAULT(1)
  #ENABLE (%INIActive)
    #PROMPT('.INI File to use',DROP,'Program Name.INI|Other'),%INIFile
    #ENABLE(%INIFile='Other')
      #PROMPT('File Name',@S40),%ININame
    #ENDENABLE
    #PROMPT('Save Window Locations', CHECK), %INISaveWindow, DEFAULT(1)
  #ENDENABLE
#ENDBUTTON
#!
#!Global Template Declarations.
#MESSAGE('Generating ' & %Application,0) #! Open the Message Box
#DECLARE(%FilesUsed),UNIQUE,MULTI
                                                   #! Label of every file used
#DECLARE(%FilePut,%FilesUsed)
                                                   #! "Yes" for RI PUT used
                                                   #! "Yes" for RI DELETE used
#DECLARE(%FileDelete,%FilesUsed)
#DECLARE(%ModuleFilesUsed,%Module),UNIQUE,MULTI,SAVE #!Name of file used in module
#DECLARE(%ModuleFilePut,%ModuleFilesUsed),SAVE
                                                  #! "Yes" for RI PUT used
#DECLARE(%ModuleFileDelete,%ModuleFilesUsed),SAVE #! "Yes" for RI DELETE used
```

```
#DECLARE(%IniFileName)
                                                   #! Used to construct INI file
#DECLARE (%ModuleProcs,%Module),MULTI,SAVE,UNIQUE #! Program MAP prototype
#DECLARE (%ModulePrototype,%ModuleProcs)
                                                   #! Module MAP prototype
#DECLARE (%AccessMode)
                                                   #! File open mode equate
#DECLARE(%BuildFile)
                                                   #! Construction filename
#1
#!Initialization Code for Global User-defined Symbols.
                                                   #! IF Shared Files Enabled
#IF(%SharedFiles)
  #SET (%AccessMode, '42h')
                                                   #! default access 'shared'
                                                   #! ELSE (IF NOT Shared Files ..)
#ELSE
  #SET (%AccessMode, '22h')
                                                   #! default access 'open'
#ENDIF
                                                   #! END (IF Shared Files ...)
#IF(%INIFile = 'Program Name.INI')
                                                   #! IF using program.ini
  #SET(%INIFileName, %Application & '.INI')
                                                   #! SET the file name
                                                   #! ELSE (IF NOT using Program.ini)
  #SET(%INIFileName,%ININame)
                                                   #! SET the file name
#ENDIF
                                                   #! END (IF using program.ini)
#!
#! Main Source Code Generation Loop.
#DECLARE (%GlobalRegenerate)
                                                   #! Flag that controls generation
#IF(~%ConditionalGenerate OR %DictionaryChanged OR %RegistryChanged)
  #SET(%GlobalRegenerate,%True)
                                                   #! Generate Everything
#ELSE
                                                   #! ELSE (If no global change)
  #SET(%GlobalRegenerate,%False)
                                                   #! Generate changed modules only
#ENDIF
                                                   #! END (IF Global Change)
#SET(%BuildFile,(%Application & '.TM$'))
                                                   #! Make temp program filename
#FOR(%Module), WHERE (%Module <> %Program)
                                                   #! For all member modules
  #MESSAGE('Generating Module:
                                  ' & %Module, 1) #! Post generation message
  #IF(%ModuleChanged OR %GlobalRegenerate)
                                                   #! IF module to be generated
    #FREE(%ModuleProcs)
                                                   #! Clear module prototypes
    #FREE (%ModuleFilesUsed)
                                                   #! Clear files used
    #CREATE(%BuildFile)
                                                   #! Create temp module file
    #FOR(%ModuleProcedure)
                                                   #! FOR all procs in module
      #FIX(%Procedure,%ModuleProcedure)
                                                   #! Fix current procedure
      #MESSAGE('Generating Procedure: ' & %Procedure, 2) #! Post generation message
      #GENERATE (%Procedure)
                                                   #! Generate procedure code
    #ENDFOR
                                                   #! END (For all procs in module)
    #CLOSE(%BuildFile)
                                                   #! Close last temp file
    #CREATE (%Module)
                                                   #! Create a module file
    #GENERATE (%Module)
                                                   #! Generate module header
    #APPEND(%BuildFile)
                                                   #! Append the temp mod file
    #CLOSE (%Module)
                                                   #! Close the module file
  #ENDIF
                                                   #! END (If module to be...)
#ENDFOR
                                                   #! END (For all member modules)
#FIX(%Module,%Program)
                                                   #! FIX to program module
#MESSAGE('Generating Module: ' & %Module, 1)
                                                   #! Post generation message
#FREE (%ModuleProcs)
                                                   #! Clear module prototypes
#FREE (%ModuleFilesUsed)
                                                   #! Clear files used
#CREATE(%BuildFile)
                                                   #! Create temp module file
#FOR(%ModuleProcedure)
                                                   #! For all procs in module
  #FIX(%Procedure,%ModuleProcedure)
                                                   #! Fix current procedure
  #MESSAGE('Generating Procedure: ' & %Procedure, 2) #! Post generation message
  #GENERATE (%Procedure)
                                                   #! Generate procedure code
#ENDFOR
                                                   #! EndFor all procs in module
#CLOSE()
                                                   #! Close last temp file
See Also: #GENERATE, #PROMPT
```

23

# **#ASSERT** (evaluate assumption)

#ASSERT( condition [, message])

**#ASSERT** Evaluates assumptions to detect unexpected errors.

condition An expression that should always evaluate as true.

message A string constant containing the text to display if the condition is not true. If

omitted, the text of the condition is displayed.

**#ASSERT** evaluates assumptions to detect unexpected errors. #ASSERT evaluates the *condition* expression and displays the *message* if the *condition* is not true. This allows you to test the veracity of any programming assumptions you are making at any point in your template code.

#### Example:

```
#ASSERT(%False) #!Displays '%False'
#ASSERT(%False, 'Message Text') #!Displays 'Message Text'
```

# **#AT** (insert code in an embed point)

**#AT(** location[, instances])[, WHERE(expression)][, AUTO][, PRESERVE][, DESCRIPTION(text)]
[, PRIORITY( number)][, FIRST][, LAST]

statements

**#ENDAT** 

**#AT** Specifies a *location* to generate *statements*.

location An #EMBED identifier. This may be a #EMBED for a procedure that comes

from another template set.

instances The location parameters that identify the embedded source code point for a

multi-valued #EMBED *identifier*. There may as many *instance* parameters as are required to explicitly identify the embedded source code point. These

instances are omittable.

WHERE More closely specifies the #AT *location* as only those embed points where the

expression is true.

expression An expression that specifies exact placement.

**AUTO** Opens a new scope for the #AT. This means that any #DECLARE statements

in the #AT would not be available to the #PROCEDURE being generated.

**PRESERVE** Preserves the current fixed instances of all built-in multi-valued symbols when

the #AT is called and restores all those instances when the #AT code

terminates.

**DESCRIPTION** Specifies *text* that will be displayed at the embed tree node specified by the

location.

**PRIORITY** Specifies the order inwhich the #AT is generated into the *location*. The lowest

value generates first. If omitted, the PRIORITY is assumed to be 5000.

*number* An integer constant in the range 1 to 10000.

FIRST Equivalent to PRIORITY(1).

**LAST** Equivalent to PRIORITY(10000).

statements Template and/or target language code.

**#ENDAT** Terminates the section.

The **#AT** structure specifies a *location* to generate *statements*. #AT is valid only in a #CONTROL, #CODE, or #EXTENSION templates, and is used to allow them to generate *statements* into multiple *locations*. The #AT structure must terminate with **#ENDAT**.

The WHERE clause allows you to create an *expression* that can specify a single specific instance of a #EMBED that has a *symbol* attribute. You may not place #AT within any type of conditional structure (such as #IF or #CASE). If you need to conditionally generate the code, place the #IF or #CASE structure within the #AT structure.

### Example:

```
#CONTROL(BrowseList,'Add Browse List controls')
    #AT(%ControlEvent,'?Insert','Accepted'),PRIORITY(5000)
    #IF(%InsertAllowed)
GlobalRequest = InsertRecord
%UpdateProc
    #ENDIF
    #ENDAT
#!
See Also: #EMBED, #CODE, #CONTROL, #EXTENSION, #RESTRICT
```

# **#ATEND** (template reset code)

**#ATEND** 

statements

**#ENDAT** 

**#ATEND** Specifies template code to execute after the #PROCEDURE, #CODE,

#CONTROL, or #EXTENSION generates.

statements Template language code.

**#ENDAT** Terminates the section.

The **#ATEND** structure specifies template code to execute after the #PROCEDURE, #CODE, #CONTROL, or #EXTENSION generates its code. Therefore, the *statements* should only contain Template language. #ATEND is usually used to reset internal template variables. You may not place #ATEND within any type of conditional structure (such as #IF or #CASE). If you need to conditionally generate the code, place the #IF or #CASE structure within the #ATEND structure.

### Example:

```
#CONTROL(BrowseList,'Add Browse List controls')
#ATEND
#SET(%ListQueue,%NULL)
#ENDAT
```

See Also: #PROCEDURE, #CODE, #CONTROL, #EXTENSION

# **#ATSTART** (template initialization code)

**#ATSTART** 

statements

**#ENDAT** 

**#ATSTART** Specifies template code to execute before the #PROCEDURE, #CODE,

#CONTROL, or #EXTENSION generates.

statements Template language code.

**#ENDAT** Terminates the section.

The **#ATSTART** structure specifies template code to execute before the #PROCEDURE, #CODE, #CONTROL, or #EXTENSION generates its code. Therefore, the *statements* should normally only contain Template language. #ATSTART is usually used to initialize internal template variables. You may not place #ATSTART within any type of conditional structure (such as #IF or #CASE). If you need to conditionally generate the code, place the #IF or #CASE structure within the #ATSTART structure.

#### **Example:**

See Also: #PROCEDURE, #CODE, #CONTROL, #EXTENSION

### **#BOXED** (prompt group box)

```
#BOXED([ string ] ) [, AT( ) ] [, WHERE( expression ) ] [, CLEAR ] [, HIDE ] [, SECTION ]
prompts
#ENDBOXED
```

**#BOXED** Creates a group box of *prompts*.

string A string constant containing the text to display as the group box caption.

AT Specifies the position of the group in the window, relative to the first prompt

placed on the window from the Template (excluding the standard prompts on every procedure properties window). This attribute takes the same parameters as the Clarion language AT attribute.

WHERE Specifies the #BOXED is visible only for those instances where the expression

is true.

*expression* An expression that specifies the condition for use.

**CLEAR** Specifies the *prompts* symbol values are cleared when disabled.

**HIDE** Specifies the *prompts* are hidden if the WHERE *expression* is false when the

dialog is first displayed. If no WHERE attribute is present, prompts are always

hidden.

**SECTION** Specifies all AT() attributes for the *prompts* are positioned relative to the start of

the #BOXED section.

prompts One or more #PROMPT statements. This may also contain #DISPLAY,

#VALIDATE, #ENABLE, #PREPARE, and #BUTTON statements.

**#ENDBOXED** Terminates the group box of *prompts*.

The **#BOXED** statement creates a group box displaying the *string* as its caption. If the WHERE attribute is present, the *prompts* are hidden or visible based upon the evaluation of the *expression*. If the *expression* is true, the *prompts* are visible, otherwise they are hidden.

### Example:

See Also: #PROMPT ,#VALIDATE

# **#BREAK** (break out of a loop)

#### **#BREAK**

The **#BREAK** statement immediately breaks out of the #FOR or #LOOP structure in which it is enclosed. Control passes to the next statement following the #ENDFOR or #ENDLOOP. #BREAK is only valid within a #FOR or #LOOP structure, else an error is generated during Template file pre-processing. #BREAK acts as a #RETURN statement if issued from within a #GROUP inserted in the loop (unless it is within a #FOR or #LOOP structure completely contained within the #GROUP).

### Example:

```
#SET(%StopFile,'CUSTOMER')
#FOR(%File)
#IF (UPPER(%File) = %StopFile)
#BREAK
#ENDIF
OPEN(%File)
#ENDFOR
```

### **#BUTTON** (call another page of prompts)

#BUTTON (string [, icon ]) [, HLP( id )] [, AT()] [, REQ ] [, INLINE] [, WHENACCEPTED(group)]

[,| FROM( fromsymbol, expression ) [, WHERE( condition ) ]| ]

| MULTI( multisymbol, expression ) |

prompts

**#ENDBUTTON** 

**#BUTTON** Creates a command button to call another page of *prompts*.

string An expression containing the text to display on the button's face. This may

contain an ampersand (&) to indicate the "hot" letter for the button.

icon A string constant containing the name of an .ICO file or standard icon to

display on the button's face. The string then serves only for "hot" key

definition.

**HLP** Specifies on-line help is available for the #BUTTON.

id A string constant containing the identifier to access the Help system. This

may be either a Help keyword or "context string."

**AT** Specifies the position of the button in the window, relative to the first

prompt placed on the window from the Template (excluding the standard prompts on every procedure properties window). This attribute takes the same parameters as the Clarion language AT attribute. Specifying zero width and height indicates the #BUTTON occupies no space on the

prompt dialog.

**REQ** Specifies the programmer must press the button at least once when the

procedure is created.

**FROM** Specifies the programmer may enter a set of values for the *prompts* for

each instance of the fromsymbol.

fromsymbol A built-in multi-valued symbol which pre-defines all instances on which the

prompts symbols are dependent. The programmer may not add, change,

or delete instances of the fromsymbol.

expression A string expression to format data display in the multiple value display list

box.

WHERE Specifies the #BUTTON displays only those instances of the *fromsymbol* 

where the condition is true.

condition An expression that specifies the condition for use.

MULTI Specifies the programmer may enter multiple sets of values for the

prompts. This allows multiple related groups of prompts.

multisymbol A user-defined symbol on which all the prompts symbols are dependent.

This symbol is internally assigned a unique value for each set of *prompts*.

**INLINE**The multiple values the programmer enters for the #BUTTON appears as

a list box with update buttons which allow the programmer to enter multiple values. The MULTI or FROM attribute must also be present.

WHENACCEPTED Specifies the named *group* to execute when the #BUTTON is pressed.

group The name of the #GROUP to execute.

prompts One or more #PROMPT statements. This may also contain #DISPLAY,

#VALIDATE, #ENABLE, and #BUTTON statements.

**#ENDBUTTON** Terminates the group of *prompts* which are on the page called by the

**#BUTTON.** 

The **#BUTTON** statement creates a command button displaying either the *string* or the *icon* on its face. When the programmer presses the button, a new page of *prompts* appears for selection and entry.

Each new page of *prompts* has its own OK, CANCEL, and TEMPLATE HELP buttons as standard fields. All other fields on the page are generated from the *prompts* within the #BUTTON structure.

Each page's OK button closes the current page of *prompts*, saving the data the programmer entered in the *prompts*, then returns to the prior window. The CANCEL button closes the current page of *prompts* without saving, then returns to the prior window. If the page calls another page with a nested #BUTTON statement and the programmer presses OK on the lowest level page, then CANCEL on the page that called it, the entire transaction is cancelled.

The MULTI attribute specifies the programmer may enter multiple sets of values for the *prompts*. The button calls a window containing a list box to display all the multiple values entered for the sets of *prompts*, along with Insert, Change, and Delete buttons. These three buttons call another window containing all the *prompts* to allow the programmer to update the entries in the list. The *expression* is used to format the information for display in the list box.

The FROM attribute also specifies the programmer may enter multiple sets of values for the *prompts*. The button calls a window containing a list box that displays each instance of the *fromsymbol*, along with an Edit button. This button calls another window containing all the *prompts* to allow the programmer to update the entries associated with that instance of the *fromsymbol*. The *expression* is used to format the information for display in the list box. The WHERE attribute may be used to limit the instances of the *fromsymbol* to only those that meet the WHERE *condition*.

### Example:

```
#PROMPT('Name a File',FILE),%FileName
                                                  #!Prompt on the first page
#BUTTON('Page Two')
                                                  #!Button on first page calls
 #PROMPT('Pick One',OPTION),%InputChoice
                                                  #!These prompts on second page
 #PROMPT('Choice One',RADIO)
 #PROMPT('Choice Two', RADIO)
 #ENABLE(%InputChoice = 'Choice Two')
    #PROMPT('Screen Field', CONTROL), %SomeField
    #VALIDATE(%ScreenFieldType = 'LIST','Must select a list box')
  #ENDENABLE
#ENDBUTTON
                                                  #!Terminate second page prompts
#PROMPT('Enter some value',@S20),%InputValue1
                                                  #!Another prompt on first page
#!Multiple input button:
#BUTTON('Multiple Names'), MULTI(%ButtonSymbol,%ForeName & ' ' & %SurName)
 #PROMPT('First Name',@S20),%ForeName
 #PROMPT('Last Name',@S20),%SurName
#ENDBUTTON
                                                  #!Terminate second page prompts
#PROMPT('Enter another value', @S20), %InputValue2 #!Another prompt on first page
 #!Multiple input button dependent on %File:
#BUTTON('File Options'),FROM(%File)
 #PROMPT('Open Access Mode',DROP('Open|Share'),%FileOpenMode
#ENDBUTTON
                                                  #!Terminate second page prompts
```

See Also: #PROMPT, #VALIDATE, #ENABLE

### **#CALL** (insert code from a #GROUP, without indention)

**#CALL(** symbol [ ( set ) ] [, parameters ] ) [, returnvalue ]

**#CALL** Inserts code from a #GROUP, retaining the indention in its #GROUP.

symbol A symbol that names a #GROUP section.

set The #TEMPLATE name parameter for the template set to which the

#GROUP belongs. If omitted, the #GROUP must be of the same template set *name* as the #PROCEDURE in which it is used.

parameters The parameters passed to the #GROUP. Each parameter must be

separated by a comma. All parameters defined for the #GROUP must

be passed; they may not be omitted.

returnvalue A symbol to receive the value returned by the #RETURN statement.

The **#CALL** statement places the code from the #GROUP named by the *symbol*, retaining the indention in its #GROUP--any source in column 1 in the #GROUP is generated into column 1, no matter where the #CALL is placed This is equivalent to using #INSERT with the NOINDENT parameter.

The *set* parameter specifies the #TEMPLATE that contains the #GROUP. This allows any Template to use #GROUP code from any other registered Template. The *parameters* passed to the #GROUP fall into two categories: value-parameters and variable-parameters. Value-parameters are declared by the #GROUP as a user-defined symbol, while variable-parameters are declared by the #GROUP as a user-defined symbol with a prepended asterisk (\*). Either a symbol or an expression may be passed as a value-parameter. Only a symbol may be passed as a variable-parameter.

The *returnvalue* symbol receives the value returned by the #GROUP from the #RETURN statement that terminates the #GROUP. If the #GROUP does not contain a #RETURN statement, or that #RETURN does not have a parameter, then the value received is an empty string (").

#### **Example:**

```
#CALL(%SomeGroup) #!Ordinary insert retaining original indention
#CALL(%GenerateFormulas(Clarion)) #!Insert #GROUP from Clarion Template
#CALL(%FileRecordFilter,%Secondary) #!Insert #GROUP with passed parameter
#!#GROUP from Clarion Template with two passed parameters
#CALL(%FileRecordFilter(Clarion),%Primary,%Secondary)
```

See Also: #GROUP, #INSERT, #INVOKE, #RETURN

### **#CASE** (conditional execution structure)

```
#CASE( condition )
#OF( expression )
[ #OROF( expression ) ]
statements
[ #ELSE
  statements ]
#ENDCASE
```

**#CASE** Initiates a selective execution structure.

condition Any Template Language expression which returns a value.

**#OF** The #OF statements are executed when the #OF expression is equal to

the condition of the CASE. There may be many #OF options in a

#CASE structure.

expression Any Template Language expression which returns a value.

**#OROF** The #OROF statements are executed when the #OROF expression is

equal to the condition of the #CASE. There may be many #OROF

options associated with one #OF option.

**#ELSE** The #ELSE statements are executed when all preceding #OF and

#OROF *expressions* are not equal to the *condition* of the #CASE. #ELSE (if used) must be the last option in the #CASE structure.

statements Any valid executable source code.

**#ENDCASE** Terminates the #CASE structure.

A **#CASE** structure selectively executes *statements* based on equivalence between the #CASE *condition* and one of the #OF or #OROF *expressions*. If there is no exact match, the *statements* following #ELSE are executed. The #CASE structure must be terminated by **#ENDCASE**. If there is no #ENDCASE, an error message is issued during Template file pre-processing. #CASE structures may be nested within other #CASE structures.

```
#CASE(%ScreenField)
#OF('?Ok')
  #INSERT(%OkButtonGroup)
#OF('?Cancel')
#OROF('?Exit')
  #INSERT(%CancelButtonGroup)
#ELSE
  #INSERT(%OtherControlsGroup)
#ENDCASE
```

### **#CLASS** (define a formula class)

#CLASS( string, description )

**#CLASS** Defines a formula class.

string A string constant containing the formula class.

description A string expression containing the description of the formula class to display

in the list of those available in the Formula Editor.

The **#CLASS** statement defines a formula class for use in the Formula Editor. The Formula Class allows the Template to determine the precise logical position at which the formula appears in the generated source code.

## **#CLEAR** (clear single-valued symbol)

#CLEAR( symbol)

**#CLEAR** Removes the value from a single-valued user-defined symbol.

symbol A single-valued user-defined symbol.

The **#CLEAR** statement removes the value from a single-valued user-defined symbol. This statement is approximately the same as using #SET to assign a null value to the *symbol*, except it is more efficient.

### Example:

```
#DECLARE(%SomeSymbol) #!Declare symbol
#SET(%SomeSymbol,'Value') #!Assign a value
#!%SomeSymbol now contains: 'Value'
#CLEAR(%SomeSymbol) #!Clear value
#!%SomeSymbol now contains: ''
```

See Also: #DECLARE, #ADD, #FREE

### **#CLOSE** (close source file)

#CLOSE([file])[, READ]

**#CLOSE** Closes an open generated source code disk file.

file A string constant, template symbol, or expression containing a DOS

file specification. This may be a fully qualified DOS pathname. If omitted, the current disk file receiving generated source code is

closed.

**READ** Closes the read-only input file.

The **#CLOSE** statement closes an open disk file receiving the generated source code. If the *file* is omitted, the current disk file receiving generated source code is closed. If the *file* does not exist, or is already closed, a source generation error is produced.

#### **Example:**

```
#SET(%NewProgramFile,(%Application & '.$$$'))
                                                  #!Temp new program filename
#CREATE(%NewProgramFile)
                                                  #!Create new program file
#GENERATE (%Program)
                                                  #!Generate main program header
#CLOSE (%NewProgramFile)
                                                  #!Create new program file
#OPEN(%ProgramFile),READ
                                                  #!Open it in read-only mode
#DECLARE (%ASCIIFileRecord)
#LOOP
 #READ (%ASCIIFileRecord)
 #! Parse the line and do something with it
 #IF(%ASCIIFileRecord = %EOF)
 #BREAK
 #ENDIF
#ENDLOOP
#CLOSE(%ProgramFile),READ
                                                  #!Close the read-only file
```

See Also: #OPEN ,#READ ,#CREATE

### **#CODE** (define a code template)

#CODE( name,description [,target]) [, SINGLE][, HLP( helpid)] [, PRIMARY( message [, flag])]

[, DESCRIPTION( expression ) ] [, ROUTINE ]

[, PRIORITY( number)] [, REQ( addition [,| BEFORE| ] ) ] [,| FIRST| ]

|AFTER| |LAST|

**#CODE**Begins a code template that generates source into an embedded source code

point.

name The label of the code template. This must be a valid Clarion label.

description A string constant describing the code template.

target A string constant that specifies the source language the code template

generates. If omitted, it defaults to Clarion. This restricts the #CODE to

matching target language use, only.

**SINGLE** Specifies the #CODE may be used only once in a given procedure (or program,

if the embedded source code point is global).

**HLP** Specifies on-line help is available.

helpid A string constant containing the identifier to access the Help system. This may

be either a Help keyword or "context string."

**PRIMARY** Specifies a primary file for the code template must be placed in the procedure's

Data / Tables Pad.

message A string constant containing a message that appears in the Data / Tables Pad

next to the #CODE's Primary file.

flag Either OPTIONAL (the file is not required), OPTKEY (the key is not required),

or NOKEY (the file is not required to have a key).

**DESCRIPTION** Specifies the display description of a #CODE that may be used multiple times

in a given application or procedure.

expression A string constant or expression that contains the description to display.

**ROUTINE** Specifies the generated code is not automatically indented from column one.

**PRIORITY** Specifies the order in which the #CODE is generated into the embed point. The

lowest value generates first. If omitted, the PRIORITY is assumed to be 5000.

*number* An integer constant in the range 1 to 10000.

**REQ** Specifies the #CODE requires a previously placed #CODE, #CONTROL, or

#EXTENSION before it may be used. It also means all prompts and variables of

the required addition are available to it.

addition The name of the previously placed #CODE, #CONTROL, or #EXTENSION

template, from any template set.

**BEFORE** Legacy attribute, replaced by PRIORITY.

**AFTER** Legacy attribute, replaced by PRIORITY.

**FIRST** Equivalent to PRIORITY(1).

**LAST** Equivalent to PRIORITY(10000).

**#CODE** defines the beginning of a code template which can generate code into embedded source code points. A #CODE section may contain Template and/or target language code. The #CODE section is terminated by the first occurrence of a Template Code Section (#PROGRAM, #MODULE, #PROCEDURE, #CONTROL, #CODE, #EXTENSION, or #GROUP) statement, or the end of the file. Within a single Template set, separate #CODE sections may not be defined with the same *name*.

#CODE generates its code into a #EMBED embedded source code point. The generated code is automatically indented when placed in ROUTINEs, unless the ROUTINE attribute is present. A #CODE section may contain #PROMPT statements to prompt for the values needed to generate proper source code. It may also contain #EMBED statements, which become active only if the #CODE section is used.

You can use the #WHERE statement to limit the availability of the #CODE to those embedded source code points where the generated code would be appropriate. A #CODE may contain multiple #WHERE statements to explicitly define all the valid embedded source code points in which it may appear. #RESTRICT can also further restrict the availability of the #CODE based on an expression or Template language statements.

The #AT/#ENDAT structure allows a single #CODE to generate code into multiple embedded source code points to support its functionality.

```
#CODE(ChangeProperty,'Change control property')
  #WHERE(%SetupWindow..%ProcedureRoutines) #!Appropriate only after window open
  #PROMPT('Control to change',CONTROL),%MyField,REQ
  #PROMPT('Property to change',@S20),%Property,REQ
  #PROMPT('New Value',@S20),%Value,REQ
%MyField{%Property} = '%Value' #<!Change the %Property of %MyField

See Also: #EMBED,
#WHERE,
#RESTRICT,
#AT (insert code in an embed point)</pre>
```

# **#COMMENT** (specify comment column)

#COMMENT( column )

**#COMMENT** Sets the default column number for aligned comments.

column A numeric constant in the range 1 to 255.

The **#COMMENT** statement sets the default column number in which Clarion comments prefaced with the #<! statement will be generated by the Application Generator.

### **Example:**

```
#COMMENT(50) #!Set comment column
IF Action = 1 #<!If adding a record
   SomeVariable = InitVariable
END</pre>
```

See Also: #<

### **#CONTEXT** (set template code generation context)

#CONTEXT( section [, instance])

statements

**#ENDCONTEXT** 

**#CONTEXT** Sets the code generation context to emulate generating the named section.

section One of the following valid symbols: %Application, %Procedure, %Module, or

%Program.

instance A symbol containing a valid instance number of a code, control, or extension

template used in the named section.

statements Template language code.

**#ENDCONTEXT** Terminates the context change.

The **#CONTEXT** structure specifies template code that executes as if the source code for the named *section* were being generated. Once the context has been set, all the prompt symbols, declared symbols, and embeds in the named *section* are in scope and available for use in the #CONTEXT *statements*. If an *instance* is specified, the prompts for the corresponding component are brought into scope. #CONTEXT is valid for use anywhere in template code.

The key to understanding the use of the #CONTEXT structure is "as if the source code for the named section were being generated." This statement means that the statements are evaluated as if #GENERATE were executing. For example, a #EMBED statement within a #CONTEXT structure does not name a new embed point but instead, generates the contents of the named embed point.

### **Example:**

#CODE(StealSomeCode,'Preparing to Process the Window Code Stealer')
#PROMPT('Procedure Name',FROM(%Procedure)),%ProcToStealFrom,REQ
#FIX(%Procedure,%ProcToStealFrom)
#CONTEXT(%Procedure)
#EMBED(%BeforeAccept,'Preparing to Process the Window')
#ENDCONTEXT

See Also: #CODE, #CONTROL, #EXTENSION

### **#CREATE** (create source file)

#CREATE( file )

**#CREATE** Creates a disk file to receive generated source code.

file A string constant, template symbol, or expression containing a DOS

file specification. This may be a fully qualified DOS pathname.

The **#CREATE** statement creates a disk file to receive the source code generated by #GENERATE. If the *file* does not exist, it is created. If the *file* already exists, it is opened and emptied (truncated to zero length). If the *file* is already open, a source generation error is produced.

The *file* is automatically selected as the active source output destination. Any file that is created must be closed with a #CLOSE statement.

#### **Example:**

```
#SET(%NewProgramFile,(%Application & '.$$$')) #!Temp new program filename
#CREATE(%NewProgramFile) #!Create new program file
#GENERATE(%Program) #!Generate main program header
```

See Also: #CLOSE

### **#CYCLE** (cycle to top of loop)

#CYCLE

The **#CYCLE** statement immediately passes control back to the top of the #FOR or #LOOP structure in which it is enclosed to begin the next iteration. #CYCLE is only valid within a #FOR or #LOOP structure, else an error is generated during Template file pre-processing. #CYCLE acts as a #RETURN statement if issued from within a #GROUP inserted in the loop (unless it is within a #FOR or #LOOP structure completely contained within the #GROUP).

#### Example:

```
#SET(%StopFile,'CUSTOMER')
#FOR(%File)
#IF (UPPER(%File) <> %StopFile)
    OPEN(%File)
    #CYCLE
#ELSE
    #BREAK
#ENDIF
#ENDFOR
```

### **#DEBUG** (toggle debug generation)

#DEBUG( value )

**#DEBUG** Toggles debug generation on and off.

value A symbol containing zero (0) or one(1). When zero, debug generation is

turned off. When one, debug generation is turned on.

The **#DEBUG** statement toggles debug generation on and off, and overrides the Debug Generation setting in the Application Options dialog. When this is checked, **#DEBUG** controls the specific sections to output to the text file, so the file can be restricted to a manageable size.

### **#DECLARE** (declare a user-defined symbol)

#DECLARE( symbol [, type ] ) [, MULTI ] [, UNIQUE ] [, SAVE ]
#DECLARE( symbol [, parentsymbol] [, type ] ) [, MULTI ] [, UNIQUE ] [, SAVE ]

**#DECLARE** Explicitly declares a user-defined symbol.

symbol The name of the symbol being declared. This must meet all the

requirements of a user-defined symbol. This must not be a #PROMPT

symbol or a variable in the same scope.

parentsymbol Specifies the parent of the symbol, indicating its value is dependent

upon the current value in another symbol. This must be a multi-valued symbol. You may specify more than one *parentsymbol* if the *symbol* is dependent upon a set of symbols. This allows implicit multi-dimensional

arrays.

type The data type of the symbol: LONG, REAL, or STRING. If omitted, the

data type is STRING.

**MULTI** Specifies the *symbol* may contain multiple values.

**UNIQUE** Specifies a multi-valued symbol that cannot contain duplicate values.

The values are stored in ascending order. This implicitly declares the

symbol as multi-valued, the MULTI attribute is not required.

**SAVE** Specifies the value(s) in the *symbol* are saved between source

generation sessions. A symbol with the SAVE attribute may only be

declared in the #APPLICATION area.

The **#DECLARE** statement explicitly declares a user-defined *symbol*. This may contain a single value or multiple values. All user-defined symbols must be explicitly declared with #DECLARE except those declared on #GROUP parameters, and #PROMPT or #EQUATE statements.

The MULTI attribute declares the *symbol* as multi-valued. This allows the #FIX, #FOR, #ADD, #DELETE, #SELECT, and #FREE statements to operate on the *symbol*.

The UNIQUE attribute ensures all instances of a multi-valued *symbol* to be unique and sorted in ascending sequence. When UNIQUE is specified, MULTI is not required. The #ADD statement builds the *symbol* values in sorted order and only allows a single instance of every value in the *symbol* when each entry is added.

If the #DECLARE statement contains one or more *parentsymbol* parameters, the user-defined *symbol* is dependent on the *parentsymbols*. This means a separate instance (or instances, if multi-valued) of the *symbol* is available for each instance of the *parentsymbol*. If there are no *parentsymbol* parameters, it is independent.

#DECLARE may be used to create dependent *symbols*. The *parentsymbol* must be a multivalued symbol, whether it is a built-in or user-defined symbol.

The SAVE attribute causes a *symbol's* value(s) to be saved at the end of source generation and restored when the #DECLARE statement is eXEcuted at the beginning of the next source generation session. A *symbol* with the SAVE attribute may only be declared in the #APPLICATION section.

### Example:

```
#APPLICATION('Sample One')
#DECLARE(%UserSymbol),SAVE
                                            #!Value saved after generation
                                             #! and restored for next generation
#DECLARE(%ModuleFile,%Module),UNIQUE,MULTI #!Level-1 dependent symbol
#DECLARE(%ModuleFilePut,%ModuleFile)
                                             #!Level-2 dependent symbol
#DECLARE(%ModuleFileDelete,%ModuleFile)
                                             #!Second Level-2 dependent symbol
#DECLARE(%FileList),MULTI
                                             #!Multivalued symbol
#DECLARE(%FieldListID,%FileList,LONG),UNIQUE
#DECLARE(%FieldList,%FieldListID)
#DECLARE (%FieldListType,%FieldListID)
#DECLARE (%Dest)
                                             #!implicitly STRING
#DECLARE(%Char, STRING)
                                             #!explicitly STRING
#DECLARE (%Idx,LONG)
                                             #!explicitly LONG
#DECLARE (%LnS,LONG)
                                             #!ditto
```

See Also: #FIX ,#FOR ,#ADD ,#DELETE ,#FREE ,EQUATE

### **#DEFAULT (default procedure starting point)**

**#DEFAULT** 

procedure

**#ENDDEFAULT** 

**#DEFAULT** Begins a default procedure declaration section.

procedure Default procedure in .TXA file format.

**#ENDDEFAULT** Terminates the default procedure declaration.

The **#DEFAULT** structure contains a single default *procedure* declaration in .TXA format as generated by the Application Generator's Export function. #DEFAULT may only be placed at the end of a #PROCEDURE section. You may have multiple #DEFAULT structures for a single #PROCEDURE. The enclosed *procedure* section of a .TXA file should contain a procedure of the preceding #PROCEDURE's type. The recommended way to create a #DEFAULT structure is to edit the default procedure in the template registry, and then export the template as text, which creates a .TXA file.

### **Structure Attributes**

### #ORDINAL(number)

#ORDINAL stores a unique ID number for every control populated in the window.

### #ORIG(ControlName)

#ORIG stores the original control name populated by a template. When a control that already exists is populated, or a control is copied in the window or report, the control will be automaticaly renamed, but #ORIG will store the original name.

#### #SEQ(number)

#SEQ is used to link a control to a template. The *number* represents the template instance number.

#### #FIELDS(field1,field2,fieldn)

The #FIELDS attribute stores the fields to be showed in each column on a populated LIST control.

### #LINK(control name)

The #LINK statement, when added to a control will link the control to a specific template family. When the linked control is deleted the window formatter also will delete any matching control containing the #LINK attribute. This is used primarily with prompts and entry controls, or radio buttons, or in some templates like the UpdateButtons where the Insert, Change & Delete buttons are linked to each other.

#### **Example:**

#### #DEFAULT

```
NAME DefaultForm
[COMMON]

DESCRIPTION 'Default record update'

FROM Clarion Form
[PROMPTS]

%WindowOperationMode STRING ('Use WINDOW setting')
```

```
%INISaveWindow LONG (1)
[ADDITION]
NAME Clarion SaveButton
[INSTANCE]
INSTANCE 1
PROCPROP
[PROMPTS]
%InsertAllowed LONG (1)
%InsertMessage @S30 ('Record will be Added')
%ChangeAllowed LONG (1)
%ChangeMessage @S30
                     ('Record will be Changed')
%DeleteAllowed LONG (1)
%DeleteMessage @S30 ('Record will be Deleted')
%MessageHeader LONG (0)
[ADDITION]
NAME Clarion CancelButton
[INSTANCE]
INSTANCE 2
[WINDOW]
FormWindow WINDOW('Update Records...'), AT(18,5,289,159), CENTER, SYSTEM, GRAY, MDI
            BUTTON('OK'), AT(5,140,40,12), USE(?OK), DEFAULT, #ORDINAL(1), #SEQ(1), #ORIG(?OK), #LINK(?OK)
            BUTTON('Cancel'),AT(50,140,40,12),USE(?Cancel),#ORDINAL(2),#SEQ(2),#ORIG(?Cancel)
            {\tt STRING(@S40),AT(95,140,,),USE(ActionMessage),\#ORDINAL(3)}
           END
#ENDDEFAULT
```

### **#DEFINE** (user defined macro)

**#DEFINE (**%macro name)

statements

**#ENDDEFINE** 

**#DEFINE** Defines a user defined macro that can be expanded using #EXPAND.

%macro name A user defined symbol used as the macro's identifier.

Statements A sequence of statements.

**#ENDDEFINE** Terminates the definition of a user defined macro.

**#DEFINE** defines the beginning of a section of code which can be expanded into generated code using the #EXPAND statement. A macro may not be defined with any parameters. #DEFINE must be terminated with #ENDDEFINE. Using #DEFINE and #EXPAND to define and expand macros for commonly used code sections will lead to cleaner template code while hiding unneeded target code from immediate view.

### Example:

#DEFINE (%InRangeCheck)
 IF %ControlUse <= TODAY()
 SELECT(?%ControlUse)
 END
#ENDDEFINE</pre>

See Also: #EXPAND

### **#DELETE** (delete a multi-valued symbol instance)

**#DELETE(** symbol [, position ] )

**#DELETE** Deletes the value from one instance of a multi-valued user-defined

symbol.

symbol A multi-valued user-defined symbol.

position An integer constant or symbol containing the instance number in the

symbol. Instance numbering begins with one (1). If omitted, the default

is the current fixed instance.

The **#DELETE** statement deletes the value from one instance of a multi-valued user-defined symbol. If there are any symbols dependent upon the *symbol*, they are also cleared. If this is the last instance in the *symbol*, the instance is removed. You can get the current instance number to which a symbol is fiXEd by using the **INSTANCE(%symbol)** built-in template procedure.

#### **Example:**

```
#DECLARE(%ProcFilesPrefix),MULTI
                                  #!Declare multi-valued symbol
#ADD(%ProcFilesPrefix,'SAV')
                                   #!Add a value
#ADD(%ProcFilesPrefix,'BAK')
                                  #!Add a value
#ADD(%ProcFilesPrefix,'PRE')
                                  #!Add a value
#ADD(%ProcFilesPrefix,'QUE')
                                  #!Add a value
#!%ProcFilesPrefix contains: SAV, BAK, PRE, QUE
#DELETE(%ProcFilesPrefix,1)
                                  #!Delete first value (SAV)
#!%ProcFilesPrefix contains: BAK, PRE, QUE
#FIX(%ProcFilesPrefix,'PRE') #!Fix to a value
#DELETE(%ProcFilesPrefix)
                                  #!Delete it
#!%ProcFilesPrefix contains: BAK, QUE
```

See Also: #DECLARE,#ADD

# **#DELETEALL** (delete multiple multi-valued symbol instances)

**#DELETEALL(** symbol, expression )

#DELETEALL Deletes the values from specified instances of a multi-valued user-defined

symbol.

symbol A multi-valued user-defined symbol.

expression An expression that defines the instances to delete.

The #DELETEALL statement deletes all values from the symbol that meet the expression.

### **Example:**

```
#DECLARE(%ProcFilesPrefix),MULTI #!Declare multi-valued symbol
#ADD(%ProcFilesPrefix,'SAV') #!Add a value
#ADD(%ProcFilesPrefix,'BAK') #!Add a value
#ADD(%ProcFilesPrefix,'PRE') #!Add a value
#ADD(%ProcFilesPrefix,'BAK') #!Add a value
#ADD(%ProcFilesPrefix,'QUE') #!Add a value
#!%ProcFilesPrefix contains: SAV, BAK, PRE, BAK, QUE
#DELETEALL(%ProcFilesPrefix,'BAK') #!Delete all BAK instances
#!%ProcFilesPrefix now contains: SAV, PRE, QUE
```

See Also: #DECLARE,#ADD

### **#DISPLAY** (display-only prompt)

#DISPLAY([ string])[, AT()][, PROP( name, value )]

**#DISPLAY** Displays a string constant on a properties window.

string A string expression containing the text to display.

AT Specifies the size and position of the *string* display area in the window,

allowing multiple lines of text. This attribute takes the same parameters as the Clarion language AT attribute. If a width and height are specified in the AT

attribute, then the string will span multiple lines.

**PROP** Specifies a property to assign to the prompt text. *Name* designates the

property name equate (Example: PROP:FontColor) and value is the value

assigned to the named property (Example: 0FFFFFH)

The **#DISPLAY** statement displays the *string* on a properties window. If the *string* is omitted, a blank line is displayed. The display updates whenever the value in the *string* changes. #DISPLAY is not valid in a #MODULE section.

#### Example:

```
#DISPLAY() #!Display a blank line
#DISPLAY('Ask programmer to input some') #!Display a string
#DISPLAY(' ABC Version: '&%ABCVersion), AT(10,,170), PROP(PROP:FontColor, OFFFFFH)
#PROMPT(' specific value',@s20),%InputSymbol
```

See Also: #PROMPT, #GROUP, #BOXED, #ENABLE, #BUTTON

### **#EMBED** (define embedded source point)

#EMBED ( identifier [, descriptor ] ) [, symbol ] [, HLP( helpid ) ] [, DATA ] [, HIDE ]

[, WHERE( expression ) ] [, MAP( mapsymbol, description ) ] [, LABEL ] [, NOINDENT ]

[, LEGACY ] [, PREPARE( parameters ) ] [, TREE( displaytext) ]

#EMBED Identifies an explicit position in the Template where the programmer may place

their own source code.

identifier A user-defined template symbol which identifies the embedded source code point

for the Application Generator.

descriptor A string constant containing a description of the embedded source code's

position in the Template. This is the string displayed in the list of available embedded source code windows for a procedure Template (normally omitted if

the HIDE attribute is present).

symbol A multi-valued template symbol or a literal string. You may have multiple symbols

on a single #EMBED statement. This may also have a description to specify the text to display in the embedded source tree appended to it with square brackets

(i.e. %symbol[%description]).

**HLP** Specifies on-line help is available for the #EMBED.

helpid A string constant containing the identifier to access the Help system. This may be

either a Help keyword or "context string."

**DATA** Specifies the embed point is in a data section, so the Text Editor's Window and

Report Formatters can be used.

**HIDE** Specifies the source code point does not appear in the tree of available

embedded source code points. Therefore, the #EMBED is only available for

#CODE, #CONTROL, or #EXTENSION code generation.

**WHERE** Specifies the #EMBED is available only for those instances of the *symbol* where

the expression is true.

expression An expression that specifies the condition.

MAP Maps the description to the symbol for display in the embedded source tree. You

may have as many MAP attributes as there are symbols.

mapsymbol Names which of the #EMBED symbols the MAP references.

description An expression that specifies the text to display in the embedded source tree.

LABEL Specifies the embed point is generated in column one (1) so the Text Editor will

correctly color-code the labels.

### **NOINDENT**

Specifies the code generated into the embed point retains the indention from its source (either generated or entered in by the programmer) source in column 1 is generated into column 1, no matter where the #EMBED is placed.

#### **LEGACY**

Specifies to show the embed only when you press the legacy button on the embed tree. The #EMBED is displayed in the list of available embed points only if there is already code in it. This indicates an embed point which has been superceded and is only present to allow the existing code in it to be moved to a new embed or deleted.

#### **PREPARE**

Executes preparatory code before evaluating the #EMBED symbol s. The  $n_{\rm th}$  parameter to PREPARE is evaluated immediately before the  $n_{\rm th}$  symbol is evaluated.

parameters is a comma-delimited list of expressions or calls to #GROUPs. You may have as many PREPARE parameters as there are symbols on the #EMBED.

#### **TREE**

Specifies what will be added to the embeds dialog tree. This overrides the MAP attribute.

displaytext is a comma-delimited list of strings (constraints or variables) containing tree level text, color, and priority information. Each tree level may be a separate TREE entry or contained in single quotes and separated by a vertical bar (|) character.

### 'Level One|LevelTwo|Level Three'

Following the text to display you may have optional color and priority information contained in curly braces, in the following format:

### 'TextToDisplay{{Color(0FFh),priority(5000)}'

The color information may be either a number or the text for a color EQUATE from the EQUATES.CLW file.

**#EMBED** identifies an explicit position in the Template where the programmer may call a procedure, generate code from a code template, or place their own custom embedded source code within the procedure. The Application Generator prompts the programmer for the procedure to call, or the code template to use, or calls the Text Editor to allow the programmer to write the embedded source code. **#EMBED** is also used as the destination of all the source automatically generated by **#CODE**, **#CONTROL**, and **#EXTENSION** template sections. If no code is written in the embedded source code point by the programmer or any code template, control template, or extension template, no code is generated.

In a #PROCEDURE section, the source code is automatically placed in the exact column position at which #EMBED is located within the Template. If #EMBED is directly placed in the data section of a #PROGRAM, #MODULE, or #PROCEDURE, it must be in column one (1) of the Template file (so the embedded code may contain data labels). If the #EMBED statement has the DATA atribute, the Window and Report Formatters in the Text Editor are available for use. In executable code sections, #EMBED may be placed in column one, but that is not required.

#EMBED is valid in a #GROUP section, however, this should be used with care. Since it is possible for a #GROUP to be recursive (call itself), it is possible to create embedded source code that is repeated within each iteration of the recursive #GROUP's generated code. The source

code is generated in the same relative column position as the code generated from the #GROUP. A #EMBED using the *symbol* attribute is used within a #FOR statement to allow a different piece of embedded source to be inserted for each instance of the *symbol*. It can also be used within #FOR, #LOOP, and/or recursive #GROUPs for the current instance of the symbol (if it has been #FIXed). The MAP attribute allows you to replace a *description* for the *symbol* in the embedded source tree.

```
#PROCEDURE(SampleProc, 'This is a sample procedure'), WINDOW
#EMBED(%DataSection,'Data Section Source Code Window'),DATA #!Source code in column 1
                     !Begin executable code
 #EMBED(%SetupProc,'Code Section Source Code Window 1')
                                                             #!Source code in column 3
 OPEN (Screen)
                     !Open window
 ACCEPT
                     !Event handler
   CASE SELECTED() !Handle field-selection events
   #FOR(%Control)
   OF %Control
     #EMBED(%ScreenFieldSetupEmbed,'Field Selected Embed'),%Control
   #ENDFOR
   END
                    !Handle field-action events
   CASE ACCEPTED()
   #FOR(%Control)
   OF %Control
     #EMBED(%ScreenFieldEditEmbed,'Field Accepted Embed'),%Control
   #ENDFOR
   END
 END
#!Source in col 1
#EMBED(%CustomRoutines,'Code Section Source Code Window 2'), LABEL
```

# **#EMPTYEMBED** (generate empty embed point comments)

**#EMPTYEMBED(** text [, condition ] )

**#EMPTYEMBED** Generates comments into empty embed points.

text A string constant or constant expression containing the text to place in the

empty embed point.

condition An expression that, when true, allows the comments to generate.

The **#EMPTYEMBED** statement specifies that comments generate into all embed points in which the user has not entered code. This will not generate comments for embed points in which the user has entered code or in which the templates have generated code.

The output *condition* is usually the value of a global prompt.

The comment *text* may use the %EmbedID, %EmbedDescription, and %EmbedParameters built-in symbols to identify the embed point:

%EmbedID The current embed point's identifying symbol.

%EmbedDescription The current embed point's description.

%EmbedParameters The current embed point's current instance, as a comma-delimited list.

### Example:

```
#! This example is complete extension template, ready to use
#EXTENSION(EmptyEmbeds,'Empty Embed Comments'),APPLICATION
#PROMPT('Generate Empty EMBED Comments',CHECK),%EmptyEmbeds
#EMPTYEMBED('!Embed: ' & %EmbedDescription & ' ' & %EmbedParameters,%EmptyEmbeds)
```

See Also: #PREEMBED, #POSTEMBED

### **#ENABLE** (enable/disable prompts)

#ENABLE( expression ) [, CLEAR ] [, SECTION ]

prompts

**#ENDENABLE** 

**#ENABLE** Begins a group of *prompts* which may be enabled or disabled based upon

the evaluation of the expression.

*expression* The expression which controls the prompt enable/disable.

**CLEAR** Specifies the *prompts* symbol values are cleared when disabled.

**SECTION** Specifies all AT() attributes for the *prompts* are positioned relative to the

start of the #ENABLE section.

prompts One or more #PROMPT, #BUTTON, #DISPLAY, #ENABLE, and/or

**#VALIDATE** statements.

**#ENDENABLE** Terminates the group of *prompts*.

The **#ENABLE** structure contains *prompts* which may be enabled or disabled based upon the evaluation of the *expression*. If the *expression* is true, the *prompts* are enabled, otherwise they are disabled. The *prompts* appear dimmed when disabled and the programmer may not enter data in them.

#### Example:

```
#PROMPT('Pick One',OPTION),%InputChoice #!Mutually exclusive options
#PROMPT('Choice One',RADIO)
#PROMPT('Choice Two',RADIO)
#ENABLE(%InputChoice = 'Choice Two')
    #PROMPT('Screen Field',CONTROL),%SomeField #!Enabled only for Choice Two
    #VALIDATE(%ScreenFieldType = 'LIST','Must select a list box')
#ENDENABLE
```

See Also: #PROMPT ,#GROUP ,#BOXED ,#BUTTON

# #EQUATE (declare and assign value to a user-defined symbol)

#EQUATE( symbol, value )

**#EQUATE** Declares and assigns a value to a single-valued user-defined symbol.

symbol A single-valued user-defined symbol. This must not have been previously

declared.

value A built-in or user-defined symbol, string constant, or an expression.

The **#EQUATE** statement declares the *symbol* and assigns the *value* to the *symbol*. This is directly equivalent to a #DECLARE statement followed by a #SET to assign it a value.

If the *value* parameter contains an expression, you may perform mathematics during source code generation. The expression may use any of the arithmetic, Boolean, and logical operators documented in the *Language Reference*. If the modulus division operator (%) is used in the expression, it must be followed by at least one blank space (to explicitly differentiate it from the Template symbols). Logical expressions always evaluate to 1 (True) or 0 (False). Clarion language procedure calls (those supported in EVALUATE()) and built-in template procedures are allowed.

#### **Example:**

#EQUATE(%NetworkApp,'Network')
#EQUATE(%MySymbol,%Primary)

See Also: #DECLARE, #SET

### **#ERROR** (display source generation error)

#ERROR( message )

**#ERROR** Displays a source generation error.

message A string constant, user-defined symbol, or expression containing an error

message to display in the Source Generation window.

**#ERROR** displays a *message* in the Source Generation window. This could be information for the user. It may also alert the user that they made some error which will cause the procedure Template to generate invalid source code which could create compiler errors.

When a #ERROR statement is encountered at source code generation time, its message is displayed. The user may choose to abort the compile and link process, or continue on to the compiler.

```
#PROCEDURE(SampleProc,'This is a sample procedure')
#PROMPT('Access Key',KEY),%SampleAccessKey
#IF(%SampleAccessKey = %NULL) #!IF the user did not enter a Key
#SET(%ErrorSymbol,(%Procedure & ' Access Key blank')
#ERROR(%ErrorSymbol)
#ERROR('This error is Fatal -- DO NOT CONTINUE')
#ABORT
#ENDIF
```

## **#EXPAND** (expand a user defined macro)

#EXPAND ( %macro name )

**#EXPAND** Expands a user defined macro.

%macro name A previously declared macro symbol.

**#EXPAND** is used to expand a previously defined macro into the generated source code. Using #DEFINE and #EXPAND to define and expand macros for commonly used code sections will lead to cleaner template code while hiding unneeded target code from immediate view.

### Example:

#EXPAND (%InRangeCheck)

The above template code will cause the following code to be generated:

IF %ControlUse <= TODAY()
 SELECT(?%ControlUse)
END</pre>

See Also: #DEFINE

# **#EXPORT (export symbol to text)**

#EXPORT([symbol])

**#EXPORT** Creates a .TXA or .TXD text file from a *symbol*.

symbol The template symbol to export (%Module, %Procedure, %Dictionary, or

%Program). If omitted, the current application is exported.

**#EXPORT** outputs .TXA or .TXD script text for the *symbol* to the current output file (see #CREATE or #OPEN). This file may then be used for importing to other Clarion applications.

### Example:

#OPEN('MyExp.TXA')
#FOR(%Procedure)
#EXPORT(%Procedure)
#ENDFOR

See Also: #CREATE ,#OPEN ,#IMPORT

### **#EXTENSION** (define an extension template)

```
#EXTENSION( name, description [, target ]) [, HLP( helpid )] [, MULTI ] [, DESCRIPTION( expression )]]

[, SHOW ] [, PRIMARY( message [, flag ] )] [,| APPLICATION( [ child(chain) ] )| ]

| PROCEDURE |

[, REQ( addition [,| BEFORE| ] ) [,| FIRST| ] [, PRIORITY( number )]

| AFTER | | LAST|
```

#EXTENSION Begins an extension template that generates code into embedded source code

points to add some functionality not associated with specific controls.

**HLP** Specifies on-line help is available.

name The label of the extension template. This must be a valid Clarion label.

description A string constant describing the extension template.

target A string constant that specifies the source language the extension template

generates. If omitted, it defaults to Clarion.

MULTI Specifies the #EXTENSION may be used multiple times in a given application

or procedure.

**DESCRIPTION** Specifies the display description of a #EXTENSION that may be used multiple

times in a given application or procedure.

*expression* A string constant or expression that contains the description to display.

**SHOW** Specifies the #EXTENSION prompts are placed on the procedure properties

window.

**PRIMARY** Specifies a primary file for the extension must be placed in the procedure's

Data / Tables Pad.

message A string constant containing a message that appears in the Data / Tables Pad

next to the #EXTENSION's Primary file.

flag Either OPTIONAL (the file is not required), OPTKEY (the key is not required),

or NOKEY (the file is not required to have a key).

**APPLICATION** Tells the Application Generator to make the #EXTENSION available only at the

global level.

child(chain) The name of a #EXTENSION with the PROCEDURE attribute to automatically

populate into every generated procedure when the #EXTENSION with the

APPLICATION attribute is populated.

PROCEDURE Tells the Application Generator to make the #EXTENSION available only at the

local level.

**REQ** Specifies the #EXTENSION requires a previously placed #CODE, #CONTROL,

or #EXTENSION before it may be used.

addition The name of the previously placed #CODE, #CONTROL, or #EXTENSION.

**BEFORE** Legacy attribute, replaced by PRIORITY.

**AFTER** Legacy attribute, replaced by PRIORITY.

**FIRST** Equivalent to PRIORITY(1).

**LAST** Equivalent to PRIORITY(10000).

**PRIORITY** Specifies the order inwhich the #EXTENSION is generated. The lowest value

generates first. If omitted, the PRIORITY is assumed to be 5000.

*number* An integer constant in the range 1 to 10000.

**#EXTENSION** defines the beginning of an extension template containing code to generate into the application or procedure to provide some functionality not directly associated with any control. A #EXTENSION section may contain Template and/or target language code. The #EXTENSION section is terminated by the first occurrence of a Template Code Section (#PROGRAM, #MODULE, #PROCEDURE, #CONTROL, #CODE, #EXTENSION, or #GROUP) statement, or the end of the file. Within a single Template set, separate #EXTENSION sections may not be defined with the same *name*.

#EXTENSION can only generate code into #EMBED embedded source code points using the #AT/#ENDAT structure. A #EXTENSION section may contain #PROMPT statements to prompt for the values needed to generate proper source code. These prompts appear when you edit an Extension from the Extensions button in the environment. It may also contain #EMBED statements which become active only if the #EXTENSION section is used.

#RESTRICT can restrict appearance of the #EXTENSION in the list of available extensions based on an expression or Template language statements.

```
#EXTENSION(Security,'Add password'),PROCEDURE
  #PROMPT('Password File',FILE),%PasswordFile,REQ
  #PROMPT('Password Key', KEY(%PasswordFile)), %PasswordFileKey, REQ
  #PROMPT('Password Field',COMPONENT(%PasswordFileKey)),%PasswordFileKeyField,REQ
  #AT(%DataSectionBeforeWindow)
LocalPswd
           STRING(10)
SecurityWin WINDOW
             ENTRY (@s10), USE (LocalPswd), REQ, PASSWORD
             BUTTON('Cancel'), KEY(EscKey), USE(?CancelPswd)
  #ENDAT
  #AT (%ProcedureSetup)
OPEN (SecurityWin)
ACCEPT
 CASE ACCEPTED()
 OF ?LocalPswd
    %PasswordFileKeyField = LocalPswd
    GET(%PasswordFile,%PasswordFileKey)
    IF NOT ERRORCODE()
     LocalPswd = 'OK'
   END
 BREAK
 OF ?CancelPswd
  CLEAR (LocalPswd)
  BREAK
 END
END
CLOSE (SecurityWin)
IF LocalPswd <> 'OK' THEN RETURN.
  #ENDAT
See Also: #EMBED, #AT
```

# **#FIELD (control prompts)**

#FIELD, WHERE( expression)

prompts

**#ENDFIELD** 

**#FIELD** Begins a control prompts section.

**WHERE** Specifies the #FIELD is used only for those instances where the *expression* 

is true.

*expression* An expression that specifies the condition for use.

prompts Prompt (#PROMPT, #BUTTON, etc.) statements.

**#ENDFIELD** Terminates the section.

The **#FIELD** structure contains *prompts* for controls that are populated onto a window. These *prompts* appear in the Actions... dialog.

The list of field prompts appearing in the Actions... dialog is built in the following manner:

- 1. #CONTROL prompts.
- 2. #PROCEDURE-level #FIELD prompts (also from inserted #GROUPs).
- 3. #PROCEDURE-level #FIELD prompts from active #EXTENSION sections.
- 4. #CONTROL-level #FIELD prompts.
- 5. #CODE-level #FIELD prompts.

The values the user inputs into the #FIELD prompts are used to generate the source to govern the behavior of the control.

### Example:

```
#FIELD, WHERE(%ControlType = 'BUTTON')
    #PROMPT('Enter procedure call',PROCEDURE),%ButtonProc
#ENDFIELD
```

See Also: #PROMPT #VALIDATE #ENABLE #DISPLAY #BUTTON

### **#FIND** ("super-fix" multi-value symbols)

#FIND( symbol, fixsymbol [, limit ] )

**#FIND** FIXes all multi-valued parent symbols to values that point to a single child instance.

symbol A multi-valued symbol.

fixsymbol A symbol or expression containing the value to fix the symbol to.

limit A parent symbol which limits the search scope to the children of the limit symbol.

The **#FIND** statement finds the first instance of the *fixsymbol* contained within the *symbol* then fiXEs it and all the "parent" symbols on which the *symbol* is dependent to the values that "point to" the value of the *fixsymbol* contained in the *symbol*. This is done so that all the symbol dependencies are aligned and you can reference other symbols dependent on "parent" symbols of the *symbol*.

For example, assume %ControlUse contains CUS:Name. The #FIND(%Field,%ControlUse) statement:

- Finds the first instance of %Field that matches the current value in %ControlUse (the first instance of CUS:Name in %Field) in the current procedure.
- FIXes %Field to that value (CUS:Name).
- FIXes %File to the name of the file containing that field (Customer).
- This allows the Template code to reference other the symbols dependent upon %File (like %FilePre to get the file's prefix).

The *fixsymbol* must contain a valid instance of one of the *symbol*'s multiple values. If the *fixsymbol* does not contain a valid instance, the *symbol* is cleared and contains no value when referenced.

### Example:

#FIND (%Field, %ControlUse) #!FIXEs %Field and %File to %ControlUse parents

See Also: #SELECT ,#FIX

## #FIX (fix a multi-value symbol)

#FIX( symbol, fixsymbol)

**#FIX** FIXes a multi-valued symbol to the value of a single instance.

symbol A multi-valued symbol.

fixsymbol A symbol or expression containing the value to fix the symbol to.

The **#FIX** statement fixes the current value of the multi-valued symbol to the value contained in the *fixsymbol*. This is done so that one instance of the symbol may be referenced outside a #FOR loop structure, or so you can reference the symbols dependent upon the multi-valued symbol.

The *fixsymbol* must contain a valid instance of one of the *symbol*'s multiple values. If the *fixsymbol* does not contain a valid instance, the *symbol* is cleared and contains no value when referenced. Unless #ADD has been used to add a new value and fix to that instance, #FIX or #SELECT must be used to set the value in a *symbol* before it contains any value for Template processing outside of a #FOR loop.

#FIX is completely independent of #FOR in that #FOR always loops through every instance of the *symbol*, whether there is a previous #FIX for that *symbol* or not. If there is a previous #FIX statement for that *symbol* before the #FOR loop, that *symbol* reverts to that previous *fixvalue* after the #FOR terminates.

If #FIX is used within a #FOR structure, the scope of the #FIX is limited to within the #FOR in which it is used. It does not change the #FOR symbol's iteration value if both the #FOR and #FIX happen to use the same symbol.

## **Example:**

```
#SET(%OneFile,'HEADER') #! Put values into two User-defined symbols
#SET(%TwoFile,'DETAIL')
#FIX(%File,%OneFile) #! %File refers to 'HEADER'
#FOR(%File) #! %File iteratively refers to all file names
#FIX(%File,%TwoFile) #! %File refers to 'DETAIL'
#ENDFOR #! %File refers to 'HEADER' again
```

See Also: #SELECT,#FIND

**#ENDFOR** 

## **#FOR (generate code multiple times)**

**#FOR(** symbol) [, **WHERE(** expression)] [, **REVERSE**] statements

**#FOR** Loops through all instances of a multi-valued symbol.

symbol A multi-valued symbol.

WHERE Specifies the statements in the #FOR loop are executed only for those

instances of the symbol where the expression is true.

expression An expression that specifies the condition for execution.

**REVERSE** Specifies the #FOR loops through the instances of the *symbol* in reverse

order.

statements Target and/or Template Language statements.

**#ENDFOR** Terminates the #FOR structure.

**#FOR** is a loop structure which generates its *statements* once for each value contained in its *symbol* during source code generation. If there are no values in the *symbol*, no code is generated. #FOR must be terminated by **#ENDFOR**. If there is no #ENDFOR, an error message is issued during Template file pre-processing. A #FOR loop may be nested within another #FOR loop.

The #FOR loop begins with the first instance of the *symbol* (or last, if the **REVERSE** attribute is present) and processes through all instances of the *symbol*--it is not affected by any #FIX statements. If the **WHERE** attribute is present, the #FOR *statements* are executed only for those instances of the *symbol* where the *expression* is true. This creates a conditional #FOR loop.

Since #FOR is a loop structure, the #BREAK and #CYCLE statements may be used to control the loop. #BREAK immediately terminates #FOR loop processing and continues with the statement following the #ENDFOR that terminates the #FOR. #CYCLE immediately returns control to the #FOR statement to continue with the next instance of the *symbol*.

## **Example:**

```
#FOR(%ScreenField),WHERE(%ScreenFieldType = 'LIST')
#INSERT(%ListQueueBuild) #!Generate only for LIST controls
#ENDFOR
```

See Also: #BREAK, #CYCLE

## **#FREE (free a multi-valued symbol)**

#FREE( symbol)

**#FREE** Clears all instances of a multi-valued user-defined symbol.

symbol A multi-valued user-defined symbol.

The **#FREE** statement clears all instances of a multi-valued user-defined symbol. If there are any symbols dependent upon the *symbol*, they are also cleared.

## Example:

```
#DECLARE(%ProcFilesPrefix),MULTI
                                     #!Declare multi-valued symbol
#ADD(%ProcFilesPrefix,'SAV')
                                     #!Add a value
                                     #!Add a value
#ADD(%ProcFilesPrefix,'BAK')
                                     #!Add a value
#ADD(%ProcFilesPrefix,'PRE')
                                     #!Add a value
#ADD(%ProcFilesPrefix,'BAK')
#ADD(%ProcFilesPrefix,'QUE')
                                     #!Add a value
               #!%ProcFilesPrefix contains: SAV, BAK, PRE, BAK, QUE
#DELETEALL(%ProcFilesPrefix,'BAK') #!Delete all BAK instances
               #!%ProcFilesPrefix now contains: SAV, PRE, QUE
#FREE (%ProcFilesPrefix)
                                     #!Free the symbol
               #!%ProcFilesPrefix now contains nothing
```

See Also: #DECLARE ,#ADD ,#CLEAR

## **#GENERATE** (generate source code section)

**#GENERATE(** section )

**#GENERATE** Generates a section of the application.

section One of the following built-in symbols: %Program, %Module, or %Procedure. This symbol

indicates the portion of the application to generate.

The **#GENERATE** statement generates the source code for the specified *section* of the application by executing the Template Language statements contained within that *section*. #GENERATE should only be used within the #APPLICATION or a #UTILITY section of the Template.

When section is:

%Program The #PROGRAM section of the Template is generated.

%Module The appropriate #MODULE section of the Template is generated.

%Procedure The appropriate #PROCEDURE section of the Template for the current value of %Procedure

is generated.

```
#GENERATE (%Program)
                                                #!Generate program header
#FOR(%Module)
                                                #1
  #GENERATE (%Module)
                                                #!Generate module header
  #FOR(%ModuleProcedure)
                                                #!For all procs in module
    #FIX(%Procedure,%ModuleProcedure)
                                                #!Fix current procedure
    #GENERATE (%Procedure)
                                                #!Generate procedure code
  #ENDFOR
                                                #!EndFor all procs in module
#ENDFOR
                                                #!EndFor all modules
```

## **#GLOBALDATA** (default global data declarations)

#### **#GLOBALDATA**

declarations

**#ENDGLOBALDATA** 

**#GLOBALDATA** Begins a default global data declaration section.

declarations Data declarations.

**#ENDGLOBALDATA** Terminates the default global data declarations.

The **#GLOBALDATA** structure contains default data *declarations* global to the program. The *declarations* are then available to the programmer through the *Data* button on the **Global Properties** dialog. #GLOBALDATA may be placed in a #PROGRAM, #PROCEDURE, #CODE, #CONTROL, or #EXTENSION section of the Template. The *declarations* will appear in the global data section of the generated source code.

#### Example:

#### **#GLOBALDATA**

Action BYTE !Disk action variable

TempFile CSTRING(65) !Temporary filename variable

**#ENDGLOBALDATA** 

## **#GROUP** (reusable statement group)

#GROUP( symbol [, [ type ] parameters [= default ] ] ) [, AUTO ] [, PRESERVE ] [, HLP( helpid ) ]

**#GROUP** Begins a section of template code that may be inserted into another portion of

the template.

symbol A user-defined symbol used as the #GROUP's identifier.

type The data type of a passed parameter. LONG, REAL, STRING, or \* (asterisk). An

asterisk (\*) indicates it is a variable-parameter (passed by address), whose value may be changed by the #GROUP. LONG, REAL, and STRING indicates it is a value-parameter (passed by value), whose value is not changed by the #GROUP. If *type* is omitted, the *parameter* is a passed as a STRING.

parameters User-defined symbols by which values passed to the #GROUP are referenced.

You may pass multiple *parameters*, each separated by commas, to a #GROUP. All specified *parameters* must be passed to the #GROUP; they may be omitted

only if a *default* is supplied.

=default The value passed for an omitted parameter.

**AUTO** Opens a new scope for the group. This means that any #DECLARE statements

in the #GROUP would not be available to the #PROCEDURE being generated.

Passing *parameters* to a #GROUP implicitly opens a new scope.

**PRESERVE** Preserves the current fixed instances of all built-in multi-valued symbols when

the #GROUP is called and restores all those instances when the #GROUP code

terminates.

**HLP** Specifies on-line help is available.

helpid A string constant containing the identifier to access the Help system. This may be

either a Help keyword or "context string."

**#GROUP** defines the beginning of a section of code which is generated into the source. A #GROUP section may contain Template and/or target language code. The #GROUP section is terminated by the first occurrence of a Template Code Section (#PROGRAM, #MODULE, #PROCEDURE, #CONTROL, #CODE, #EXTENSION, or #GROUP) statement, or the end of the file. Within a single Template, separate #GROUP sections may not be defined with the same symbol. The parameters passed to a #GROUP fall into two categories: value-parameters and variable-parameters.

**Value-parameters** are declared as user-defined symbols, with an optional *type* and are "passed by value" (a copy of the value is passed) Either symbols or expressions may be passed as value-parameters. When a multi-valued symbol is passed as a value-parameter, only the current instance is passed.

**Variable-parameters** are declared as user-defined symbols with a prepended asterisk (\*) (and no *type*). A variable-parameter is "passed by address" and any change to its value by the #GROUP code changes the value of the passed symbol. Only symbols may be passed to a #GROUP as variable-parameters. When a multi-valued symbol is passed as a variable-parameter, all instances are passed.

The statements contained in the #GROUP section are generated by the #INSERT or #CALL statements. A #GROUP may contain #EMBED statements to define embedded source code points. A #GROUP may contain #PROMPT statements to obtain programmer input.

A #GROUP may act as a function if the #RETURN statement which passes control back from the #GROUP has a parameter. The value is returned to the CALL built-in procedure or directly to the expression in which the #GROUP is called as a function. If the #GROUP is called without the CALL built-in procedure and takes no parameters, open and close parentheses must be appended to the #GROUP symbol. For example, you may either place CALL(%MyGroup) in an expression or just %MyGroup().

#### Example:

```
#GROUP(%GenerateFormulas)
                                    #!A #GROUP without parameters
 #FOR(%Formula)
   #IF(%FormulaComputation)
%Formula = %FormulaComputation
    #ELSE
IF(%FormulaCondition)
 %Formula = %FormulaTrue
ELSE
 %Formula = %FormulaFalse
END
    #ENDIF
  #ENDFOR
#GROUP(%ChangeProperty,%MyField,%Property,%Value) #!A #GROUP that receives parameters
%MyField(%Property) = '%Value' #<!Change the %Property of %MyField
#!A #GROUP that receives a variable-parameter and a value-parameter:
#GROUP(%SomeGroup, * %VarParm, LONG %ValParm)
```

See Also: #INSERT, #RETURN, CALL

# **#HELP** (specify template help file)

#HELP( helpfile )

**#HELP** Specifies the Template's help file.

helpfile A string constant containing the name of the template's help file.

The **#HELP** statement specifies a *helpfile* which is used by this template. Once specified, the *helpfile* is used to access the help topics specified by the help id's in all HLP attributes in the template.

## Example:

#HELP('Template.HLP')

## **#IF (conditionally generate code)**

```
#IF( expression )
statements
[#ELSIF( expression )
statements ]
[#ELSE
statements ]
#ENDIF
```

**#IF** A conditional execution structure.

expression Any Template Language expression which can evaluate to false (blank or zero)

or true (any other value). The expression may contain Template symbols, constant values, and any of the arithmetic, Boolean, and logical operators documented in the *Language Reference*. Procedure calls are allowed. If the modulus division operator (%) is used in the expression, it must be delimited by at least one blank space on each side (to explicitly differentiate it from the

Template symbols).

statements One or more Clarion and/or Template Language statements.

**#ELSIF** Provides an alternate expression to evaluate when preceding #IF and #ELSIF

expressions are false.

#ELSE Provides alternate statements to execute when all preceding #IF and #ELSIF

expressions are false.

**#ENDIF** Terminates the #IF structure.

**#IF** selectively generates a group of *statements* depending on the evaluation of the *expression(s)*. The #IF structure consists of a #IF statement and all statements following it until the structure is terminated by **#ENDIF**. If there is no #ENDIF, an error message is issued during Template file pre-processing. #IF structures may be nested within other #IF structures.

**#ELSIF** and **#ELSE** are logical separators which separate the #IF structure into *statements* groups which are conditionally generated depending upon the evaluation of the *expression(s)*. There may be multiple #ELSIF statements within one #IF structure, but only one #ELSE.

When #IF is encountered during code generation:

- If the *expression* evaluates as true, only the *statements* following #IF are generated, up to the next following #ELSIF, #ELSE, or #ENDIF.
- If the *expression* evaluates as false, #ELSIF (if present) is evaluated in the same manner. If the #ELSIF *expression* is true, only the *statements* following it are generated, up to the following #ELSIF, #ELSE, or #ENDIF.
- If all preceding #IF and #ELSIF conditions evaluate false, only the statements following #ELSE (if present) are generated, up to the following #ENDIF. If there is no #ELSE, no code is generated.

```
#IF(SUB(%ReportControlStatement,1,6)='HEADER')
#SET(%Indentation,%Indentation+1)
#ELSIF(SUB(%ReportControlStatement,1,6)='FOOTER')
#SET(%Indentation,%Indentation+1)
#ELSIF(SUB(%ReportControlStatement,1,6)='DETAIL')
#SET(%Indentation,%Indentation+1)
#ELSIF(SUB(%ReportControlStatement,1,6)='OPTION')
#SET(%Indentation,%Indentation+1)
#ELSIF(SUB(%ReportControlStatement,1,5)='GROUP')
#SET(%Indentation,%Indentation+1)
#ELSIF(SUB(%ReportControlStatement,1,5)='BREAK')
#SET(%Indentation,%Indentation+1)
#ELSIF(SUB(%ReportControlStatement,1,4)='FORM')
#SET(%Indentation,%Indentation+1)
```

# **#IMAGE (display graphic)**

#IMAGE( picture ) [, AT( ) ]

**#IMAGE** Displays a graphic image on a properties window.

picture A string expression containing the name of the image file to

display.

AT Specifies the size and position of the *picture* display area in

the window. This attribute takes the same parameters as the

Clarion language AT attribute.

The **#IMAGE** statement displays the *picture* graphic image on a properties window. The display updates whenever the value in the *picture* changes. #IMAGE is not valid in a #MODULE section.

```
#IMAGE('SomePic.BMP') #!Display a bitmap
```

## **#IMPORT(import from text script)**

#IMPORT( source ) [, | RENAME | ]
| REPLACE|

#IMPORT Creates an .APP for Clarion for Windows from a .TXA script source

file.

source The name of the .TXA script file from which to create the .APP file.

**RENAME** Overrides the **Procedure Name Clash** prompt dialog and renames all

procedures.

**REPLACE** Overrides the **Procedure Name Clash** prompt dialog and replaces all

procedures.

The **#IMPORT** statement adds procedure definitions to a Clarion for Windows .APP file from a .TXA script *source* file. This can be used for importing from other versions of Clarion application development products.

```
#UTILITY(SomeUtility,'Some Utility Template')
#PROMPT('File to import',@s64),%ImportFile
#IMPORT(%ImportFile)
```

## **#INCLUDE** (include a template file)

#INCLUDE( filename )

**#INCLUDE** Adds a template file to the Template file chain.

filename A string constant containing the name of the template file to include.

The **#INCLUDE** statement adds a template file to the Template file chain. The template file containing the #INCLUDE statement continues to be processed after the included file has been processed.

```
#TEMPLATE(Clarion,'Clarion Standard Shipping Templates')
#INCLUDE('Program.TPW') #!Include a template file
#INCLUDE('Window.TPW') #!Include another template file
```

# **#INDENT** (change indentation level)

#INDENT( value )

## {bmc blk2blue.bmp}

**#INDENT** Changes the indentation level of generated code.

value An expression that resolves to a positive or negative integer which specifies

the amount and direction to change the current indentation level.

The **#INDENT** statement changes the indentation level of generated code by the amount and direction specified by the *value* parameter. If the *value* is positive, the indentation level increases (moves right). If the *value* is negative, the indentation level decreases (moves left).

#### Example:

#INDENT(-2) #!Change indent level left 2 spaces

See Also: #INSERT

## **#INSERT (insert code from a #GROUP)**

**#INSERT(** symbol [ ( set ) ] [, parameters ] )[, returnvalue ] [, NOINDENT ]

#INSERT Inserts code from a #GROUP. symbol A symbol that names a #GROUP section. The #TEMPLATE name parameter for the template set to which the #GROUP set belongs. If omitted, the #GROUP must be of the same template set name as the #PROCEDURE in which it is used. parameters The parameters passed to the #GROUP. Each parameter must be separated by a comma. All parameters defined for the #GROUP must be passed; they may not be omitted. returnvalue A symbol to receive the value returned by the #RETURN statement. NOINDENT Specifies the code inserted retains the indention in its #GROUP--any source in column 1 in the #GROUP is generated into column 1, no matter where the #INSERT is placed.

The **#INSERT** statement places, at the exact position the #INSERT is located within the Template code, the code from the #GROUP named by the *symbol*. The *set* parameter specifies the #TEMPLATE that contains the #GROUP. This allows any Template to use #GROUP code from any other registered Template.

The *parameters* passed to the #GROUP fall into two categories: value-parameters and variable-parameters. Value-parameters are declared by the #GROUP as a user-defined symbol, while variable-parameters are declared by the #GROUP as a user-defined symbol with a prepended asterisk (\*). Either a symbol or an expression may be passed as a value-parameter. Only a symbol may be passed as a variable-parameter.

The *returnvalue* symbol receives the value returned by the #GROUP from the #RETURN statement that terminates the #GROUP. If the #GROUP does not contain a #RETURN statement, or that #RETURN does not have a parameter, then the value received is an empty string (").

### **Example:**

```
#INSERT(%SomeGroup) #!Ordinary insert
#INSERT(%GenerateFormulas(Clarion)) #!Insert #GROUP from Clarion Template
#INSERT(%FileRecordFilter, %Secondary) #!Insert #GROUP with passed parameter
#!#GROUP from Clarion Template with two passed parameters:
#INSERT(%FileRecordFilter(Clarion), %Primary, %Secondary)
```

See Also: #GROUP, #CALL, #RETURN

## **#INVOKE** (insert code from a named **#GROUP**)

**#INVOKE(** symbol [, parameters ]) [, returnvalue ] [, **NOINDENT** ]

#INVOKE	Inserts code from a named #GROUP.
symbol	A symbol containing the name of a #GROUP section (including the #TEMPLATE to which it belongs).
parameters	The parameters passed to the #GROUP. Each parameter must be separated by a comma. All parameters defined for the #GROUP must be passed; they may not be omitted.
returnvalue	A symbol to receive the value returned by the #RETURN statement.
NOINDENT	Specifies the code inserted retains the indention in its #GROUPany source in column 1 in the #GROUP is generated into column 1, no matter where the #INSERT is placed.

The **#INVOKE** statement places, at the exact position the #INVOKE is located within the Template code, the code from the #GROUP named in the *symbol*. The *symbol* must contain the name of a #GROUP, including the #TEMPLATE set to which it belongs. The main difference between #INVOKE and #CALL is the *symbol* parameter, which is a variable containing the #GROUP to call in #INVOKE and a constant naming the #GROUP to call in #CALL.

The *parameters* passed to the #GROUP fall into two categories: value-parameters and variable-parameters. Value-parameters are declared by the #GROUP as a user-defined symbol, while variable-parameters are declared by the #GROUP as a user-defined symbol with a prepended asterisk (\*). Either a symbol or an expression may be passed as a value-parameter. Only a symbol may be passed as a variable-parameter.

The *returnvalue* symbol receives the value returned by the #GROUP from the #RETURN statement that terminates the #GROUP. If the #GROUP does not contain a #RETURN statement, or that #RETURN does not have a parameter, then the value received is an empty string (").

#### Example:

```
#SET(%SomeGroup,'%GenerateFormulas(Clarion)') #!Set variable to a #GROUP name
#INVOKE(%SomeGroup)

#SET(%SomeGroup,'%FileRecordFilter(Clarion)') #!Set variable to another #GROUP name
#INVOKE(%SomeGroup,%Secondary) #!Insert #GROUP with passed parameter
#INVOKE(%SomeGroup,%Primary,%Secondary) #!#GROUP with two passed parameters
```

See Also: #GROUP ,#INSERT ,#CALL ,#RETURN

## **#LOCALDATA** (default local data declarations)

#### **#LOCALDATA**

declarations

**#ENDLOCALDATA** 

**#LOCALDATA** Begins a default local data declaration section.

declarations Data declarations.

**#ENDLOCALDATA** Terminates the default local data declarations.

The **#LOCALDATA** structure contains default data *declarations* local to the procedure generated by the #PROCEDURE procedure Template. The *declarations* are then available to the programmer through the *Data* button on the **Procedure Properties** dialog. #LOCALDATA may only be placed in a #PROCEDURE, #CODE, #CONTROL, or #EXTENSION section of the Template. The *declarations* will appear in the generated procedure between the keywords PROCEDURE and CODE.

#### Example:

**#LOCALDATA** 

Action BYTE !Disk action variable

TempFile CTRING(65) !Temporary filename variable

#ENDLOCALDATA

## **#LOOP** (iteratively generate code)

**#LOOP** [, | UNTIL( expression ) | ]

| WHILE( expression ) |

| FOR( counter, start, end ) [, BY( step ) ] |

| TIMES( iterations ) |

statements

#ENDLOOP

**#LOOP** Initiates an iterative statement execution structure.

**UNTIL** Evaluates its expression before each iteration of the #LOOP. If its expression

evaluates to true, the #LOOP control sequence terminates.

expression Any Template language expression which can evaluate to false (blank or zero)

or true (any other value).

**WHILE** Evaluates its *expression* before each iteration of the #LOOP. If its *expression* 

evaluates to false, the #LOOP control sequence terminates.

FOR Initializes its counter to the start value, and increments it by the step value each

time through the loop. When the *counter* is greater than the *end* value, the

#LOOP control sequence terminates.

counter A user-defined symbol used as the loop counter.

start An expression containing the initial value to which to set the loop *counter*.

end An expression containing the ending value of the loop counter.

**BY** Explicitly defines the increment value for the *counter*.

step An expression containing the increment value for the *counter*. If omitted, the

step defaults to one (1).

**TIMES** Loops the number of times specified by the *iterations*.

iterations An expression containing the number of times to loop.

statements One or more target and/or Template Language statements.

**#ENDLOOP** Terminates the #LOOP structure.

A **#LOOP** structure repetitively executes the *statements* within its structure. The #LOOP structure must be terminated by **#ENDLOOP**. If there is no #ENDLOOP, an error message is issued during Template file pre-processing. A #LOOP structure may be nested within another #LOOP structure.

The **#LOOP,UNTIL** or **#LOOP,WHILE** statements create exit conditions for the #LOOP. Their expressions are always evaluated at the top of the #LOOP, before the #LOOP is executed. A #LOOP WHILE structure continuously loops as long as the expression is true. A #LOOP UNTIL structure continuously loops as long as the expression is false. The expression may contain Template symbols, constant values, and any of the arithmetic, Boolean, and logical operators documented in the *Language Reference*. Procedure calls are allowed. If the modulus division operator (%) is used in the expression, it must be followed by at least one blank space (to explicitly differentiate it from the Template symbols).

The **#LOOP,FOR** statement also creates an exit condition for the #LOOP. The #LOOP initializes the *counter* to the *start* value on its first iteration. The #LOOP automatically increments the *counter* by the *step* value on each subsequent iteration, then evaluates the *counter* against the *end* value. When the *counter* is greater than the *end*, the #LOOP control sequence terminates.

#LOOP (without WHILE, UNTIL, or FOR) loops continuously, unless a #BREAK or #RETURN statement is executed. #BREAK terminates the #LOOP and continues execution with the statement following the #LOOP structure. All *statements* within a #LOOP structure are executed unless a #CYCLE statement is executed. #CYCLE immediately gives control back to the top of the #LOOP for the next iteration, without executing any statements following the #CYCLE in the #LOOP.

#### **Example:**

```
#SET(%LoopBreakFlag,'NO')
#LOOP
                                      #!Continuous loop
  #INSERT (%SomeRepeatedCodeGroup)
  #IF(%LoopBreakFlag = 'YES')
                                      #!Check break condition
    #BREAK
  #ENDIF
#ENDLOOP
#SET(%LoopBreakFlag,'NO')
#LOOP,UNTIL(%LoopBreakFlag = 'YES')
                                      #!Loop until condition is true
  #INSERT (%SomeRepeatedCodeGroup)
#ENDLOOP
#SET(%LoopBreakFlag,'NO')
#LOOP,WHILE(%LoopBreakFlag = 'NO')
                                      #!Loop while condition is true
  #INSERT(%SomeRepeatedCodeGroup)
#ENDLOOP
```

See Also: #BREAK ,#CYCLE

## **#MESSAGE** (display source generation message)

#MESSAGE( message, line )

**#MESSAGE** Displays a source generation message.

message A string constant, or a user-defined symbol, containing a message to

display in the Source Generation dialog.

line An integer constant or symbol containing the line number on which to

display the message. If out of the range 1 through 3, the message is

displayed in the title bar as the window caption.

**#MESSAGE** displays a *message* in the Source Generation message dialog. The first #MESSAGE statement displays the message window. Subsequent #MESSAGE statements modify the display text.

```
#MESSAGE('Generating ' & %Application,0) #!Display Title bar text
#MESSAGE('Generating ' & %Procedure,2) #!Display Progress message on line 2
```

## **#MODULE** (module area)

#MODULE( name, description [, target, extension ] ) [, HLP( helpid ) ] [, EXTERNAL ]

**#MODULE** Begins the module section.

name The name of the Module which identifies it for the Template Registry and

Template Language statements. This must be a valid Clarion label.

description A string constant describing the #MODULE section for the Template Registry and

Application Generator.

target A string constant that specifies the source language the Template generates.

The word "EXTERNAL" is convention adopted to indicate an external source or

object module. If omitted, it defaults to Clarion.

extension A string constant that specifies the source code file extension for the target. If

omitted, it defaults to .CLW.

**HLP** Specifies on-line help is available.

helpid A string constant containing the identifier to access the Help system. This may be

either a Help keyword or "context string."

**EXTERNAL** Specifies no source generates into the module.

The **#MODULE** statement defines the beginning of the section of the template which puts data into each generated source module's data area. The #MODULE Section is terminated by the next Template Code Section (#PROGRAM, #MODULE, #PROCEDURE, #CONTROL, #CODE, #EXTENSION, or #GROUP) statement encountered, or the end of the file. A Template set may contain multiple #MODULE statements.

Code generated by a #MODULE section is (usually) placed at the beginning of a source code file generated by the Application Generator.

#BUTTON, #PROMPT, and #DISPLAY statements are not valid within a #MODULE section.

```
#MODULE(ExternalOBJ,'External .OBJ module','EXTERNAL','.OBJ'),EXTERNAL
#MODULE(ExternalLIB,'External .LIB module','EXTERNAL','.LIB'),EXTERNAL
#MODULE(GENERATED,'Clarion MEMBER module')

MEMBER('%Program')

!MEMBER statement is required
%ModuleData

#!Data declarations local to the Module
```

## **#OPEN** (open source file)

**#OPEN(** file ) [, READ ]

**#OPEN** Opens a disk file to receive generated source code.

file A string constant, template symbol, or expression containing a

DOS file specification. This may be a fully qualified DOS

pathname.

**READ** Opens the file as read-only. The file cannot be already open for

output.

The **#OPEN** statement opens a disk file to receive the source code generated by **#GENERATE**. If the *file* does not exist, it is created. If the *file* already exists, it is opened in "append source" mode. If the *file* is already open, a source generation error is produced. The *file* is automatically selected as the active source output destination.

If the READ attribute is present, the file is opened in read-only mode so the #READ statement can read it as an ASCII text file. Only one file can be open for input at one time.

#### Example

```
#SET(%ProgramFile,(%Application & '.$$$'))
                                                  #!Temp program filename
#OPEN(%ProgramFile)
                                                  #!Open existing program file
#GENERATE (%Program)
                                                  #!Generate main program header
#CLOSE(%ProgramFile)
                                                  #!Close output file
#OPEN(%ProgramFile),READ
                                                  #!Open it in read-only mode
#DECLARE (%ASCIIFileRecord)
#LOOP
 #READ (%ASCIIFileRecord)
 #! Parse the line and do something with it
 #IF(%ASCIIFileRecord = %EOF)
 #BREAK
 #ENDIF
#ENDLOOP
#CLOSE(%ProgramFile),READ
```

See Also: #READ ,#CLOSE

# **#PDEFINE** (add **#pragma** to project

**#PDEFINE (** symbol, value )

**#PDEFINE** Adds a #pragma statement to the project system.

symbol A symbol that contains a pragma identifier.

value The value that is associated with the symbol to determine whether to omit or

compile code that is enclosed using the OMIT or COMPILE directives.

The **#PDEFINE** statement adds a #pragma (compiler option) statement to the project system. A pragma is added to the project file in the form of *symbol* => *value*.

```
#IF (%DemoVersion)
    #PDEFINE('_DEMO_',1)
#ELSE
    #PDEFINE('_DEMO_',0)
#ENDIF
```

# **#POP** (delete and re-fix a multi-value symbol)

#POP( symbol)

**#POP** Deletes the last instance of a multi-valued symbol and re-fiXEs to the new last instance.

symbol A multi-valued user-defined symbol.

The **#POP** statement deletes the last instance of a multi-valued symbol and re-fiXEs to the new last instance. This is directly equivalent to issuing a #DELETE(%MultiSymbol,ITEMS(%MultiSymbol)) statement followed by #SELECT(%MultiSymbol,ITEMS(%MultiSymbol)) statement.

## Example:

#POP(%MultiSymbol) #!Delete last instance and fix to new last instance

# **#POSTEMBED** (generate ending embed point comments)

**#POSTEMBED(** text [, condition])

**#POSTEMBED** Generates comments at the end of embed point code.

text A string constant or constant expression containing the text to place in the

embed point.

condition An expression that, when true, allows the comments to generate.

The **#POSTEMBED** statement specifies that comments generate at the end of embed points that contain code. The output *condition* is usually the value of a global prompt.

The comment *text* may use the %EmbedID, %EmbedDescription, and %EmbedParameters built-in symbols to identify the embed point:

%EmbedID The current embed point's identifying symbol.

%EmbedDescription The current embed point's description.

%EmbedParameters The current embed point's current instance, as a comma-delimited

list.

## **Example:**

See Also: #PREEMBED, #EMPTYEMBED

# **#PREEMBED** (generate beginning embed point comments)

**#PREEMBED(** text [, condition])

**#PREEMBED** Generates comments at the beginning of embed point code.

text A string constant or constant expression containing the text to place in the

embed point.

condition An expression that, when true, allows the comments to generate.

The **#PREEMBED** statement specifies that comments generate at the beginning of embed points that contain code. The output *condition* is usually the value of a global prompt.

The comment *text* may use the %EmbedID, %EmbedDescription, and %EmbedParameters built-in symbols to identify the embed point:

%EmbedID The current embed point's identifying symbol.

%EmbedDescription The current embed point's description.

%EmbedParameters The current embed point's current instance, as a comma-

delimited list.

## Example:

See Also: #POSTEMBED, #EMPTYEMBED

## **#PREPARE (setup prompt symbols)**

#### **#PREPARE**

statements

**#ENDPREPARE** 

**#PREPARE** Begins a prompts symbol setup section.

statements Template language statements to fix multi-valued symbols to the values

needed to process the #PROMPT or #BUTTON statement preceding the

#PREPARE.

**#ENDPREPARE** Terminates the section.

The **#PREPARE** structure contains Template language statements to fix multi-valued symbols to the values needed to process the **#PROMPT** or **#BUTTON** statements preceding the **#PREPARE**.

A #PREPARE section that precedes all the prompts is executed once, before the prompts are added to a window. In particular, if the prompts are displayed on the procedure properties screen, editing the window definition and returning does not execute the prepare code.

```
#CODE (SetProperty, 'Set a property on a control')
  #DECLARE (%Choices), MULTI
  #DECLARE (%NextLine)
  #FREE (%Choices)
  #OPEN('property.clw'), READ
  #READ (%NextLine)
  #LOOP WHILE (%NextLine <> %Eof)
    #! Exclude PROPLIST: properties
    #IF (SUB(%NextLine, 1, 5) = 'PROP:')
      #ADD(%Choices, SUB(%NextLine, 1, INSTRING(' ',%NextLine)-1))
    #END
    #READ (%NextLine)
  #END
  #CLOSE, READ
#ENDPREPARE
#PROMPT('Control:', FROM(%Control)),%Target
#PROMPT('Property:', FROM(%Choices)),%Selection
#PROMPT('Value:', @s255),%TargetValue
%target{%Selection} = %TargetValue
```

## **#PRINT** (print a source file)

**#PRINT(** file, title )

**#PRINT** Prints a *file* to the current Windows printer.

file A string constant, template symbol, or expression containing

a DOS file specification. This may be a fully qualified DOS

pathname.

title A string constant, template symbol, or expression containing

the title to generate for the file.

The **#PRINT** statement prints the contents of the *file* to the Windows default printer.

## **#PRIORITY** (set new embed priority level)

**#PRIORITY(** number) [,**DESCRIPTION**(treedesc)]

**#PRIORITY** Specifies a new priority level for the code following the #PRIORITY statement.

*number* An integer constant in the range 1 to 10000.

**DESCRIPTION** An optional description of the priority point.

treedesc is a string constant or expression that will appear in the embed tree for

this priority point.

The **#PRIORITY** statement specifies a new priority *number* for the code statements following the #PRIORITY.

#PRIORITY is only valid when used in the #AT/#ENDAT structure. It cannot exist within other nested structures contained within the #AT/#ENDAT structure (e.g., #PRIORITY cannot be placed inside of a #CASE/\*#ENDCASE which is nested within a #AT/#ENDAT).

#### **Example:**

```
#CONTROL(BrowseList,'Add Browse List controls')
  #AT(%ControlEvent,'?Insert','Accepted'),PRIORITY(5000) #!Start at priority 5000
GlobalRequest = InsertRecord #!Goes into priority 5000
  #PRIORITY(8500),DESCRIPTION('Before calling update procedure')
%UpdateProc #!Goes into priority 8500
  #ENDAT
#!
```

**See Also:** #AT (insert code in an embed point) , #EMBED , #CODE , #CONTROL #EXTENSION

## **#PROCEDURE** (begin a procedure template)

#PROCEDURE( name, description [, target ])[, REPORT ] [, WINDOW ] [, HLP( helpid ) ]
[, PRIMARY( message [, flag ]) ] [, QUICK( wizard ) ] [, PARENT( name(family) ) ]

**#PROCEDURE** Begins a procedure template.

name The label of the procedure template. This must be a valid Clarion label.

description A string constant describing the procedure Template.

target A string constant that specifies the source language the template generates. If

omitted, it defaults to Clarion.

**REPORT** Tells the Application Generator to make the Report Formatter available.

**WINDOW** Tells the Application Generator to make the Window Formatter available.

**HLP** Specifies on-line help is available.

helpid A string constant containing the help identifier. This may be either a Help

keyword or "context string."

**PRIMARY** Specifies at least one file must be placed in the procedure's Data / Tables Pad.

message A string constant containing a message that appears in the Data / Tables Pad

next to the procedure's Primary file.

flag If present, contains OPTIONAL (the file is not required), OPTKEY (the key is

not required), or NOKEY (the file is not required to have a key).

QUICK Specifies the procedure has a wizard #UTILITY that runs when the Use

Procedure Wizard box is checked.

wizard The identifier (including template class, if necessary) of the wizard #UTILITY

template.

**PARENT** Specifies that the procedure has a parent procedure, and inherits all of the

prompts and interfaces of that parent procedure.

name A string constant naming the parent procedure – Example: window

family The name of the template class where the parent procedure name is defined.

Example: ABC

The **#PROCEDURE** statement begins a Procedure template. A Procedure template contains the Template and *target* language statements used to generate the source code for a procedure within your application. A **#PROCEDURE** section is terminated by the first occurrence of a Template Code Section (**#PROGRAM**, **#MODULE**, **#PROCEDURE**, **#CONTROL**, **#CODE**,

#EXTENSION, or #GROUP) statement, or the end of the file. Within a Template set you may have multiple #PROCEDURE sections, but they must all have unique *name* parameters.

```
#PROCEDURE(ProcName1,'This is a sample window procedure'),WINDOW
#PROCEDURE(ProcName2,'This is a sample report procedure'),REPORT
#PROCEDURE(ProcName3,'This is a sample anything procedure'),WINDOW,REPORT
#PROCEDURE(Browse,'List with Wizard'),WINDOW,QUICK(BrowseWizard(Wizards))
#PROCEDURE(Splash,'Splash Window'),WINDOW,REPORT,PARENT(Window(ABC))
```

## **#PROGRAM (global area)**

**#PROGRAM(** name, description [, target, extension ] ) [, **HLP(** helpid ) ]

**#PROGRAM** Defines the beginning of the main program module. The name of the #PROGRAM which identifies it for the Template Registry and name Template Language statements. This must be a valid Clarion label. description A string constant describing the #PROGRAM section for the Template Registry and Application Generator. target A string constant that specifies the source language the Template generates. If omitted, it defaults to Clarion. A string constant that specifies the source code file extension for the target. If extension omitted, it defaults to .CLW. HLP Specifies on-line help is available. helpid A string constant containing the identifier to access the Help system. This may be either a Help keyword or "context string."

The **#PROGRAM** statement defines the beginning of the main program module of the Template. The **#PROGRAM** section is terminated by the next Template Code Section (**#MODULE**, **#PROCEDURE**, **#CONTROL**, **#CODE**, **#EXTENSION**, or **#GROUP**) statement encountered, or the end of the file. Only one **#PROGRAM** section is allowed in a Template set.

#BUTTON, #PROMPT, and #DISPLAY statements are not valid within a #PROGRAM section. Global prompts go in the #APPLICATION section.

```
#PROGRAM(CLARION,'Standard Clarion Shipping Template')
PROGRAM !PROGRAM statement required
INCLUDE('Keycodes.clw')
INCLUDE('Errors.clw')
INCLUDE('Equates.clw')
```

## **#PROJECT (add file to project)**

**#PROJECT(** module )

**#PROJECT** Includes a source or object code library, or Project file, in the

application's Project file.

module A string constant which names a source (.CLW if Clarion is the target

language), object (.OBJ), library (.LIB) file containing procedures required by the procedure Template. This may also name a Project (.PRJ) file to be called by the application's Project. The type of file being imported is determined by the file extension. You can also use

this to add any valid project resource (icons, images, etc.)

The **#PROJECT** statement specifies a source or object code library, or Project file, which is required to be in the application for the correct functioning of procedures created by the procedure Template.

#PROJECT provides a direct method of communicating *module* information to the Application Generator and Project system. It alerts the Application Generator to the required presence of the *module* for compiling and/or linking the application. Therefore, the application's Project file (generated by the Application Generator) automatically includes the *module* for making, compiling, and/or linking.

If multiple instances of the same #PROJECT statement are referenced by procedures created in the application, only the first is used. This would occur when multiple procedure Templates require the same *module*, or multiple application procedures are created from the same procedure Template.

#PROJECT allows a developer to automate the installation of third-party libraries and Templates to other developer's computers. This ensures that the application's Project is generated correctly.

#PROJECT for a Project (.PRJ) file provides the ability to create a hierarchy of Projects on large development projects. Where multiple libraries are being linked into a package, this allows you to ensure "make dependencies" are met for all libraries referenced in a particular project.

## Extended library support for #PROJECT

Extended library support for the Clarion Win32/Clarion.NET project system is also available using the following format:

#PROJECT('BuildAction(FileName), CopyToOutputDirectory=CopyAction')

where:

BuildAction Can be one of the following: projectreference, reference, include,

compile, none, library or filedriver

FileName Any file accessible via the redirection system

CopyAction Can be one of these values; Never, Always, PreserveNewest.

Only applicable when BuildAction is set to library or None.

Based on the combination of settings above, you can now specify if a library needs to be rebuilt, and if and how the library gets copied to the designated Output Path set by the target project.

```
#AT(%CustomGlobalDeclarations)
    #PROJECT('Party3.LIB')
#ENDAT

#AT(%CustomGlobalDeclarations)
    #PROJECT('Compile(mylocalLib.LIB), CopyToOutputDirectory=Always')
#ENDAT
```

# **#PROMPT (prompt for programmer input)**

```
#PROMPT (string, type) [, symbol] [, REQ] [, DEFAULT( default)] [, ICON( file )] [, AT()]
[, PROMPTAT()] [, MULTI( description )] [, UNIQUE] [, INLINE] [, VALUE( value )]
[, SELECTION( description )] [, CHOICE] [, WHENACCEPTED( expression )]
[, HSCROLL] [, PROP( name, value )]
```

**#PROMPT** Asks the programmer for input.

string A string constant containing the text to display as the input prompt. This may

contain an ampersand (&) denoting a "hot" key used in conjunction with the ALT

key to get to this field on the properties screen.

type A picture token or prompt keyword.

symbol A User-defined symbol to receive the input. A #PROMPT with a RADIO or

EMBED type cannot have a symbol, all other types must have a symbol.

**REQ** Specifies the prompt cannot be left blank or zero.

**DEFAULT** Specifies an initial value (which may be overridden).

default A string constant containing the initial value.

**ICON** Specifies an icon for the button face of a #PROMPT with the MULTI attribute.

file A string constant containing the name of the .ICO file to display on the button

face.

AT Specifies the position of the prompt entry area in the window, relative to the first

prompt placed on the window from the Template (excluding the standard prompts on every procedure properties window). This attribute takes the same

parameters as the Clarion language AT attribute.

**PROMPTAT** Specifies the position of the prompt *string* in the window, relative to the first

prompt placed on the window from the Template (excluding the standard prompts on every procedure properties window). This attribute takes the same

parameters as the Clarion language AT attribute.

**MULTI** Specifies the programmer may enter multiple values for the #PROMPT. The

prompt appears as a button which pops up a list box allowing the programmer to

enter multiple values, unless the INLINE attribute is also present.

description A string constant containing the name to display on the button face and at the

top of the list of prompt values.

**UNIQUE** The multiple values the programmer enters for the #PROMPT are unique values

and are sorted in ascending order. The MULTI attribute must also be present.

**INLINE**The multiple values the programmer enters for the #PROMPT appears as a list

box with update buttons which allow the programmer to enter multiple values.

The MULTI attribute must also be present.

**VALUE** Specifies the value assigned to the *symbol* when the #PROMPT is selected.

Valid only when the #PROMPT type is RADIO.

value A string constant containing the value to assign to the symbol.

**SELECTION** Specifies the programmer may select multiple values for the #PROMPT from the

list of choices presented by the FROM *type*. The prompt appears as a button which pops up a list box allowing the programmer to choose multiple values,

unless the INLINE attribute is also present.

**CHOICE** Specifies the *symbol* receives the ordinal position number of the selection

instead of the string text from a DROP or OPTION/RADIO #PROMPT set.

WHENACCEPTED Specifies an expression to execute when the #PROMPT posts an Accepted

event (the programmer has entered or chosen data).

group The name of the #GROUP to execute.

**HSCROLL** Specifies horizontal scroll bars in the DROP list. Valid only when the #PROMPT

type is DROP.

**PROP** Specifies a property to assign to the prompt text. *Name* designates the property

name equate (Example: PROP:FontColor) and *value* is the value assigned to

the named property (Example: 0FFFFFH)

The **#PROMPT** statement asks the programmer for input. A **#PROMPT** statement may be placed in **#APPLICATION**, **#PROCEDURE**, **#CODE**, **#CONTROL**, **#EXTENSION**, **#UTILITY**, or **#FIELD** sections. It may not be placed in a **#PROGRAM**, **#MODULE**, **#TEMPLATE**, or **#GROUP** section.

When the #PROMPT is placed in a template section, the prompt *string* and its associated entry field are placed as follows:

Section Name	Window Name
#APPLICATION	Global Settings
#PROCEDURE	Procedure Properties
#CODE	Embeds Dialog
#CONTROL	Control Properties Actions Tab
#EXTENSION	Extensions Dialog
#FIELD	Control Properties Actions Tab

## **#PROMPT Entry Types**

The *type* parameter may either contain a picture token to format the programmer's input, or one of the following keywords:

CHECK Creates a check box

COLOR Calls a standard Windows Color dialog

COMPONENT The label of a key component field (can be limited to one key)

CONTROL A window control

DROP Creates a drop list of items specified in its parameter

EDIT Creates a TEXT control with optional size parameter

EMBED Allows the user to edit a specified embedded source code point

EXPR A multi-field selection box that builds an expression

FIELD The label of a file field (can be limited to one file)

FILE The label of a data file

FONTDIALOG Calls a standard Windows Font dialog

FORMAT Calls the List Box Formatter.

FROM Creates a drop list of items contained in its symbol parameter

ICON Calls a standard Windows Open File dialog, filtered for ICON file

selection

KEY The label of a key (can be limited to one file)

KEYCODE A keycode or keycode EQUATE

OPENDIALOG Calls a standard Windows Open File dialog

OPTFIELD Constant text or the label of a file field

OPTION Creates a radio button structure

PICTURE Calls the picture token formatter.

PROCEDURE The label of a procedure

RADIO Creates a radio button

SAVEDIALOG Calls a standard Windows Save File dialog

SPIN Creates a spin control

TEXT Creates a text entry control

For all *types* except RADIO and CHECK (and MULTI attribute prompts), the #PROMPT *string* is displayed on the screen immediately to the left of its data input area. A #PROMPT with the REQ attribute cannot be left blank or zero; it is a required input field. The DEFAULT attribute may be used to provide the programmer with an initial *value* in the #PROMPT, which may be overridden at design time.

A #PROMPT with a RADIO *type* creates one Radio button for the immediately preceding #PROMPT with an OPTION *type*. There may be multiple RADIOs for one OPTION. Each RADIO's *string*, when selected, is placed in the closest preceding OPTION's *symbol*. The OPTION structure is terminated by the first #PROMPT following it that is not a RADIO.

The MULTI attribute specifies the programmer may enter multiple values for the #PROMPT. A button appears on the Properties window with the *description* on its face. Alternatively, this can have an ICON attribute to name an .ICO file to display on the button face. This button calls a window containing a list box to display all the multiple values entered for the #PROMPT, along with Insert, Change, and Delete buttons. These three buttons call another window containing the #PROMPT *string* and its data entry field to allow the programmer to update the entries in the list.

The EDIT attribute creates 3 controls on the dialog window; a prompt with text of the #PROMPT *string*, a single line TEXT control, and a button on the right of the TEXT control.

When the programmer has entered a value for the #PROMPT, the input value is assigned to the *symbol*. The value entered by the programmer may be checked for validity by one or more #VALIDATE statements immediately following the #PROMPT statement.

The value(s) placed in the *symbol* may be used or evaluated elsewhere within the Template. A *symbol* defined by a #PROMPT in the #APPLICATION section of the Template is Global, it can be used or evaluated anywhere in the Template. A *symbol* defined by #PROMPT in a #PROCEDURE section is Local, and is a dependent symbol to %Procedure; it can be used or evaluated only within that #PROCEDURE section. A *symbol* defined by #PROMPT in a #CODE, #CONTROL, or #EXTENSION section of the Template can be used or evaluated only within that section.

#### Example:

See Also: #DISPLAY ,#VALIDATE ,#GROUP ,#BOXED ,#ENABLE ,#BUTTON ,#DECLARE ,#EQUATE

# **#PROMPT Entry Types Alpha Listing CHECK (check box)**

**CHECK** 

The **CHECK** *type* in a #PROMPT statement indicates the prompt's *symbol* is a toggle switch which is used only for on/off, yes/no, or true/false evaluation. CHECK puts a check box on screen in the entry area for the #PROMPT. When the Check box is toggled on, the prompt's *symbol* equals %True. When the Check box is toggled off, the prompt's *symbol* equals %False.

#### Example:

#PROMPT('Network Application',CHECK),%NetworkApp

# **COLOR** (call Color dialog)

### **COLOR**

The **COLOR** *type* in a #PROMPT statement indicates the prompt's *symbol* must contain the name of the color selected by the programmer from the Windows standard Color dialog.

### Example:

#PROMPT('Ask for Color', COLOR), %ColorSymbol

# **COMPONENT (list of KEY fields)**

**COMPONENT** [ ( scope ) ]

**COMPONENT** Displays a list of KEY component fields.

scope A symbol containing a KEY. If omitted, the list displays all KEY components

for all KEYs in all FILEs.

The **COMPONENT** *type* in a #PROMPT statement indicates the prompt's *symbol* must contain the label of one of the component fields of a KEY. A list of available KEY fields pops up when the #PROMPT is encountered on the Properties screen.

The COMPONENT may have a *scope* parameter that limits the KEY components available in the list. If *scope* is the label of a KEY, the list displays all KEY components for that KEY.

#### **Example:**

#PROMPT('Record Selector', COMPONENT(%Primary)), %RecordSelector

# **CONTROL** (list of window fields)

### **CONTROL**

The **CONTROL** *type* in a #PROMPT statement indicates the prompt's *symbol* must contain the field equate label of a window control. A list of available controls pops up when the #PROMPT is encountered on the Properties screen.

### Example:

#PROMPT('Locator Field', CONTROL), %Locator

### **DROP** (droplist of items)

DROP [ (scope)]

**DROP** Creates a droplist of items.

Scope A string constant or expression containing the items for the

list. Each item must be delimited by the vertical bar (|)

character.

The **DROP** *type* in a #PROMPT statement indicates the prompt's *symbol* must contain one item from the list specified in the *scope* parameter.

The *scope* parameter must contain all the items for the list. The *scope* may optionally contain text in square brackets following each choice that specifies the value to assign to the #PROMPT's *symbol*. This is useful for internationalization.

The list of items drops down just like a Clarion language LIST control with the DROP attribute. If no default value is specified, the prompt's symbol defaults to the first value in the *scope* list.

```
#PROMPT('If file not found', DROP('Create the file|Halt Program')),%FileNotFound
#PROMPT('Que es esto?', DROP('Nombre[Name]|Numero[Number]')),%WhatIsThis
#!"Name" is the value put in %WhatIsThis when the user chooses "Nombre"
```

## **DROP** (droplist of items)

DROP [ (scope)]

**DROP** Creates a droplist of items.

Scope A string constant or expression containing the items for the

list. Each item must be delimited by the vertical bar (|)

character.

The **DROP** *type* in a #PROMPT statement indicates the prompt's *symbol* must contain one item from the list specified in the *scope* parameter.

The *scope* parameter must contain all the items for the list. The *scope* may optionally contain text in square brackets following each choice that specifies the value to assign to the #PROMPT's *symbol*. This is useful for internationalization.

The list of items drops down just like a Clarion language LIST control with the DROP attribute. If no default value is specified, the prompt's symbol defaults to the first value in the *scope* list.

#### Example:

```
#PROMPT('If file not found', DROP('Create the file|Halt Program')),%FileNotFound
#PROMPT('Que es esto?', DROP('Nombre[Name]|Numero[Number]')),%WhatIsThis
#!"Name" is the value put in %WhatIsThis when the user chooses "Nombre"
```

#!"Number" is the value put in %WhatIsThis when the user chooses "Numero"

## **EMBED** (enter embedded source)

EMBED( identifier [, instance ] )

**EMBED** Specifies the prompt directly edits an embedded source code point.

Identifier The user-defined template symbol which identifies the #EMBED embedded

source code point to edit.

Instance A string constant or expression containing one of the values in the multi-

valued symbol used by the #EMBED. You must have as many *instances* as are necessary to explicitly identify the single #EMBED point instance to edit.

The **EMBED** *type* in a #PROMPT statement indicates the prompt is used to directly edit an embedded source code point. This places an an entry area with an ellipsis (...) button next to the prompt to allow the user access to the embedded source code point. The programmer may enter a procedure call in the entry area, or press the ellipsis (...) button to go into the normal source dialog.

If the #EMBED is associated with a multi-valued symbol, you must identify the specific *instance* of the #EMBED. If you use a multi-valued symbol as an *instance* expression, it must be fixed to a single value. Most commonly, this would be used in a #FIELD structure.

```
#PROMPT('Embedded Data Declarations',EMBED(%DataSection))
#FIELD, WHERE(%ControlType = 'BUTTON')
    #PROMPT('Action when button is pressed',EMBED(%ControlEvent,%Control,'Accepted'))
#ENDFIELD
```

### **EMBED** (enter embedded source)

EMBED( identifier [, instance ] )

**EMBED** Specifies the prompt directly edits an embedded source code point.

Identifier The user-defined template symbol which identifies the #EMBED embedded

source code point to edit.

Instance A string constant or expression containing one of the values in the multi-

valued symbol used by the #EMBED. You must have as many *instances* as are necessary to explicitly identify the single #EMBED point instance to edit.

The **EMBED** *type* in a #PROMPT statement indicates the prompt is used to directly edit an embedded source code point. This places an an entry area with an ellipsis (...) button next to the prompt to allow the user access to the embedded source code point. The programmer may enter a procedure call in the entry area, or press the ellipsis (...) button to go into the normal source dialog.

If the #EMBED is associated with a multi-valued symbol, you must identify the specific *instance* of the #EMBED. If you use a multi-valued symbol as an *instance* expression, it must be fixed to a single value. Most commonly, this would be used in a #FIELD structure.

```
#PROMPT('Embedded Data Declarations',EMBED(%DataSection))
#FIELD, WHERE(%ControlType = 'BUTTON')
    #PROMPT('Action when button is pressed',EMBED(%ControlEvent,%Control,'Accepted'))
#ENDFIELD
```

### **EMBEDBUTTON** (call Embeds dialog)

**EMBEDBUTTON(** identifier [,instance1,...instanceN] )

identifier The user-defined template symbol which identifies the embedded source code

point to edit.

instance A string constant or expression containing one of the values in the multi-valued

symbol used by the embedded dialog opened by . You must have as many instances as are necessary to explicitly identify the single #EMBED point

instance to edit.

The **EMBEDBUTTON** *type* in a #PROMPT statement indicates the prompt's *symbol* will used to produce text on a button that opens the embedded source dialog. The embed points displayed are determined by the identifier's template symbol and optional instances used to distinguish different embed areas. Essentially, this prompt allows the EMBED functionality to be called from a secondary window, eliminating screen clutter.

#### Example:

#PROMPT('Advanced...', EMBEDBUTTON(%ControlPostEventHandling,%Control,'Selected'))

### **EMBEDBUTTON** (call Embeds dialog)

**EMBEDBUTTON(** identifier [,instance1,...instanceN] )

identifier The user-defined template symbol which identifies the embedded source code

point to edit.

instance A string constant or expression containing one of the values in the multi-valued

symbol used by the embedded dialog opened by . You must have as many instances as are necessary to explicitly identify the single #EMBED point

instance to edit.

The **EMBEDBUTTON** *type* in a #PROMPT statement indicates the prompt's *symbol* will used to produce text on a button that opens the embedded source dialog. The embed points displayed are determined by the identifier's template symbol and optional instances used to distinguish different embed areas. Essentially, this prompt allows the EMBED functionality to be called from a secondary window, eliminating screen clutter.

#### Example:

#PROMPT('Advanced...', EMBEDBUTTON(%ControlPostEventHandling,%Control,'Selected'))

# **FILE (list of files)**

**FILE** 

The **FILE** *type* in a #PROMPT statement indicates the prompt's *symbol* must contain the label of a data file. A list of available files from the procedure's Data / Tables Pad pops up when the #PROMPT is encountered on the Properties screen.

### Example:

#PROMPT('Logout File',FILE),%LogoutFile

# **FORMAT (call listbox formatter)**

### **FORMAT**

The **FORMAT** *type* in a #PROMPT statement indicates the prompt's *symbol* must contain a LIST or COMBO control's FORMAT attribute string, so it calls the listbox formatter to create it.

### Example:

#PROMPT('Alternate LIST format', FORMAT), %AlternateFormatString

# FROM (list of symbol values)

FROM( symbol [, expression ] [, value ] )

**FROM** Specifies a drop-down list of values from the *symbol*.

symbol A multi-valued symbol (built-in or user-defined).

expression An expression which controls which symbol values are displayed. Only symbol

values where the expression is true are displayed in the drop list.

value The symbol containing the content of the first parameter of the multi-valued

symbol.

The **FROM** *type* in a #PROMPT statement indicates the user must select one item from the list contained in the *symbol*. The *expression* can be used to limit the *values* displayed, while the *value* defines the display elements.

```
#PROMPT('Select an Event',FROM(%ControlEvent)),%WhichEvent
#PROMPT('Select a Button',FROM(%ControlField,%ControlType = 'BUTTON')),%WhichButton
#PROMPT('Pick a Field',FROM(%Control,%ControlUse <> '',%ControlUse)),%MyButton
```

## ICON (call Icon selection dialog)

ICON( title, extensions )

ICON Calls the Windows common Open File dialog.

Title A string constant containing the title to place on the file open dialog.

extensions A string constant containing the available file extension selections for the

List Files of Type drop list.

The **ICON** *type* in a #PROMPT statement is similar to the OPENDIALOG #PROMPT type, and indicates the prompt's *symbol* must contain the name of the file selected by the programmer from the Open File dialog (see also FILEDIALOG). The file must already exist on disk.

```
#PROMPT('Icon (*.ico):',ICON('Select ChildRoot Level Icon','Icon files (*.ico)|*.ico')),%MCRTChil
#PROMPT('&Default Icon:',ICON),%PrimaryDefaultIcon
#PROMPT('Start Icon',ICON('Select an Icon','Icons|*.ICO|GIF|*.GIF|JPEG|*.JPG|BitMap|*.BMP|Pcx|*.F
```

# **KEY (list of keys)**

KEY [ ( scope ) ]

**KEY** Displays a list of KEYs.

scope A symbol containing a FILE. If omitted, the list displays all KEYs in all FILEs.

The **KEY** *type* in a #PROMPT statement indicates the prompt's *symbol* must contain the label of a KEY. A list of available keys from the data dictionary pops up when the #PROMPT is encountered on the Properties screen.

There may be a *scope* parameter that limits the KEYs available in the list. If *scope* names a FILE, the list displays all KEYs in the FILE. If there is no *scope* parameter, the list displays all KEYs in all FILEs.

#### **Example:**

#PROMPT('Which Key', KEY(%Primary)), %UseKey

# **KEYCODE** (list of keycodes)

### **KEYCODE**

The **KEYCODE** *type* in a #PROMPT statement indicates the prompt's *symbol* must contain a keycode or keycode equate label. A selection list of keycode equate labels from KEYCODES.EQU pops up when the user presses the ellipsis button next to the prompt on the Properties screen.

### Example:

#PROMPT('Hot Key', KEYCODE), %ActiveKey

# **OPENDIALOG** (call Open File dialog)

**OPENDIALOG(** title, extensions)

**OPENDIALOG** Calls the Windows common Open File dialog.

title A string constant containing the title to place on the file open dialog.

extensions A string constant containing the available file extension selections for the

List Files of Type drop list.

The **OPENDIALOG** *type* in a #PROMPT statement indicates the prompt's *symbol* must contain the name of the file selected by the programmer from the Open File dialog (see FILEDIALOG in the *Language Reference*). The file must already exist on disk.

#### Example:

#PROMPT('Ask for File', OPENDIALOG('Pick File', 'Source | \*.CLW')), %FileSymbol

# **OPTFIELD** (optional text or data field)

### **OPTFIELD**

The **OPTFIELD** *type* in a #PROMPT statement indicates the prompt's *symbol* may either contain text entered by the programmer or the label of a field in a data file. When a field is selected, the #PROMPT symbol contains the field name with an exclamation prepended (!FieldName). A list of available fields pops up when the programmer presses the "..." button next to the #PROMPT entry box on the Properties screen.

### Example:

#PROMPT('Default Value',OPTFIELD),%DefaultValue

# **OPTION** (display radio buttons)

### **OPTION**

The **OPTION** *type* in a #PROMPT statement indicates the prompt's *symbol* receives the value of one of the *strings* in one of the following RADIO #PROMPT statements, unless the CHOICE attribute is present, then the *symbol* receives the ordinal position number of the RADIO #PROMPT the programmer chooses from an OPTION set instead of the *string* text. Each of the *strings* displays a radio button on the Properties screen when the #PROMPT is encountered.

```
#PROMPT('Ask for Choice',OPTION),%OptionSymbol
#PROMPT('Option One',RADIO)
#PROMPT('Option Two',RADIO)
#PROMPT('Option Three',RADIO)
```

# **PICTURE** (call picture formatter)

### **PICTURE**

The **PICTURE** *type* in a #PROMPT statement calls the picture formatter to create a picture token used to format data for display.

### Example:

#PROMPT('Display Format', PICTURE), %DisplayPicture

# PROCEDURE (add to logical procedure tree)

### **PROCEDURE**

The **PROCEDURE** *type* in a #PROMPT statement indicates the value placed in the *symbol* is the name of a procedure in your application. This procedure name is added to the Application Generator's logical procedure call tree in the appropriate place.

### Example:

#PROMPT('Next Procedure', PROCEDURE), %NextProcedure

## **RADIO** (one radio button)

**RADIO** 

The **RADIO** *type* in a #PROMPT statement creates one RADIO button for the closest preceding OPTION prompt. When selected, the RADIO's *string* is placed in the OPTION's *symbol* unless the CHOICE attribute or VALUE is present. With the CHOICE attribute on the OPTION, the *symbol* receives the ordinal position number of the RADIO #PROMPT the programmer chooses from an OPTION set instead of the *string* text. With the VALUE attribute on the RADIO, the *symbol* receives *value* text.

```
#PROMPT('Ask for Choice', OPTION), %OptionSymbol
#PROMPT('Option One', RADIO)
#PROMPT('Option Two', RADIO)
#PROMPT('Option Three', RADIO)
#PROMPT('Ask for Another Choice',OPTION),%OptionSymbol2,CHOICE
#PROMPT('Option A', RADIO)
                                             #!%OptionSymbol2 receives 1
#PROMPT('Option B', RADIO)
                                             #!%OptionSymbol2 receives 2
#PROMPT('Option C', RADIO)
                                             #!%OptionSymbol2 receives 3
#PROMPT('Ask for Yet Another Choice',OPTION),%OptionSymbol3
#PROMPT('Option A', RADIO), VALUE('A')
                                             #!%OptionSymbol3 receives A
#PROMPT('Option B', RADIO), VALUE('B')
                                             #!%OptionSymbol3 receives B
#PROMPT('Option C', RADIO), VALUE('C')
                                             #!%OptionSymbol3 receives C
```

# SAVEDIALOG (call Save File dialog)

SAVEDIALOG( title, extensions )

**SAVEDIALOG** Calls the Windows common Save File dialog.

title A string constant containing the title to place on the file save dialog.

extensions A string constant containing the available file extension selections for the List

Files of Type drop list.

The **SAVEDIALOG** *type* in a #PROMPT statement indicates the prompt's *symbol* must contain the name of the file selected by the programmer from the Save File dialog (see FILEDIALOG in the *Language Reference*). The file must not already exist on disk.

#### Example:

#PROMPT('Ask for FileName', SAVEDIALOG('Pick File', 'Source|\*.CLW')), %FileSymbol

## SPIN (spin box)

SPIN( picture, low, high [, step ] )

**SPIN** Creates a spin control.

picture A data entry picture token.

low A numeric constant or expression containing the lowest valid value.

high A numeric constant or expression containing the highest valid value.

step A numeric constant or expression containing the amount to change each

increment between lowest and highest valid values. If omitted, the default is 1.

The **SPIN** *type* in a #PROMPT statement creates a spin control for the programmer to select a valid number.

#### Example:

```
#PROMPT('How Many?',SPIN(@n2,1,10)),%SpinSymbol
```

# **TEXT** (text box)

#### **TEXT**

The **TEXT** *type* in a #PROMPT statement creates a multi-line text entry control for the programmer to enter text into.

#### Example:

#PROMPT('Comment?', TEXT), %Comments

### **#PROTOTYPE** (procedure prototype)

**#PROTOTYPE(** parameter list)

**#PROTOTYPE** Assigns the *parameter list* to the **Prototype** entry field.

parameter list

A string constant containing the procedure's prototype parameter list (the entire procedure prototype without the leading procedure name) for the application's MAP structure (see the discussion of *Procedure Prototypes* in the *Language Reference*).

The **#PROTOTYPE** statement assigns the *parameter list* to the **Prototype** entry field on the Application Generator's Procedure Properties window, which automatically "dims out" the field (the programmer may not override this Prototype). This allows you to create procedure Templates which require a specific parameter list without forcing the programmer to know the procedure's prototype.

The #PROTOTYPE statement is valid only within a #PROCEDURE section and only one is allowed per #PROCEDURE section. If there is no #PROTOTYPE statement in the #PROCEDURE, the programmer is allowed to change it.

```
#PROCEDURE(SomeProc,'Some Procedure Template')
%Procedure PROCEDURE(Parm1,Parm2,Parm3)
  #PROTOTYPE('(STRING,*LONG,<*SHORT>)')
         #!This procedure expects three parameters:
         #! a STRING passed by value
            a LONG passed by address
         #!
            a SHORT passed by address which may be omitted
#PROCEDURE (SomeFunc, 'Some Template Procedure')
%Procedure PROCEDURE (Parm1, Parm2, Parm3)
  #PROTOTYPE('(STRING,*LONG,<*SHORT>),STRING')
         #!This procedure expects three parameters:
         #! a STRING passed by value
         #! a LONG passed by address
         #! a SHORT passed by address which may be omitted
         #!It returns a STRING
```

# **#PURGE** (delete all single or multi-valued symbol instances)

**#PURGE(** symbol)

**#PURGE** Deletes the values from all instances of a user-defined symbol.

symbol A user-defined symbol.

The **#PURGE** statement deletes all values from the *symbol*. If there are any symbols dependent upon the *symbol*, they are also cleared. If the *symbol* is dependent upon a multi-valued symbol, all instances of that dependent *symbol* are purged for all instances of the symbol upon which it is dependent.

### Example:

```
#DECLARE(%ProcFilesPrefix),MULTI #!Declare multi-valued symbol
#ADD(%ProcFilesPrefix,'SAV') #!Add a value
#ADD(%ProcFilesPrefix,'BAK') #!Add a value
#ADD(%ProcFilesPrefix,'PRE') #!Add a value
#ADD(%ProcFilesPrefix,'BAK') #!Add a value
#ADD(%ProcFilesPrefix,'QUE') #!Add a value
#!%ProcFilesPrefix contains: SAV, BAK, PRE, BAK, QUE
#PURGE(%ProcFilesPrefix) #!Delete all instances
```

See Also: #DECLARE,#ADD

### **#QUERY** (conditionally generate source)

#QUERY( section, source )

**#QUERY** Generates source if the named #SUSPEND section has been released.

section The name of the #SUSPEND section to #QUERY.

source The code to generate.

The **#QUERY** statement conditionally generates its *source* based on whether the named #SUSPEND *section* has been released (either explicitly or implicitly). If the #SUSPEND *section* has been released then #QUERTY generates its source, without affecting the release of any other nested #SUSPEND section it may be in--it does not create an implict #RELEASE.

#### Example:

```
#SUSPEND(Fred) #!Begin suspended generation section named "Fred"
#?1
#SUSPEND #!Begin unnamed suspended generation section
#?2
#QUERY(Fred,'3') #!Generate "3" only if the "Fred" section is released
#?4
#RESUME

#!Unconditional generation causes implicit #RELEASE of "Fred"
#RESUME #!End "Fred" section

#!The above code will generate 1, 3, 5 on successive output lines
#!The 2 and 4 don't generate because the unnamed section was not released
```

See Also: #SUSPEND

# #READ (read one line of a source file)

#READ( symbol)

**#READ** Reads the next record from the opened read-only file.

symbol The symbol to receive the text from the file.

The **#READ** statement reads the next record (up to the next CR/LF encountered) from open readonly file. The *symbol* receives the text from the file. If the last record has been read, the *symbol* will contain a value equivalent to the %EOF built-in symbol.

#### Example:

```
#OPEN(%ProgramFile),READ #!Open it in read-only mode
#DECLARE(%ASCIIFileRecord)
#LOOP
    #READ(%ASCIIFileRecord)
#IF(%ASCIIFileRecord = %EOF)
    #BREAK
#ENDIF
#! Parse the line and do something with it
#ENDLOOP
#CLOSE(%ProgramFile),READ #!Close the read-only file
```

See Also: #OPEN, #CLOSE

### **#REDIRECT** (change source file)

#REDIRECT([file])

#### **#REDIRECT** Changes the current generated source destination file.

file

A string constant, template symbol, or expression containing a DOS file specification that has already been opened with #OPEN or #CREATE. This may be a fully qualified DOS pathname. If omitted, the source generation destination returns to the previous file that received generated source.

The **#REDIRECT** statement changes the destination *file* for generated source code. All source generation output is directed to the specified *file* until a #OPEN or another #REDIRECT statement is executed. If the file has not been previously opened (or created), or is closed, then a source generation error is produced.

The destination files for generated source are kept as a LIFO (Last In, First Out) "stack" list. When #REDIRECT is issued without a *file* parameter, the source generation destination reverts to the previous destination file.

```
#SET(%NewProgramFile,(%Application & '.CLW'))
                                                  #!Temp new program filename
#CREATE(%NewProgramFile)
                                                  #!Create new program file
#FOR(%Module)
  #CREATE(%Module & '.CLW')
                                                  #!Make module files
#ENDFOR
#REDIRECT(%NewProgramFile)
                                                  #!Redirect output to program file
#GENERATE (%Program)
                                                  #!Generate main program header
#CLOSE (%NewProgramFile)
                                                  #!Create new program file
#FOR (%Module)
  #REDIRECT(%Module & '.CLW')
                                                  #!Redirect output to module file
  #GENERATE (%Module)
                                                  #!Generate module header
                                                  #!For all procs in module
  #FOR (%ModuleProcedure)
    #FIX(%Procedure,%ModuleProcedure)
                                                  #!Fix current procedure
    #GENERATE (%Procedure)
                                                  #!Generate procedure code
  #ENDFOR
                                                  #!EndFor all procs in module
#ENDFOR
#!The following code demonstrates the LIFO files list:
#REDIRECT('F1.CLW')
                                                  #!List contains:
                                                                     F1
#REDIRECT('F2.CLW')
                                                  #!List contains:
                                                                     F1, F2
#REDIRECT('F3.CLW')
                                                                     F1, F2,
                                                  #!List contains:
                                                                               F3
#REDIRECT()
                                                  #!List contains:
                                                                     F1,
                                                                          F2
#REDIRECT()
                                                  #!List contains:
                                                                     F1
```

## **#REJECT** (section invalid for use)

#### #REJECT

The **#REJECT** statement terminates #RESTRICT processing, indicating that the Template Code Section (#CODE, #CONTROL, #EXTENSION, #PROCEDURE, #PROGRAM, or #MODULE) is invalid.

The #RESTRICT structure contains Template language *statements* that evaluate the propriety of generating the section's source code. The #ACCEPT statement may be used to explicitly declare the section as appropriate. An implicit #ACCEPT also occurs if the #RESTRICT *statements* execute without encountering a #REJECT statement. The #REJECT statement must be used to specifically exclude the section from use. Both the #ACCEPT and #REJECT statements immediately terminate processing of the #RESTRICT code.

#### **Example:**

```
#CODE (ChangeControlSize, 'Change control size')
  #WHERE (%EventHandling)
  #RESTRICT
    #CASE(%ControlType)
    #OF 'LIST'
    #OROF 'BUTTON'
      #REJECT
    #ELSE
      #ACCEPT
    #ENDCASE
  #ENDRESTRICT
  #PROMPT('Control to change',CONTROL),%MyField,REQ
  #PROMPT('New Width',@n04),%NewWidth
  #PROMPT('New Height',@n04),%NewHeight
%MyField{PROP:Width} = %NewWidth
%MyField{PROP:Height} = %NewHeight
```

See Also: #RESTRICT, #ACCEPT

### #RELEASE (commit conditional source generation)

#### #RELEASE

The **#RELEASE** enables source generation in a **#SUSPEND** section. This allows empty unnecessary "boiler-plate" code to be easily removed from the generated source. The code in a **#SUSPEND** section is generated only when a **#RELEASE** statement is encountered.

#SUSPEND sections may be nested within each other to as many levels as necessary. A #RELEASE encountered in an inner nested section commits source generation for all the outer nested levels in which it is contained, also.

A #EMBED that contains source to generate performs an implied #RELEASE. Any generated source output also performs an implied #RELEASE. Therefore, an explicit #RELEASE statement is not always necessary. The #? statement defines an individual conditional source line that does not perform the implied #RELEASE.

```
ACCEPT
#SUSPEND
                              #!Begin suspended generation
  #?CASE SELECTED()
  #FOR(%ScreenField)
    #SUSPEND
  #?OF %ScreenField
    #EMBED(%ScreenSetups, 'Control selected code'), %ScreenField
    #!Implied #RELEASE from the #EMBED of both nested sections
    #RESUME
  #?END
#RESUME
                              #!End suspended generation
#SUSPEND
                              #!Begin suspended generation
  #?CASE EVENT()
  #SUSPEND
  #?OF EVENT:AlertKey
    #SUSPEND
    #?CASE KEYCODE()
      #FOR %HotKey
        #RELEASE
                              #!Explicit #RELEASE
    #?OF %HotKey
      #EMBED(%HotKeyProc,'Hot Key code'),%HotKey
      #ENDFOR
    #?END
    #RESUME
  #?END
#RESUME
                              #!End suspended generation
END
    IF scField
        scField{Prop:Background} = scColor
#!
#! test for style
#SUSPEND
        #?scField{Prop:FontStyle} = scStyle
#IF(%SelectedStyle = %True)
```

### **#REMOVE** (delete a source file)

#REMOVE(file)

**#REMOVE** Deletes a source output file.

file A string constant, template symbol, or expression containing a DOS

file specification. This may be a fully qualified DOS pathname.

The **#REMOVE** statement deletes the specified source output *file*. If the *file* does not exist, #REMOVE is ignored and source generation continues.

#### **Example:**

```
#FOR(%Module)
   #SET(%TempModuleFile,(%Module & '.$$$'))
                                                       #!Set temp module file
   #CREATE (%TempModuleFile)
                                                       #!Create temp module file
   #FOR(%ModuleProcedure)
                                                       #!For all procs in module
      #FIX(%Procedure,%ModuleProcedure)
                                                       #!Fix current procedure
      #GENERATE (%Procedure)
                                                       #!Generate procedure code
                                                       #!EndFor all procs in module
   #SET(%ModuleFile,(%Module & '.CLW'))
                                                       #!Set to current module file
   #CREATE(%ModuleFile)
                                                       #!Create module file
   #GENERATE (%Module)
                                                       #!Generate module header
   #APPEND (%TempModuleFile)
                                                       #!Add generated procedures
   #REMOVE (%TempModuleFile)
                                                       #!Delete the temporary file
```

#ENDFOR

### **#REPLACE** (conditionally replace source file)

#REPLACE( oldfile, newfile )

**#REPLACE** Performs "intelligent" file replacement.

oldfile A string constant, template symbol, or expression containing a DOS file specification. This

may be a fully qualified DOS pathname.

newfile A string constant, template symbol, or expression containing a DOS file specification. This

may be a fully qualified DOS pathname.

The **#REPLACE** statement performs a binary comparison between the contents of the *oldfile* and *newfile*. If the contents of the *oldfile* are different from the contents of the *newfile* (or the *oldfile* does not exist), then the *oldfile* is deleted and the *newfile* is copied to the *oldfile*. If the two files are identical, then no action is taken. If the *newfile* does not exist, #REPLACE is ignored and source generation continues.

```
#FOR(%Module)
   #SET(%TempModuleFile,(%Module & '.$$$'))
                                                      #!Set temp module file
   #CREATE (%TempModuleFile)
                                                      #!Create temp module file
   #GENERATE (%Module)
                                                      #!Generate module header
   #FOR(%ModuleProcedure)
                                                      #!For all procs in module
      #FIX(%Procedure,%ModuleProcedure)
                                                      #!Fix current procedure
                                                      #!Generate procedure code
      #GENERATE (%Procedure)
   #ENDFOR
                                                      #!EndFor all procs in module
   #SET(%ModuleFile,(%Module & '.CLW'))
                                                      #!Set to existing module file
   #REPLACE(%ModuleFile,%TempModuleFile)
                                                      #!Replace old with new (if changed)
```

# **#REPORTS** (default report structures)

#### #REPORTS

structures

**#ENDREPORTS** 

**#REPORTS** Begins a default report data structure section.

structures Default REPORT structures.

**#ENDREPORTS** Terminates the default report section.

The **#REPORTS** structure contains default REPORT data structures for a procedure Template. The default report *structures* provide a starting point for the procedure's report design.

The #REPORTS section may contain multiple *structures* which may be chosen as the starting point for the procedure's report design. If there is more than one report structure to choose from, the Application Generator displays a list of those *structures* available the first time the procedure's report is editted. The names of the windows which appear in the Application Generator's list comes from a preceding comment beginning with two exclamations and a right angle bracket (!!>).

If the procedure template contains a #DEFAULT procedure, there is no need for #REPORT, since the default report is already in the #DEFAULT. Therefore, the list does not appear when the report is first editted.

```
#REPORTS
```

## **#RESTRICT** (define section use constraints)

```
#RESTRICT [, WHERE( expression ) ]
    statements
#ENDRESTRICT
```

#### {bmc blk2blue.bmp}

#RESTRICT Specifies conditions where a Template Code Section (#CODE, #CONTROL,

#EXTENSION, #PROCEDURE, #PROGRAM, or #MODULE) can be used.

**WHERE** The #RESTRICT *statements* are excuted only when the *expression* is true.

expression A logical expression to limit execution of the #RESTRICT statements.

statements Template language code to #ACCEPT or #REJECT use of the section which

contains the #RESTRICT structure.

**#ENDRESTRICT** Terminates the #RESTRICT structure.

The **#RESTRICT** structure provides a mechanism to limit the availability of a Template Code Section (#CODE, #CONTROL, #EXTENSION, #PROCEDURE, #PROGRAM, or #MODULE) at application design time to only those points where the generated code would be appropriate. Any WHERE clause on the Template Code Section is evaluated first, before #RESTRICT.

The #ACCEPT statement may be used to explicitly declare the section as appropriate for use. An implicit #ACCEPT also occurs if the #RESTRICT statements execute without encountering a #REJECT statement. The #REJECT statement must be used to specifically exclude the section from use. Both the #ACCEPT and #REJECT statements immediately terminate processing of the #RESTRICT code.

#### **Example:**

```
#CODE(ChangeControlSize,'Change control size')
#RESTRICT
    #CASE(%ControlType)
    #OF('LIST')
    #OROF('BUTTON')
    #REJECT
    #ELSE
     #ACCEPT
    #ENDCASE
#ENDRESTRICT
#PROMPT('Control to change',CONTROL),%MyField,REQ
#PROMPT('New Width',@n04),%NewWidth
#PROMPT('New Height',@n04),%NewHeight
%MyField{PROP:Width} = %NewWidth
%MyField{PROP:Height} = %NewHeight
```

See Also: #ACCEPT ,#REJECT

## **#RESUME** (delimit conditional source)

#### #RESUME

The **#RESUME** statement marks the end of a section of source that is generated only if a #RELEASE statement is encountered. This allows empty unnecessary "boiler-plate" code to be easily removed from the generated source. The beginning of the section must be delimited by a matching #SUSPEND statement.

These #SUSPEND sections may be nested within each other to as many levels as necessary. A #RELEASE encountered in an inner nested section commits source generation for all the outer nested levels in which it is contained, also.

A #EMBED that contains source to generate performs an implied #RELEASE. Any generated source output also performs an implied #RELEASE. Therefore, an explicit #RELEASE statement is not always necessary. The #? statement defines an individual conditional source line that does not perform the implied #RELEASE.

When a #RESUME is executed without the output to the file being released, any conditional lines of code are un-done back to the matching #SUSPEND.

#### **Example:**

```
ACCEPT
#SUSPEND
                                 #!Begin suspended generation
  #?CASE SELECTED()
  #FOR(%ScreenField)
    #SUSPEND
  #?OF %ScreenField
    #EMBED(%ScreenSetups,'Control selected code'),%ScreenField
    #!Implied #RELEASE from the #EMBED of both nested sections
    #RESUME
  #?END
#RESUME
                                 #!End suspended generation
#SUSPEND
                                 #!Begin suspended generation
  #?CASE EVENT()
  #SUSPEND
  #?OF EVENT:AlertKey
    #SUSPEND
    #?CASE KEYCODE()
      #FOR %HotKey
        #RELEASE #!Explicit #RELEASE
    #?OF %HotKey
      #EMBED(%HotKeyProc,'Hot Key code'),%HotKey
      #ENDFOR
    #?END
    #RESUME
  #?END
#RESUME
                                 #!End suspended generation
END
```

See Also: #SUSPEND, #RELEASE, #?

## **#RETURN** (return from **#GROUP**)

#RETURN([returnvalue])

**#RETURN** Immediately returns from the #GROUP.

returnvalue An expression containing the value to return to the calling statement. If

omitted, an empty string (") is returned.

The **#RETURN** statement immediately returns control to the statement following the #INSERT, #CALL, or #INVOKE that called the #GROUP, or returns the *returnvalue* to the CALL or INVOKE built-in procedures. If the #INSERT, #CALL, or #INVOKE that called the #GROUP are set to receive the *returnvalue*, the value is placed in the symbol named in the #INSERT, #CALL, or #INVOKE statement.

#RETURN is only valid in a #GROUP section.

#### Example:

```
#GROUP(%ProcessListGroup,%PassedControl)
#FIX(%ScreenField,%PassedControl)
#IF (%ScreenFieldType <> 'LIST')
#UNFIX(%ScreenField)
#RETURN
#ENDIF
```

See Also: #GROUP, #INSERT, #CALL, CALL, #INVOKE, INVOKE

# **#RUN** (execute program)

#RUN( program ) [, WAIT ]

**#RUN** Launches the named *program*.

program A string constant containing the name of the program to

execute, including any command line parameters.

**WAIT** Specifies waiting for the *program* to complete its execution

before proceeding to the next template language statement.

The **#RUN** statement launches the specified *program* by using the Clarion language RUN statement. Template execution continues concurrently with the execution of the *program*, unless the WAIT attribute is specified.

#### Example:

#RUN ('MyExe.EXE')

#!Launch MyExe.EXE

## **#RUNDLL** (execute DLL procedure)

#RUNDLL( library, procedure [, parameter ] ) [, | RETAIN | ] [, WIN32 ]

#RUNDLL Executes a procedure from any Windows-standard Dynamic Link Library (.DLL). library A string constant containing the name of the .DLL file, including the extension. procedure A string constant containing the name of the procedure in the DLL file to execute. parameter A string constant or expression containing a single parameter to pass to the procedure. **RETAIN** Specifies that the *library* stays in memory after the *procedure* has completed execution. RELEASE Specifies that the *library* is unloaded from memory after the *procedure* has completed execution. WIN32 Specifies that the library is a 32-bit DLL.

The **#RUNDLL** statement executes the specified *procedure* from the specified *library*. The *library* .DLL is dynamically loaded before the *procedure* executes and unloaded after, unless the RETAIN attribute is specified.

If the RETAIN attribute is specified, another #RUNDLL statement with the RELEASE attribute and naming the same *library* must follow so that the .DLL is unloaded from memory. Failure to unload the .DLL can result in memory leaks. The RETAIN and RELEASE attributes can be nested as long as the #RUNDLL statements match up.

If a parameter is named, then the procedure must accept a single \*CSTRING parameter (only). If no parameter is named, then the procedure must not accept any parameters. In either case, the procedure cannot return a value. If the parameter named is a single-valued user-defined symbol, then any changes to the passed parameter's value in the called procedure are reflected in that parameter symbol.

#### Example:

```
!A .DLL 'Services.DLL' contains these two procedures:
SoundBeep PROCEDURE
CODE
BEEP
AskForName PROCEDURE (*CSTRING Name)
Window WINDOW ('Enter Name), AT(,,260,100), SYSTEM, GRAY, AUTO
         ENTRY (@s20), AT (4,4), USE (Name)
         BUTTON ('OK'), AT (200,4), USE (?Ok), STD (STD:Close)
 CODE
OPEN (Window)
ACCEPT
 END
! The Template code that calls the procedures in Services.DLL:
#DECLARE (%UserName)
#SET (%UserName, 'Unknown')
#RUNDLL ('Services.DLL', 'SoundBeep'),RETAIN
                                                     !Use RETAIN to improve performance
#RUNDLL ('Services.DLL', 'AskForName', %UserName)
#RUNDLL ('Services.DLL', 'SoundBeep'),RELEASE
                                                     !RELEASE matches the RETAIN
```

## **#SECTION** (define code section)

#SECTION (<name>)
statements
#ENDSECTION

**#SECTION** Marks the beginning of a section of generated code.

name A string that identifies the name of the section.

statements Any template or target language statements.

**#ENDSECTION** Terminates the #SECTION.

The **#SECTION** structure defines a contiguous section of generated code so that the position of embedded source code is correctly patched up for error positions in the resulting generated code. #APPEND with the SECTION attribute performs the patch.

#### **Named Sections**

A *name* parameter has been added to the #SECTION statement. This parameter can then be referenced by the SECTION attribute of the #APPEND statement as follows:

```
#SECTION('First Section')
...
#ENDSECTION

#SECTION('Another Section')
...
#ENDSECTION
...

#APPEND('FileName'), SECTION('Another Section')
#APPEND('FileName'), SECTION('First Section')
```

The first #APPEND statement with the SECTION attribute uses the last defined section in source order. The next #APPEND statement is used for the previous section, etc. A named #SECTION can be used with the #APPEND statement **only once**. If the SECTION attribute of the #APPEND statement has a parameter defined, for example:

```
#APPEND('somefile'), SECTION('somesection')
```

The template source generator will append the #SECTION defined with the name 'somesection' and then removes it from the list of sections. If the SECTION attribute has no parameter

```
#APPEND('somefile'), SECTION
```

The generator uses the most recently declared #SECTION not removed yet from the top of sections stack and then pops it (but does not destroy).

In summary, to avoid any logic problems, all #APPEND statements **should not** mix usage of named and unnamed sections.

#### Other Example:

See Also: #APPEND

```
#CREATE(%Temp) #!Create temp module file

#SECTION

#EMBED(%MyEmbed,@s30)

#ENDSECTION

#CLOSE

#CREATE('target.clw')

CODE

#APPEND(%Temp),SECTION #!Correctly patch position of #EMB

ED

#CLOSE
```

### Named #SECTIONS

A new parameter has been added to the #SECTION statement.

#### Example:

```
#SECTION('First Section')
...
#ENDSECTION

#SECTION('Another Section')
...
#ENDSECTION
```

This parameter can then be referenced by the SECTION attribute of the #APPEND statement as follows:

```
#APPEND('FileName'), SECTION('Another Section')
#APPEND('FileName'), SECTION('First Section')
```

The first #APPEND statement with the SECTION attribute uses the last defined section in source order. The next #APPEND statement is used for the previous section, etc

A named #SECTION can be used with the #APPEND statement only once.

If the SECTION attribute of the #APPEND statement has a parameter defined, for example:

```
#APPEND('somefile'), SECTION('somesection')
```

the template source generator will append the #SECTION defined with the name 'somesection' and then removes it from the list of sections.

If the SECTION attribute has no parameter

```
#APPEND('somefile'), SECTION
```

the generator uses the most recently declared #SECTION not removed yet from the top of sections stack and then pops it (but does not destroy).

In summary, to avoid any logic problems, all #APPEND statements **should not** mix usage of named and unnamed sections.

# **#SELECT** (fix a multi-value symbol)

#SELECT( symbol, instance)

**#SELECT** Fixes a multi-valued symbol to a particular *instance* number.

symbol A multi-valued symbol.

instance An expression containing the number of the instance to which to fix.

The **#SELECT** statement fiXEs the current value of the multi-valued *symbol* to a specific *instance*. The result of #SELECT is exactly the same as #FIX. Each *instance* in the multi-valued *symbol* is numbered starting with one (1).

The *instance* must contain a valid instance number of one of the *symbol's* multiple values. If the *instance* is not valid, the *symbol* is cleared and contains no value when referenced. The INSTANCE built-in template procedure can return the instance number.

Unless #ADD has been used to add a new value and fix to that instance, #FIX or #SELECT must be used to set the value in a *symbol* before it contains any value for Template processing outside of a #FOR loop.

#### Example:

#SELECT(%File,1) #!Fix to first %File instance

## See Also:

#FIX ,#FIND

# **#SERVICE** (internal use only)

#### **#SERVICE**

The **#SERVICE** statement is for internal use only. It is not documented and is listed here simply because it is visible in the shipping templates.

## **#SET** (assign value to a user-defined symbol)

#SET( symbol, value )

**#SET** Assigns a value to a single-valued user-defined symbol.

symbol A single-valued user-defined symbol. This must have been previously declared with the

#DECLARE statement.

value A built-in or user-defined symbol, string constant, or an expression.

The **#SET** statement assigns the *value* to the *symbol*. If the *value* parameter contains an expression, you may perform mathematics during source code generation. The expression may use any of the arithmetic, Boolean, and logical operators documented in the *Language Reference*. If the modulus division operator (%) is used in the expression, it must be followed by at least one blank space (to explicitly differentiate it from the Template symbols). Logical expressions always evaluate to 1 (True) or 0 (False). Clarion language procedure calls (those supported in EVALUATE()) and built-in template procedures are allowed.

#### Example:

```
#SET(%NetworkApp,'Network')
#SET(%MySymbol,%Primary)
#FOR(%File)
    #SET(%FilesCounter,%FilesCounter + 1)
%FileStructure
#ENDFOR
```

See Also: #DECLARE

## **#SHEET (declare a group of #TAB controls)**

```
#SHEET [, HSCROLL ] [, ADJUST ]

tabs
#ENDSHEET
```

**#SHEET** Declares a group of #TAB controls.

**HSCROLL** Specifies scrolling #TAB controls.

**ADJUST** Specifies automatic prompt positioning if the #TAB controls create more than one row of tabs.

tabs Multiple #TAB control declarations.

**#ENDSHEET** Terminates the group box of *prompts*.

**#SHEET** declares a group of #TAB controls that offer the user multiple "pages" of prompts for the window. The multiple #TAB controls in the SHEET structure define the "pages" displayed to the user.

```
#UTILITY(ApplicationWizard, 'Create a New Database Application'), WIZARD
#!
#SHEET
 #TAB('Application Wizard')
    #IMAGE ('CMPAPP.BMP')
    #DISPLAY('This wizard will create a new Application.'), AT(90,8,235,24)
    #DISPLAY('To begin creating your new Application, click Next.'), AT(90)
  #ENDTAB
  #TAB('Application Wizard - File Usage'),FINISH(1)
   #IMAGE ('WINAPP.BMP')
   #DISPLAY('You can gen procs for all files, or select them'), AT(90,8,235,24)
    #PROMPT('Use all files in DCT',CHECK),%GenAllFiles,AT(90,,180),DEFAULT(1)
  #ENDTAB
  #TAB('Select Files to Use'), WHERE(NOT %GenAllFiles), FINISH(1)
   #IMAGE('WINAPP.BMP')
    #PROMPT('File Select',FROM(%File)),%FileSelect,INLINE,SELECTION('File Select')
  #TAB('Application Wizard - Finally...'),FINISH(1)
   #IMAGE('WINAPP.BMP')
   #DISPLAY('Old procs can be overwritten or new procs suppressed')
   #PROMPT('Overwrite existing procs',CHECK),%OverwriteAll,AT(90,,235),DEFAULT(0)
    #IMAGE('<255,1,4,127>'),AT(90,55)
    #DISPLAY('Your First Procedure is always overwritten!'),AT(125,54,200,20)
  #ENDTAB
#ENDSHEET
```

## **#SUSPEND** (begin conditional source)

#SUSPEND(<section>)

**#SUSPEND** Identify the start of a conditionally generated source section

section A name that identifies a specific #SUSPEND section

The **#SUSPEND** statement marks the start of a section of source that is generated only if a non-conditional source line or a #RELEASE statement is encountered. (i.e., a line of code without "#?" or a #RELEASE must be encountered for the code between #SUSPEND and #RESUME to be generated). This allows empty unnecessary "boiler-plate" code to be easily removed from the generated source. The end of the section must be delimited by a matching #RESUME statement.

These #SUSPEND sections may be nested within each other to as many levels as necessary. A #RELEASE encountered in an inner nested section commits source generation for all the outer nested levels in which it is contained, also. The *section* parameter is used to distinguish between other nested #SUSPEND statements.

A #EMBED that contains source to generate performs an implied #RELEASE. Any generated source output also performs an implied #RELEASE. Therefore, an explicit #RELEASE statement is not always necessary. The #? statement defines an individual conditional source line that does not perform the implied #RELEASE.

```
ACCEPT
#SUSPEND
                                #!Begin suspended generation
  #?CASE SELECTED()
  #FOR(%ScreenField)
    #SUSPEND
  #?OF %ScreenField
    #EMBED(%ScreenSetups, 'Control selected code'), %ScreenField
                                #!Implied #RELEASE from the #EMBED of both nested sections
    #RESUME
  END
#RESUME
                                #!End suspended generation
#SUSPEND
                                #!Begin suspended generation
  #?CASE EVENT()
  #SUSPEND
  #?OF EVENT: AlertKey
    #SUSPEND
    #?CASE KEYCODE()
      #FOR %HotKey
                                #!Explicit #RELEASE
        #RELEASE
    #?OF %HotKey
      #EMBED(%HotKeyProc,'Hot Key code'),%HotKey
      #ENDFOR
    # ? END
    #RESUME
  #?END
#RESUME
                                #!End suspended generation
END
See Also: #RELEASE ,#RESUME ,#? ,#QUERY
```

## **#SYSTEM** (template registration and load)

#### **#SYSTEM**

The **#SYSTEM** statement marks the beginning of a section of Template code which executes when the Template set is registered or loaded from the template registry. The section is terminated by the next Template Code Section (#PROGRAM, #MODULE, #PROCEDURE, #CONTROL, #CODE, #EXTENSION, #UTILITY, or #GROUP) statement. Any #PROMPT statements in a #SYSTEM section appear on the Application Options dialog, once the Template Registry has been loaded (opened an .APP file).

#### Example:

#### #SYSTEM

#TAB('Wizards')

#PROMPT('Use Toolbar mode for Wizards',CHECK),%UseToolBarForWizard #ENDTAB

#DECLARE (%GlobalSystemSymbol)

## **#TAB** (declare a page of a **#SHEET** control)

**#TAB(** text ) [, **HLP(** helpid ) ] [,**FINISH(** expression )] [,**WHERE(** expression )] prompts

**#ENDTAB** 

**#TAB** Declares a group of *prompts* that constitute one of the multiple "pages" within a #SHEET structure.

text A string constant containing the text to display on the tab, or as the title of the

window, if the WIZARD attribute is present on the #UTILITY.

**HLP** Specifies on-line help is available.

FINISH Specifies the "Finish" button is present. Valid only in a #UTILITY with the

WIZARD attribute.

expression An expression that specifies whether the "Finish" button is enabled or disabled.

If the expression is true, the button is enabled, if false, the button is disabled.

WHERE Specifies the #BOXED is visible only for those instances where the expression

is true.

*expression* An expression that specifies the condition for use.

prompts One or more #PROMPT statements. This may also contain #DISPLAY,

#VALIDATE, #ENABLE, and #BUTTON statements.

**#ENDTAB** Terminates the page of *prompts*.

The **#TAB** structure declares a group of *prompts* that constitute one of the multiple "pages" of controls contained within a #SHEET structure. The multiple #TAB controls in the #SHEET structure define the "pages" displayed to the user.

```
#UTILITY(ApplicationWizard, 'Create a New Database Application'), WIZARD
#!
#SHEET
 #TAB('Application Wizard'),FINISH(0)
                                                    #!Finish button dim
    #IMAGE ('CMPAPP.BMP')
    #DISPLAY('This wizard will create a new Application.'), AT(90,8,235,24)
    #DISPLAY('To begin creating your new Application, click Next.'), AT(90)
  #TAB('Application Wizard - File Usage'),FINISH(1)
                                                           #!Finish button active
    #IMAGE ('WINAPP.BMP')
    #DISPLAY('You can gen procs for all files, or select them'), AT(90,8,235,24)
    #PROMPT('Use all files in DCT',CHECK),%GenAllFiles,AT(90,,180),DEFAULT(1)
  #ENDTAB
  #TAB('Select Files to Use'), WHERE(NOT %GenAllFiles), FINISH(1)
   #IMAGE('WINAPP.BMP')
   #PROMPT('File Select',FROM(%File)),%FileSelect,INLINE,SELECTION('File Select')
  #ENDTAB
  #TAB('Application Wizard - Finally...'),FINISH(1)
   #IMAGE('WINAPP.BMP')
   #DISPLAY('Old procs can be overwritten or new procs suppressed')
   #PROMPT('Overwrite existing procs',CHECK),%OverwriteAll,AT(90,,235),DEFAULT(0)
   #IMAGE('<255,1,4,127>'),AT(90,55)
    #DISPLAY('Your First Procedure is always overwritten!'),AT(125,54,200,20)
  #ENDTAB
#ENDSHEET
```

## **#TEMPLATE** (begin template set)

#TEMPLATE( name, description ) [, PRIVATE ] [, FAMILY( sets ) ]

**#TEMPLATE** Begins the Template set.

name The name of the Template set which uniquely identifies it for the Template

Registry and Template Language statements. This must be a valid Clarion label.

description A string constant describing the Template set for the Template Registry and

Application Generator.

**PRIVATE** Prevents re-generation from the Template Registry.

**FAMILY** Names the other Template sets in which the #TEMPLATE is valid for use.

sets A string constant containing a comma delimited list of the *names* of other

Template sets in which the #TEMPLATE is valid for use.

The **#TEMPLATE** statement marks the beginning of a Template set. This should be the first noncomment statement in the Template file. The Template Registry allows multiple Template sets to be registered for the Application Generator.

Each Template Code Section (#APPLICATION, #PROGRAM, #MODULE, #PROCEDURE, #CONTROL, #CODE, #EXTENSION, and #GROUP) within a Template is uniquely identified by its #TEMPLATE statement's *name* and the name of the section. This allows different Template sets to contain Template Code Sections with names that duplicate those in other Template sets without ambiguity, and allows the programmer to concurrently use Template sets from multiple sources to generate applications.

```
#TEMPLATE(SampleTemplate,'This is a sample Template'),PRIVATE,FAMILY('ABC')
#INCLUDE('FileTwo.TPW')
#INCLUDE('FileThree.TPW')
```

## **#TYPEMAP (map EQUATE to data type)**

**#TYPEMAP** ( equate data type, 32-bit representation [,16-bit representation] )

#TYPEMAP

Maps an EQUATE data type to a true data type based on the target operating system.

equate data type

A string constant containing the label of an equate used to represent a data type.

32-bit data type

A string constant containing the label of a data type that represents the equated data type in a 32-bit program.

A string constant containing the label of a data type that represents the equated data type in a 16-bit program.(deprecated)

The **#TYPEMAP** statement allows the template to map a data type EQUATE to a true data type based on the target operating system of the application. This allows the compiler to resolve these EQUATES to their respective data types.

```
#TYPEMAP('SIGNED','LONG')
#TYPEMAP('SIGNED','LONG','SHORT')
```

# **#UNFIX** (unfix a multi-value symbol)

**#UNFIX(** symbol)

**#UNFIX** Unfixes a multi-valued symbol.

symbol A multi-valued symbol.

The **#UNFIX** statement unfiXEs the current value of the multi-valued *symbol*. If the unfiXEd *symbol* is referenced outside a #FOR loop structure, it has no value and you cannot reference any other symbols dependent upon the multi-valued *symbol*.

```
#SET(%OneFile,'HEADER') #! Put values into two User-defined symbols
#SET(%TwoFile,'DETAIL')
#FIX(%File,%OneFile) #! %File refers to 'HEADER'
#FOR(%File) #! %File iteratively refers to all file names
#FIX(%File,%TwoFile) #! %File refers to 'DETAIL'
#ENDFOR
#! %File refers to 'HEADER' again
#UNFIX(%File) #! %File refers to no spcific value
```

## **#UTILITY** (utility execution section)

**#UTILITY(** name, description ) [, **HLP(** helpid ) ] [, **WIZARD(** procedure ) ]

#UTILITY	Begins a utility generation control.
name	The name of the #UTILITY which identifies it for the Template Registry. This must be a valid Clarion label.
description	A string constant describing the utility section.
HLP	Specifies on-line help is available.
helpid	A string constant containing the identifier to access the Help system. This may be either a Help keyword or "context string."
WIZARD	Specifies the #UTILITY is used as a Wizard to generate a procedure or a complete application.
procedure	A string constant containing the fully qualified name of the #PROCEDURE for which it is a WIZARD.

The **#UTILITY** statement marks the beginning of a utility execution control section. The section is terminated by the next Template Code Section (#PROGRAM, #MODULE, #PROCEDURE, #CONTROL, #CODE, #EXTENSION, #UTILITY, or #GROUP) statement. The Template statements contained in this section control the utility execution process. Multiple #UTILITY sections are allowed in a single Template set.

The #UTILITY section is very similar to the #APPLICATION section, in that it allows you to produce output from the application. The purpose of #UTILITY is to provide extensible supplemental utilities for such things as program documentation, or a tree diagram of procedure calls. The list of registered utilities appears in the Utilities menu in the Clarion for Windows environment. #UTILITY with the WIZARD attribute specifies it contains a #SHEET with #TABs that display one tab at a time, guiding the user through the prompts.

```
#UTILITY(ProcCallTree, 'Output procedure call tree')
  #CREATE(%Application & '.TRE')
Procedure Call Tree: for %Application
#INSERT(%DisplayTree, %FirstProcedure, '', ' ')
#CLOSE
#!**************
#GROUP(%DisplayTree, %ThisProc, %Level, %NextIndent)
  #FIX(%Procedure, %ThisProc)
%Level+-%ThisProc (%ProcedureTemplate)
  #FOR(%ProcedureCalled)
    #IF(INSTANCE(%ProcedureCalled) = ITEMS(%ProcedureCalled))
#INSERT(%DisplayTree, %ProcedureCalled, %Level & %NextIndent, ' ')
    #ELSE
#INSERT(%DisplayTree, %ProcedureCalled, %Level & %NextIndent, '| ')
    #ENDIF
  #ENDFOR
```

## **#VALIDATE** (validate prompt input)

**#VALIDATE(** expression, message)

**#VALIDATE** Validates the data entered into the immediately preceding #PROMPT field.

expression The expression to use to validate the entered data.

message A string constant containing the error message to display if the data is invalid.

The **#VALIDATE** statement validates the data entered into the #PROMPT field immediately preceding the #VALIDATE. The *expression* is evaluated when the OK button is pressed on the Procedure Properties window. If the *expression* is false, the *message* is displayed to the programmer in a message box, and control is given to the #PROMPT field that immediately precedes the #VALIDATE. There may be multiple #VALIDATE statements following a #PROMPT to validate the entry.

#### Example:

See Also: #PROMPT

```
#PROMPT('Input Value, Even numbers from 100-200',@N3),%Value
#VALIDATE((%Value > 100) AND (%Value < 200),'Value must be between 100 and 200')
#VALIDATE((%Value % 2 = 0),'Value must be an even number')
#PROMPT('Screen Field',CONTROL),%SomeField
#PREPARE

#FIX(%Control,%SomeField)
#ENDPREPARE

#VALIDATE(%ControlType = 'LIST','Must select a list box')

#PROMPT('Select Change Date/Time Group:',FIELD(%Primary)), %ChangeDateGroup,REQ
#PREPARE
#FIX(%File,%Primary)
#FIX(%File,%Primary)
#FIX(%Field,%ChangeDateGroup)
#ENDPREPARE
#VALIDATE(%FieldType = 'GROUP','Change Date Group must be of type GROUP!')</pre>
```

## **#WHERE (define #CODE embed point availability)**

#WHERE( embeds )

**#WHERE** Limits the availability of a #CODE to only those specific embedded source code

points where the generated code would be appropriate.

embeds A comma-delimited list of #EMBED identifiers that specifies the embedded

source code points that may use the #CODE to generate source code.

The **#WHERE** statement limits the availability of a #CODE to only those #EMBED embedded source code points where the generated code would be appropriate. A single #CODE may contain multiple #WHERE statements to explicitly define all the valid #EMBED embedded source code points. All the #WHERE statements in a #CODE are evaluated to determine which embedded source code points have been specifically enabled.

The *embeds* list must contain individual #EMBED *identifiers* delimited by commas. It may also contain ranges of embed points in the form *FirstIdentifier..LastIdentifier*, also delimited by commas. The *embeds* list may contain both types in a "mix and match" manner to define all suitable embedded source code points.

#### Example:

```
#CODE(ChangeProperty,'Change control property')
#WHERE(%AfterWindowOpening..%CustomRoutines) #!Appropriate everywhere after window open
#PROMPT('Control to change',CONTROL),%MyField,REQ
#PROMPT('Property to change',@S20),%MyProperty,REQ
#PROMPT('New Value',@S20),%MyValue,REQ
%MyField(%MyProperty) = '%'MyValue
```

See Also: #EMBED ,##CODE ,##RESTRICT

## **#WINDOWS** (default window structures)

#### **#WINDOWS**

structures

#### **#ENDWINDOWS**

**#WINDOWS** Begins a default window data structure section.

structures Default APPLICATION or WINDOW structures.

**#ENDWINDOWS** Terminates the default window section.

The **#WINDOWS** structure contains default APPLICATION or WINDOW data structures for a procedure Template. The default window *structures* provide a starting point for the procedure's window design.

The #WINDOWS section may contain multiple *structures* which may be chosen as the starting point for the procedure's window design. If there is more than one window structure to choose from, the Application Generator displays a list of those *structures* available the first time the procedure's window is editted. The names of the windows which appear in the Application Generator's list comes from a preceding comment beginning with two exclamations and a right angle bracket (!!>).

If the procedure template contains a #DEFAULT procedure, there is no need for #WINDOWS, since the default window is already in the #DEFAULT. Therefore, the list does not appear when the window is first edited.

#### **Example:**

#### #WINDOWS

#ENDWINDOWS

# **#WITH (associate prompts with a symbol instance)**

#WITH( symbol , value )
prompts
#ENDWITH

**#WITH** Allows a set of prompts to be associated with a single instance of a

symbol (as specified by the value expression).

symbol A previously declared unique multi-valued template symbol.

value A string expression containing a unique value to add to the symbol.

prompts One or more #PROMPT statements whose values become dependent on

the value of the *symbol*. This may also contain #DISPLAY, #VALIDATE,

#ENABLE, and #BUTTON statements.

**#ENDWITH** Terminates the group of *prompts* associated with the #WITH symbol.

The **#WITH** statement adds a new instance to the *symbol* (as specified by the *value* expression) and makes the values of all the *prompts* dependent upon that instance. #WITH allows the same set of prompts, with the same prompt symbols, to be used more than once on the same screen.

#### **Example:**

#WITH(%ClassItem,'Default')
#INSERT(%ClassPrompts)
#ENDWITH

See Also: #PROMPT ,#VALIDATE ,#ENABLE ,#DISPLAY ,#BUTTON

# Built-in Template Procedures CALL (call a #GROUP as a function)

CALL( symbol [, parameters ] )

**CALL** Calls a #GROUP as a function.

symbol A symbol that names a #GROUP section in the current template set.

parameters The parameters passed to the #GROUP. Each parameter must be separated

by a comma. All parameters defined for the #GROUP must be passed; they

may not be omitted.

The **CALL** procedure places the return value from the #GROUP named by the *symbol* into the expression containing the CALL.

The *parameters* passed to the #GROUP fall into two categories: value-parameters and variable-parameters. Value-parameters are declared by the #GROUP as a user-defined symbol, while variable-parameters are declared by the #GROUP as a user-defined symbol with a prepended asterisk (\*). Either a symbol or an expression may be passed as a value-parameter. Only a symbol may be passed as a variable-parameter.

Return Data Type: STRING

#### **Example:**

```
#SET(%SomeGroup, CALL(%SelectAGroup)) #!Call %SelectAGroup to get a #GROUP name
#INVOKE(%SomeGroup) #!Insert either %TrueGroup or %FalseGroup

#GROUP(%SelectAGroup)
#IF (%SomeCondition)
#RETURN('%TrueGroup(Clarion)')
#ELSE
#RETURN('%FalseGroup(Clarion)')
#ENDIF
```

See Also: #GROUP, INVOKE, #RETURN, #CALL, #INVOKE

**Built-In Template Procedures** 

## **EXTRACT** (return attribute)

**EXTRACT(** string, attribute [, parameter])

**EXTRACT** Returns the complete form of the specified *attribute* from the property

string symbol.

string The symbol containing the properties to parse.

attribute A string constant or symbol containing the name of the property to

return.

parameter An integer constant or symbol containing the number of the property's

parameter to return. Zero (0) returns the entire parameter list (without

the attribute). If omitted, the attribute and all its parameters are

returned.

The **EXTRACT** procedure returns either the complete form of the specified *attribute* from the attribute *string* symbol, or just the specified *parameter*. This is useful if no built-in symbol exists for the particular attribute you need.

Return Data Type: STRING

Example:

#SET(%MySymbol,EXTRACT(%ControlStatement,'DROPID')) #!Return DROPID attribute
#SET(%MySymbol,EXTRACT(%ControlStatement,'DROPID',0)) #!Return all DROPID parameters

See Also: REPLACE

## **EXISTS** (return embed point existence)

EXISTS( symbol)

**EXISTS** Returns TRUE if the embedded source code point is available for use.

symbol The identifier symbol for a #EMBED embedded source code point.

The **EXISTS** procedure returns true ('1') if the embedded source code point is available for use, at design-time only. If the embedded source code point is not available for use, EXISTS returns false ("). An embedded source code point is available for use if the section containing it is being used. This means that all #EMBEDs in the #PROCEDURE section, and all #GROUP sections referenced in the #PROCEDURE, are always available. #EMBEDs in a #CONTROL, #CODE, or #EXTENSION section are available only if the section is being used.

Return Data Type: LONG

Example:

#IF(EXISTS(%CodeTemplateEmbed) = %True)
 !Generate some source
#ENDIF

# **FILEEXISTS** (return file existence)

FILEEXISTS(file)

**FILEEXISTS** Returns TRUE if the *file* is available on disk.

file An expression containing the DOS filename.

The **FILLEEXISTS** procedure returns true ('1') if the *file* is available on disk. If the *file* is not available, FILEEXISTS returns false (").

Return Data Type: LONG

#### Example:

#IF(FILEEXISTS(%SomeFile))
 #OPEN(%SomeFile)
 #READ(%SomeFile)
 !some source
#ENDIF

#### See Also:

**Built-In Template Procedures** 

## **FULLNAME** (return file path)

FULLNAME( file, [option])

**FULLNAME** Returns the fully qualified path of the specified *file* on disk.

file A string constant or expression containing the filename (including extension).

option An integer constant, variable, or expression that evaluates to a 2. Allows

FULLNAME to return the path where the file will be created.

The **FULLNAME** procedure returns the fully qualified path of the specified *file* on disk. If the optional parameter is used, FULLNAME will return the path where the file will be created.

Return Data Type: STRING

#### Example:

```
#RUNDLL('Process File','MyModule.DLL',FULLNAME(%ChosenFile))
#EQUATE(%WCFName, FULLNAME('WIZARD.WCF', 2))
```

#### See Also:

TAILNAME (extract file name from full path)

# **INLIST** (return item exists in list)

INLIST( item, symbol)

**INLIST** Returns the instance number of the *item* in the *symbol*.

item A string constant or symbol containing the name of the item to return.

symbol A multi-valued symbol that may contain the item.

The **INLIST** procedure returns the instance number of the *item* in the *symbol*. If the *item* is not contained in the *symbol*, INLIST returns zero (0).

Return Data Type: LONG

```
#IF(INLIST('?MyControl',%Control))
 !Generate some source
#ENDIF
```

# **INSTANCE**(return current instance number)

INSTANCE( symbol)

**INSTANCE** Returns the current instance number to which the *symbol* is fixed.

Symbol A multi-valued symbol.

The **INSTANCE** procedure returns the current instance number to which the *symbol* is fixed. If no #FIX or #FOR has been issued for the *symbol*, INSTANCE returns zero (0).

Return Data Type: LONG

Example:

#DELETE(%Control,INSTANCE(%Control)) #!Delete current instance

See Also:

## **INVOKE** (call a named #GROUP as a function)

INVOKE( symbol [, parameters ] )

**INVOKE** Calls a named #GROUP as a function.

symbol A symbol that contains the name of a #GROUP section in the current template set.

parameters The parameters passed to the #GROUP. Each parameter must be separated by a comma. All

parameters defined for the #GROUP must be passed; they may not be omitted.

The **INVOKE** procedure places the return value from the #GROUP named in the *symbol* into the expression containing the INVOKE.

The *parameters* passed to the #GROUP fall into two categories: value-parameters and variable-parameters. Value-parameters are declared by the #GROUP as a user-defined symbol, while variable-parameters are declared by the #GROUP as a user-defined symbol with a prepended asterisk (\*). Either a symbol or an expression may be passed as a value-parameter. Only a symbol may be passed as a variable-parameter.

Return Data Type: STRING

#### Example:

```
#SET(%SomeGroup,CALL(%SelectAGroup)) #!Call %SelectAGroup to get a #GROUP name
#SET(%AnotherGroup,INVOKE(%SomeGroup)) #!Call Selected Group for another #GROUP name
#INVOKE(%AnotherGroup) #!Insert either %DoTrueGroup or %DoFalseGroup

#GROUP(%SelectAGroup)
#IF (%SomeCondition)
#RETURN('%TrueGroup(Clarion)')

#ELSE
#RETURN('%FalseGroup(Clarion)')

#GROUP(%TrueGroup)
#RETURN('%DoTrueGroup(Clarion)')

#GROUP(%FalseGroup)
#RETURN('%DoFalseGroup(Clarion)')
```

See Also: #GROUP ,CALL ,#RETURN ,#CALL ,#INVOKE

# ITEMS (return multi-valued symbol instances)

ITEMS( symbol)

**ITEMS** Returns the number of instances contained by the *symbol*.

symbol A multi-valued symbol.

The **ITEMS** procedure returns the number of instances contained by the *symbol*.

Return Data Type: LONG

Example:

#DELETE(%Control,ITEMS(%Control)) #!Delete last instance

## **LINKNAME** (return mangled procedure name)

**LINKNAME(** prototype, [[classname], [interfacename], [parentInterfaceName]])

**LINKNAME** Returns the mangled procedure name for the linker.

Prototype A string constant or symbol containing the prorotype of the procedure as

it appears in the MAP.

class name A string constant or symbol containing the name of the class the

procedure is using.

interface name A string constant or symbol containing the name of the interface that the

class has implemented.

parentInterfaceName If a member procedure of an Interface does not exist in the Interface and

was inherited, then specify the parent Interface name where the method

is defined.

The **LINKNAME** procedure returns the mangled procedure name for the linker. If a *class name* or *interface name* is specified it should not be added as a parameter to the prototype.

Return Data Type: STRING

#### **Examples:**

```
%(LINKNAME(%Procedure & %Prototype)) @%ExpLineNumber
%[55](LINKNAME(%pClsMeth & %pClsMethProt & ',' & %pClsMethCallCon, %pClassName)) @?
%[55](LINKNAME(%pIMeth & %pIMethodPrototype & ',' & %pIMethodCallCon, %pCName, %pIface, %pIface
#SET(%ExpLine,LINKNAME('MyExportedFunc(long,string),long'))
#SET(%ExpLine,LINKNAME('MyMember(long,string),long','MyClass'))
#SET(%ExpLine,LINKNAME('MyIntMember(long,string),long','MyClass','MyInterface'))
```

See Also: Prototyper and Name Mangler

### **QUOTE** (template - replace string special characters)

QUOTE( symbol)

**QUOTE** 

Expands the *symbol's* string data, "doubling up" single quotes ('), and all unpaired left angle brackets (<) and left curly braces ({) to prevent compiler errors.

symbol

The symbol containing the properties to parse.

The **QUOTE** procedure returns the string contained in the symbol with all single quotes ('), unpaired left angle brackets (<), and un-paired left curly braces ({) "doubled up" to prevent compiler errors. This allows the user to enter string constants containing apostrophes, and filter expressions containing less than signs (<) without requiring that they enter two of each.

Return Data Type: STRING

Example:

#PROMPT('Filter Expression',@S255),%FilterExpression
#SET(%ValueConstruct,QUOTE(%FilterExpression)) #!Expand single quotes and angle brackets

See Also: UNQUOTE

# **REGISTERED** (return template registration)

REGISTERED( template )

**REGISTERED** Returns TRUE if the *template* is available for use.

template A string constant containing the name of the #PROCEDURE, #CONTROL,

#EXTENSION, #CODE, or #GROUP whose availability is in question.

The **REGISTERED** procedure returns true ('1') if the *template* is available for use, at design-time only. If the *template* is not available for use, REGISTERED returns false (").

Return Data Type: LONG

#### **Example:**

```
#IF(NOT REGISTERED('BrowseBox(Clarion)'))
  #ERROR('BrowseBox not registered')
#ENDIF
```

### **REPLACE** (replace attribute)

REPLACE( string, attribute, new value [, parameter ] )

**REPLACE** Finds the complete form of the specified *attribute* from the property

string symbol and replaces it with the new value.

string The symbol containing the properties to parse.

attribute A string constant or symbol containing the name of the property to

find.

new value A string constant or symbol containing the replacement value for the

attribute.

parameter An integer constant or symbol containing the number of the property's

parameter to affect. Zero (0) affects the entire parameter list (without

the attribute). If omitted, the attribute and all its parameters are

affected.

The **REPLACE** procedure replaces either the complete form of the specified *attribute* from the attribute *string* symbol, or just the specified *parameter* with the *new value*. It returns the modified *string*.

Return Data Type: STRING

**Example:** 

#SET(%ValueConstruct,REPLACE(%ValueConstruct,'MSG','')) #!Remove MSG attribute

See Also: EXTRACT

### **SEPARATOR** (return attribute string delimiter position)

SEPARATOR( string, start )

**SEPARATOR** Returns the position of the next comma in the attribute *string*.

String A string constant or symbol containing a comma delimited list of

attributes.

Start An integer constant or symbol containing the starting position from which

to seek the next comma.

The **SEPARATOR** procedure returns the position of the next comma in the attribute *string* from the *start* position. This procedure correctly processes nested quotes within the *string* so that commas in string constants do not cause it to return an incorrect position.

Return Data Type: LONG

Example:

#SET(%MySymbol,SEPARATOR(%ControlStatement,1)) #!Return first comma position

### **SLICE** (return substring from string)

SLICE( expression, start, end )

**SLICE** Returns a substring portion of the *expression* string.

expression A string constant, symbol, or expression containing the string from which to

return a substring portion.

start An integer constant or symbol containing the starting position (inclusive)

within the expression from which to extract the substring.

end An integer constant or symbol containing the ending position (inclusive) within

the expression from which to extract the substring.

The **SLICE** procedure returns the substring portion of the *expression* string identified by the *start* and *end* position values. This is equivalent to the Clarion language string slicing operation.

Return Data Type: STRING

Example:

#SET(%MySymbol,SLICE('ABCDE,2,4)) #!Return 'BCD'

See Also: Built-In Template Procedures

#### **SPLIT** (separate single line string to multiple lines)

SPLIT ( string [, splitcolumn ] [, indent ] )

SPLIT	Split a single comma delimited list of attributes to multiple lines
string	A string constant, template symbol or expression containing a comma delimited list of attributes.
splitcolumn	An integer constant, template symbol or expression that identifies what column to split the line at.
indent	An integer constant, template symbol or expression that designates the amount of spaces to indent on all lines generated after the first line.

**SPLIT** is used to divide a long string of comma delimited attributes into multiple lines. As each new line is created, they are connected using the line continuation (|) character, which is automatically generated. Lines are split near to the value of the *splitcolumn* column value (before or after) based on the Clarion syntax at that position. Subsequent lines are indented using the *indent* value to determine the number of leading spaces.

If the splitcolumn parameter is omitted, a default value of 90 is used.

If the *indent* parameter is omitted, a default value of 2 is used.

We need to clarify the term "comma delimited list of attributes" as used in SPLIT, UNSPLIT, EXTRACT, REPLACE and SEPARATOR functions. These functions assume that the *string* parameter has the following form:

```
[<label>] <attribute>,<attribute>,<attribute>, ...
```

In addition, each <attribute> has the following format:

```
<name>[([<parameter>],[<parameter>],...)]
```

<name> is an identifier, or an identifier with a leading # character or a string constant.
cparameter> is any valid expression.

The list of attributes may also have a leading <label>, which is an identifier, and separated from the first attribute by one or more whitespaces.

See Also: UNSPLIT, EXTRACT, REPLACE, SEPARATOR

### **TAILNAME** (extract file name from full path)

TAILNAME( symbol)

**TAILNAME** Extract a filename from a symbol, removing any path element.

symbol The symbol containing the filename to extract.

#! Generate the default install files ---

The **TAILNAME** function processes a full path and file name and removes the path part of the symbol. The returned string is its name and extension only. **TAILNAME** does not expand short names. This function is only available in template language usage.

Return Data Type: STRING

#### **Example:**

```
#CREATE(%WiseFile2)
Document Type: WSE
item: Global
    Version=7.0
    File Checksum=646309025
end
#INSERT(%InstFile, FULLNAME(%ProjectTarget), '%MAINDIR%\' & TAILNAME(%ProjectTarget), %WiseFile20
```

See Also: FULLNAME

### **UNQUOTE** (remove string special characters)

UNQUOTE( symbol)

**UNQUOTE** Contracts the *symbol's* string data, "singling up" doubled single quotes ("), and

all doubled un-paired left angle brackets (<<) and left curly braces ({{}).

symbol The symbol containing the properties to parse.

The **UNQUOTE** procedure returns the string contained in the symbol with all doubled single quotes ("), doubled un-paired left angle brackets (<<), and un-paired left curly braces ({{}}) "singled up" (returned to single instances instead of double instances of each character). This is the direct opposite to the QUOTE procedure.

Return Data Type: STRING

#### Example:

```
#PROMPT('Filter Expression',@S255),%FilterExpression
#SET(%ValueConstruct,QUOTE(%FilterExpression)) #!Expand single quotes and angle brackets
#SET(%SingledValue,UNQUOTE(%ValueConstruct)) #!Contract single quotes and angle brackets
```

See Also: QUOTE

**Built-In Template Procedures** 

### **UNSPLIT** (merge a multiple line string to single line)

UNSPLIT ( string )

**UNSPLIT** Merge a multiple line attribute string to a single line

string A string constant, template symbol or expression containing a comma

delimited list of attributes.

**UNSPLIT** is used to merge a multiple line attribute string to a single line.

If the *string* is split into multiple lines, and connected using the line continuation character ( | ), **UNSPLIT** merges all lines together into a single line. Some unneeded whitespaces between attributes may also be removed by **UNSPLIT**.

We need to clarify the term "comma delimited list of attributes" as used in SPLIT, UNSPLIT, EXTRACT, REPLACE and SEPARATOR functions. These functions assume that the *string* parameter has the following form:

```
[<label>] <attribute>,<attribute>,<attribute>, ...
```

In addition, each <attribute> has the following format:

```
<name>[([<parameter>],[<parameter>],...)]
```

<name> is an identifier, or an identifier with a leading # character or a string constant.
cparameter> is any valid expression.

The list of attributes may also have a leading <label>, which is an identifier, and separated from the first attribute by one or more whitespaces.

**UNSPLIT** is also useful when used in connection with **SEPARATOR**. Otherwise, if a *string* is long, the template must handle any possible line breaks.

**See Also:** SPLIT, SEPARATOR Built-In Template Procedures

# **VAREXISTS** (return symbol existence)

VAREXISTS( symbol)

**EXISTS** Returns TRUE if the *symbol* is available for use.

symbol The symbol whose existence is in question.

The **VAREXISTS** procedure returns true ('1') if the *symbol* is available for use, at design-time only. If the *symbol* is not available for use, VAREXISTS returns false (").

Return Data Type: LONG

Example:

#IF(NOT VAREXISTS(%MySymbol))
 #DECLARE(%MySymbol)
#ENDIF

See Also: #DECLARE

# **Additional Language Support**

In addition to the Built-In Template Procedure support, the following Clarion language statements may also be used in certain template statements:

ABS

**ACOS** 

**ADDRESS** 

AGE

ALL

**ASIN** 

ATAN

CENTER

**CHOOSE** 

CHR

CLIP

CLOCK

COS

DATE

DAY

**DEFORMAT** 

**EVALUATE** 

**FONTDIALOG** 

**FORMAT** 

**GETINI** 

**INLIST** 

**INRANGE** 

**INSTRING** 

INT

**LEFT** 

LEN

LOG<sub>10</sub>

**LOGE** 

LONGPATH

**LOWER** 

**MATCH** 

**MEMORY** 

MONTH

NUMERIC

**PATH** 

**PUTINI** 

**RANDOM** 

**RIGHT** 

**ROUND** 

SHORTPATH

SIN

**SQRT** 

**STRPOS** 

SUB

TAN

**TODAY** 

**UPPER** 

VAL

YEAR

#### Examples:

```
#IF(SUB(%SQLViewFieldAssignment, LEN(CLIP(%SQLViewFieldAssignment)), 1) ~=''')
#SET(%locType, CHOOSE(%GraphPointAction='Count','long','like(' & %GraphPointField & ')'))
SELF.Report $ %Ctrl{PROP:Text}=FORMAT(TODAY(), %DateStampFormat)
```

# Template Symbols

### **Symbol Overview**

The Clarion Template Language uses symbols which act as variables do in a programming language -- they contain information that can be used as-is or may be used in expressions. These symbols may come from the built-in symbol set, or can be defined by the template author. Both types may be single-valued or multi-valued.

The built-in symbols that are available to the Template writer contain information from both the Dictionary and the Application about how the programmer has designed the application. The template-defined symbols contain information provided by the programmer from prompts on the Application Generator's properties windows, or may only be for internal use.

All template symbols expand during source generation to place the value they contain in the generated source code (if included in template code that generates source).

See Also: Expansion Symbols ,Symbol Hierarchy Overview

#### **Expansion Symbols**

There are several special symbol forms that expand to allow formatting and special characters to generate into the source. These may be combined with each other to produce complex effects.

%% Expands to a single percent (%) sign. This allows the Application

Generator to generate the modulus operator without confusion with any

symbol.

%# Expands to a single pound (#) sign. This allows the Application

Generator to generate an implicit LONG variable without confusion with

any Template Language statement.

%@picture@symbol Formats the symbol with the specified picture when source generates.

For example, %@D1@MyDate expands the %MyDate symbol,

formatted for the @D1 picture.

%[number]symbol Expands the symbol to fill at least the number of spaces specified. This

allows proper comment and data type alignment in the generated

source.

%| Expands the next generated source onto the same line as the last. This

is the Template line continuation character. It is used to split code lines that are too long to fit on the page. In the template files on disk, these characters should not be used to continue a template code line; they

are used only for readability.

%'symbol Expands the symbol's string data, "doubling up" single quotes ('), and

all un-paired left angle brackets (<) and left curly braces ({) to prevent

compiler errors.

%(expression) Expands the expression into the generated source.

#### **Example:**

### **Symbol Hierarchy Overview**

The Built-in Symbols all form a hierarchy of dependencies. This hierarchy starts with %Application, upon which all the other built-in symbols are dependent. The following tree diagram does not show all the dependent symbols, but does graphically represent the hierarchy of symbols. Most of these are multi-valued symbols.

```
%Application
  %DictionaryFile
     %File
       %Field
       %Key
       %Relation
  %Program
  %GlobalData
  %Module
     %ModuleProcedure
     %MapItem
     %ModuleData
  %Procedure
     %Report
       %ReportControl
          %ReportControlField
     %Window
       %WindowEvent
       %Control
          %ControlEvent
     %ProcedureCalled
     %LocalData
     %ActiveTemplate
       %ActiveTemplateInstance
     %Formula
       %FormulaExpression
```

These symbols (and all the symbols not listed here that are dependent upon these) contain all the information about the application that is available in the data dictionary (.DCT) and application (.APP) files. They enable you to write a template to generate any type of code you require.

# **Built-in Symbols**Symbols Dependent on %Application

%Application The name of the .APP file. The hierarchy of built-in symbols

starts with %Application.

%ApplicationDebug Contains 1 if the application has debug enabled.

%ApplicationExternalLibrary Contains 1 if the application is using an external DLL Clarion

runtime library (CustomDII in the project).

%ApplicationLocalLibrary Contains 1 if the application is linking in the Clarion runtime

library.

%ApplicationTemplate The name of all global extension templates used in the

application. Multi-valued.

%ApplicationTemplateInstance The instance numbers of all global extension templates used

in the application. Multi-valued. Dependent on

%ApplicationTemplate.

%ApplicationTemplateInstanceDescription The description of global extension templates used in the

application. Dependent on %ApplicationTemplate.

%ApplicationTemplateParentInstance The instance number of the control template's parent global

extension template. This is the global extension template that

it is "attached" to. Dependent on %ApplicationTemplateInstance.

%ApplicationTemplatePrimaryInstance The instance number of the control template's primary global

extension template. This is the global extension template in a succession of multiple related global extension templates.

Dependent on %ApplicationTemplateInstance.

%CreateLocalMap Contains 1 if the application should create local MAP

structures instead of a single global MAP.

%DictionaryChanged Contains 1 if the .DCT file has changed since the last source

generation.

%DictionaryDateChanged The date dictionary was last changed (Clarion standard date).

%DictionaryDateCreated The dictionary creation date (Clarion standard date).

%DictionaryDescription A string containing a short description of the dictionary.

%DictionaryFile The name of the .DCT file used for the application.

%DictionaryQuickOptions A comma-delimited string containing the choices the user

made on the Options tab for the dictionary properties.

%DictionaryTimeChanged The time dictionary was last changed (Clarion standard time). %DictionaryTimeCreated The dictionary creation time (Clarion standard time). %DictionaryToolOptions A string containing the entries third-party tools have made in the TOOLOPTIONS section of the .TXD file for the dictionary. %DictionaryUserOptions A string containing the entries the user made in the User Options text box on the Options tab for the dictionary properties. %DictionaryVersion A string containing the current dictionary version and current revision number. This is stored in the format 'v.v r# where v.v is the version number and r# is the revision number. Example: '1.0 r1', '1.0 r10' %EditFilename The name of the temporary file that the procedure being edited in context is generated into. This symbol will be blank unless the file is being generated for the IDE Embeditor. Any code you wish generated only into the Embeditor can be tested using #IF (%EditProcedure). %EditProcedure The name of the procedure being edited in context. %File Contains all file declarations in the .DCT file. Multi-valued. Dependent on %DictionaryFile. %FirstProcedure The label of the application's first procedure. %GlobalData The labels of all global variable declarations made through the Global Data button on the Global Settings window. Multivalued. %GlobalDataID Same as %GlobalData Returns full identifiers of variables or fields %GlobalDataFull %GlobalDataInDictionary Contains 1 if the global variable is defined within the dictionary. Dependent on %GlobalData. %GlobalDataStatement The variable's declaration statement (data type and all attributes). Dependent on %GlobalData. %GlobalDataLast Contains 1 if the "Generate Last" option is set for %FileUsage = GLOBAL. Dependent on %GlobalData. %GlobalDataLevel The indent level for formatting complex data structures. Dependent on %GlobalData.

> A string containing the entries the user made in the User Options text box on the Options tab for the global data group

defined in the dictionary.

%GlobalDataUserOptions

%HelpFile The name of the application's help file.

%Module The names of all source code modules other than the

PROGRAM module. Multi-valued.

%Procedure The names of all procedures in the application. Multi-valued.

%Program The name of the PROGRAM module.

%ProgramDateChanged The date the program was last changed (a Clarion standard

date).

%ProgramDateCreated The program creation date (a Clarion standard date).

%ProgramExtension Contains EXE, DLL, or LIB.

%ProgramTimeChanged The time the program was last changed (a Clarion standard

time).

%ProgramTimeCreated The program creation time (Clarion standard time).

%ProjectNameSpace Default namespace set by the project types that support this

feature.

%ProjectTarget Contains the name of the file being produced.

%QuickProcedure The name of the procedure type a #UTILITY with the WIZARD

attribute is creating.

%RegistryChanged Contains 1 if the .TemplateRegistry.TRF file has changed

since the last source generation.

%Target32 Contains 1 if the application is producing a 32-bit program.

### Symbols Dependent on %File

%AliasFile The label of the ALIASed file.

%File Contains all file declarations in the .DCT file. Multi-valued.

Dependent on %DictionaryFile.

%Field The labels of all fields in the file (including MEMO fields). Multi-

valued.

%Key The labels of all keys and indexes for the file. Multi-valued.

<u>%Trigger</u> The names of all possible triggers in a file. Multi-Valued.

Possible values are

BEFORE\_INSERT

AFTER\_INSERT

BEFORE UPDATE

AFTER\_UPDATE

BEFORE DELETE

AFTER DELETE

BEFORE FETCH

AFTER\_FETCH
BEFORE CREATE
AFTER\_CREATE

%FileTriggerData The name of all variables declared in Trigger Common Data

%Relation The labels of all files that are related to the file. Multi-Valued.

{bmc blk2blue.bmp}

%File32BitOnly Contains 1 if the file can only be used in 32-bit applications.

%FileBindable Contains 1 if the file has the BINDABLE attribute.

%FileCreate Contains 1 if the file has the CREATE attribute.

%FileDescription A short description of the file.

%FileDriver Contents of the DRIVER attribute first parameter.

%FileDriverParameter Contents of the DRIVER attribute second parameter.

%FileEncrypt Contains 1 if the file has the ENCRYPT attribute.

%FileExternal Contains 1 if the file has the EXTERNAL attribute.

%FileExternalModule Contents of the file's EXTERNAL attribute parameter.

%FileIdent The internal file number assigned by the Dictionary Editor and

displayed in the IDENT in a .TXD file.

%FileLastModified Returns date and time file was last modified.

%FileLongDesc A long description of the file.

%FileName Contents of the FILE statement's NAME attribute.

%FileOEM Contains a 1 if the file has the OEM attribute.

%FileOwner Contents of the OWNER attribute.

%FilePrefix Contents of the PRE attribute (the file prefix).

%FilePrimaryKey The label of the file's primary key.

%FileQuickOptions A comma-delimited string containing the choices the user

made on the Options tab for the file.

%FileReclaim Contains 1 if the file has the RECLAIM attribute.

%FileStatement Contains the FILE statement's attributes (only).

%FileStruct The FILE statement (the label and all attributes).

%FileStructEnd The keyword END.

%FileStructRec The RECORD statement (including label and any attributes).

%FileStructRecEnd The keyword END.

%FileThreaded Contains 1 if the file has the THREAD attribute.

\*\*
WFileTriggerBeforeInsert Contains the contents of the trigger condition.

%FileTriggerAfterInsert Contains the contents of the trigger condition.

%FileTriggerBeforeUpdate Contains the contents of the trigger condition.

%FileTriggerAfterUpdate Contains the contents of the trigger condition.

%FileTriggerBeforeDelete Contains the contents of the trigger condition.

%FileTriggerAfterDelete Contains the contents of the trigger condition.

%FileTriggerDataInitialValue Contains the contents of the Initial Value of a Trigger Data

Element.

%FileType Contains FILE, VIEW, or ALIAS.

%FileUserOptions A string containing the entries the user made in the User Options text box on the Options tab for the file.

#### Symbols Dependent on %View

%ViewFile Contains the label of the file.

%ViewFileField Contains the label of the field in the file used in the VIEW. Dependent

on %ViewFileFields.

%ViewFileFields The labels of all fields in the file used in the VIEW. Multi-valued.

%ViewFiles The labels of all files in the VIEW. Multi-valued. Dependent on %File.

%ViewFileStruct The JOIN statement for a secondary file in the VIEW.

%ViewFileStructEnd The keyword END.

%ViewFilter Contents of the FILTER attribute.

%ViewJoinedTo The label of the file to which the file is JOINed.

%ViewPrimary The label of the VIEW's primary file.

%ViewPrimaryFields The labels of all fields in the VIEW from the primary file. Multi-valued.

%ViewPrimaryField Dependent on %ViewPrimaryFields. Contains the label of a field in the

VIEW from the primary file.

%ViewStatement The VIEW statement's attributes (only).

%ViewStruct The VIEW statement (including the label and all attributes).

%ViewStructEnd The keyword END.

#### **Symbols Dependent on %Field**

%Field The labels of all fields in the file (including MEMO fields). Multi-

valued.Dependent on %File.

%FieldIdent The internal field number assigned by the Dictionary Editor and

displayed in the IDENT in a .TXD file.

%FieldDescription A short description of the field.

%FieldLongDesc A long description of the field.

%FieldFile The label of the file containing the field.

%FieldID Label of the field without prefix.

%FieldDisplayPicture Default display picture.

%FieldRecordPicture STRING field storage definition picture.

%FieldDimension1 Maximum value of first array dimension.

%FieldDimension2 Maximum value of second array dimension.

%FieldDimension3 Maximum value of third array dimension.

%FieldDimension4 Maximum value of fourth array dimension.

%FieldHelpID Contents of the HLP attribute.

%FieldName Contents of the field's NAME attribute.

%FieldRangeLow The lower range of valid values for the field.

%FieldRangeHigh The upper range of valid values for the field.

%FieldType Data type of the field.

%FieldPlaces Number of decimal places for the field.

%FieldMemoSize Maximum size of the MEMO.

%FieldMemoImage Contains 1 if the MEMO has a BINARY attribute.

%FieldInitial Initial value for the field.

%FieldLookup File to access to validate this field's value.

%FieldStruct The field's declaration statement (label, data type, and all

attributes).

%FieldStatement The field's declaration statement (data type and all attributes).

%FieldHeader The field's default report column header.

%FieldPicture Default display picture.

%FieldJustType Contains L, R, C, or D for the field's justification.

%FieldJustIndent The justification offset amount.

%FieldFormatWidth The default width for the field's ENTRY control.

%FieldScreenControl The field's screen control as defined in the data dictionary.

Multi-valued. Use #FOR to extract this information. For

example:

#FOR(%FieldScreenControl)

%FieldScreenControl

#ENDFOR

%FieldScreenControlWidth Either the default from the runtime library, or the explicitly set

width in the data dictionary for the field's screen control.

Dependent on %FieldScreenControl.

%FieldScreenControlHeight Either the default from the runtime library, or the explicitly set

height in the data dictionary for the field's screen control.

Dependent on %FieldScreenControl.

%FieldReportControl The field's report control as defined in the data dictionary.

Multi-valued.

%FieldReportControlWidth Either the default from the runtime library, or the explicitly set

width in the data dictionary for the field's report control.

Dependent on %FieldReportControl.

%FieldReportControlHeight Either the default from the runtime library, or the explicitly set

height in the data dictionary for the field's report control.

Dependent on %FieldReportControl.

%FieldValidation The choice the user made on the Validity Checks tab for the

field. Can contain either NONZERO, INRANGE, BOOLEAN,

INFILE, or INLIST.

%FieldChoices The choices the user entered for a Must Be In List field

(%FieldValidation contains INLIST). Multi-valued.

%FieldValues The choices the user entered to override the VALUE attribute

for the %FieldChoices symbol. Multi-valued.

%FieldTrueValue The true choice the user entered to override the VALUE

attribute (%FieldValidation contains BOOLEAN).

%FieldFalseValue The false choice the user entered to override the VALUE

attribute (%FieldValidation contains BOOLEAN).

%FieldDisplayChoices The choices the user entered in the display override field for a

Must Be In List field (%FieldValidation contains INLIST). Multi-

valued.

%FieldQuickOptions A comma-delimited string containing the choices the user

made on the Options tab for the field.

%FieldUserOptions A string containing the entries the user made in the User

Options text box of the Options tab for the field.

%FieldToolOptions A string containing the entries third-party tools have made in

the TOOLOPTIONS section of the .TXD file for the field.

#### Symbols Dependent on %Key

%Key The labels of all keys and indexes for the file. Multi-valued.

%Keyldent The internal key number assigned by the Dictionary Editor and

displayed in the IDENT in a .TXD file.

%KeyDescription A short description of the key.

%KeyLongDesc A long description of the key.

%KeyFile The label of the file to which the key belongs.

%KeyID The label of the key (without prefix).

%KeyIndex Contains KEY, INDEX, or DYNAMIC.

%KeyName Contents of the key's NAME attribute.

%KeyAuto Contains the label of the auto-incrementing field.

%KeyDuplicate Contains 1 if the key has the DUP attribute.

%KeyExcludeNulls Contains 1 if the key has the OPT attribute.

%KeyNoCase Contains 1 if the key has the NOCASE attribute.

%KeyPrimary Contains 1 if the key is the file's primary key.

%KeyStruct The key's declaration statement (label and all attributes).

%KeyStatement The key's attributes (only).

%KeyField The labels of all component fields of the key. Multi-valued.

%KeyFieldSequence Contains ASCENDING or DESCENDING. Dependent on

%Keyfield.

%KeyQuickOptions A comma-delimited string containing the choices the user made

on the Options tab for the key.

%KeyUserOptions A string containing the entries the user made in the User Options

text box on the Options tab for the key.

%KeyToolOptions A string containing the entries third-party tools have made in the

TOOLOPTIONS section of the .TXD file for the key.

%KeyOrder The labels of all keys, indexes, and orders for the file. Multi-

valued.

%KeyOrderIdent The internal key number assigned by the Dictionary Editor and

displayed in the IDENT in a .TXD file.

%KeyOrderDescription A short description of the key.

#### Template Language Reference

%KeyOrderLongDesc A long description of the key.

%KeyOrderFile The label of the file to which the key belongs.

%KeyOrderID The label of the key (without prefix).

%KeyOrderIndex Contains KEY, INDEX, or DYNAMIC.

%KeyOrderName Contents of the key's NAME attribute.

%KeyOrderAuto Contains the label of the auto-incrementing field.

%KeyOrderDuplicate Contains 1 if the key has the DUP attribute.

%KeyOrderExcludeNulls Contains 1 if the key has the OPT attribute.

%KeyOrderNoCase Contains 1 if the key has the NOCASE attribute.

%KeyOrderPrimary Contains 1 if the key is the file's primary key.

%KeyOrderStruct The key's declaration statement (label and all attributes).

%KeyOrderStatement The key's attributes (only).

%KeyOrderQuickOptions A comma-delimited string containing the choices the user made

on the Options tab for the key.

%KeyOrderUserOptions A string containing the entries the user made in the User Options

text box on the Options tab for the key.

%KeyOrderToolOptions A string containing the entries third-party tools have made in the

TOOLOPTIONS section of the .TXD file for the key.

# **Symbols Dependent on %Trigger**

<u>%Trigger</u> <u>The names of all possible triggers in a file. Multi-Valued.</u>

Dependent on %File. Possible values are

BEFORE INSERT

AFTER INSERT

BEFORE UPDATE

AFTER UPDATE

BEFORE DELETE

AFTER\_DELETE
BEFORE\_FETCH

AFTER\_FETCH
BEFORE CREATE
AFTER\_CREATE

<u>%TriggerData</u> <u>The name of each variable in this trigger. Multi-Valued.</u>

<u>%TriggerSourceLine</u> <u>A line of source code in the trigger. Multi-Valued.</u>

<u>%TriggerLongDesc</u> <u>A long description of the trigger</u>

<u>%TriggerType</u> <u>A numeric representation of the trigger type. Possible values are:</u>

<u>Value</u>	Trigger Type
1	BEFORE_INSERT
2	AFTER_INSERT
<u>3</u>	BEFORE_UPDATE
4	AFTER_UPDATE
<u>5</u>	BEFORE_DELETE
<u>6</u>	AFTER_DELETE
<u>7</u>	BEFORE_FETCH
<u>8</u>	AFTER_FETCH
<u>9</u>	BEFORE_CREATE
<u>10</u>	AFTER_CREATE

### **Symbols Dependent on %TriggerData**

<u>%TriggerData</u> <u>The label of all variable in this trigger. Multi-Valued.</u>

Dependent on %Trigger

<u>%TriggerDataDescription</u> <u>A short description of the variable</u>

<u>%TriggerDataLongDesc</u> <u>A long description of the variable</u>

<u>%TriggerDataHeader</u> <u>The variable's default report column header.</u>

<u>%TriggerDataJustIndent</u> <u>The justification offset amount.</u>

<u>%TriggerDataJustType</u> <u>Contains L, R, C, or D for the variable's justification.</u>

<u>%TriggerDataFormatWidth</u> <u>The default width for the variable's ENTRY control.</u>

<u>%TriggerDataPicture</u> <u>Default display picture.</u>

%TriggerDataStatement The variable's declaration statement (data type and all

attributes).

<u>%TriggerDataUserOptions</u> <u>A string containing the entries the user made in the User</u>

Options text box of the Options tab for the variable.

# Symbols Dependent on %FileTriggerData

%FileTriggerData The label of all variable in the Trigger Common Data. Multi-

Valued. Dependent on %File

<u>%FileTriggerDataDescription</u> <u>A short description of the variable</u>

%FileTriggerDataLongDesc A long description of the variable

<u>%FileTriggerDataHeader</u> <u>The variable's default report column header.</u>

<u>%FileTriggerDataJustIndent</u> <u>The justification offset amount.</u>

<u>%FileTriggerDataJustType</u> <u>Contains L, R, C, or D for the variable's justification.</u>

<u>%FileTriggerDataFormatWidth</u> <u>The default width for the variable's ENTRY control.</u>

%FileTriggerDataPicture Default display picture.

%FileTriggerDataStatement The variable's declaration statement (data type and all

attributes).

%FileTriggerDataUserOptions A string containing the entries the user made in the User

Options text box of the Options tab for the variable.

#### **Symbols Dependent on %Relation**

%Relation The labels of all files that are related to the file. Multi-Valued.

%RelationPrefix The prefix of the related file.

%RelationAlias Contains the name of the file being aliased if the current file

named in %Relation is an alias.

%FileRelationType Contains 1:MANY or MANY:1.

%RelationKey The label of the related file's linking key.

%RelationPrimaryKey The label of the related file's primary key.

%FileKey The label of the file's linking key.

%RelationDriver The label of the related file's driver.

%RelationConstraintDelete May contain: RESTRICT, CASCADE, or CLEAR.

%RelationConstraintUpdate May contain: RESTRICT, CASCADE, or CLEAR.

%RelationKeyField The labels of all linking fields in the related file's key. Multi-

valued.

%RelationKeyFieldLink The label of the linking field in the file's key. Dependent on

%RelationKeyField.

%FileKeyField The labels of all linking fields in the file's key. Multi-valued.

%FileKeyFieldLink The label of the linking field in the related file's key. Dependent

on %FileKeyField.

%RelationQuickOptions A comma-delimited string containing the choices the user made

on the Options tab for the relation.

%RelationUserOptions A string containing the entries the user made in the User

Options text box on the Options tab for the relation.

%RelationToolOptions A string containing the entries third-party tools have made in

the TOOLOPTIONS section of the .TXD file for the relation.

#### Symbols Dependent on %Module

%Module The names of all source code modules other than the PROGRAM

module. Multi-valued

%ModuleDescription Contains the description of the module.

%ModuleLanguage Contains the module target language.

%ModuleTemplate The name of the Module Template used to generate the module.

%ModuleChanged Contains 1 if anything in the module has changed since the last

source generation.

%ModuleExternal Contains 1 if the module is external. (not generated by Clarion for

Windows).

%ModuleReadOnly Contains 1 if the module is read only.

%ModuleExtension The file extension for the module.

%ModuleBase The name of the module (without extension).

%ModuleInclude The file to INCLUDE in the program MAP containing the module's

prototypes.

%ModuleProcedure The names of all procedures in the module. Multi-valued.

%ModuleData The labels of all module variable declarations made through the

Data button on the Module Properties window. Multi-valued.

%ModuleDataID Same as %ModuleData

%ModuleDataFull Returns full identifiers of variables or fields. For fields inside

compound structures with prefixes %ModuleDataFull return

prefixed field identifiers.

%ModuleDataStatement The variable's declaration statement (data type and all attributes).

Dependent on %ModuleData.

%ModuleDataUserOptions A string containing the entries the user made in the User Options

text box on the Options tab for the variable. Dependent on

%ModuleData.

#### **Symbols Dependent on %Procedure**

The following symbols are in alphabetical order:

%ActiveTemplate

The names of all control templates used in the procedure. Multi-valued. Dependent on %Procedure.

The names are in the format

"MyTemplateName(MyChainName)" [with the double quotes], where "MyChainName" is the name used in

the #TEMPLATE that contains the "MyTemplateName" template.

%ActiveTemplateInstance The instance numbers of all control templates used in

the procedure. Multi-valued. Dependent on

%ActiveTemplate.

%ActiveTemplateInstanceDescription The description of the control template. Dependent

on %ActiveTemplateInstance.

%ActiveTemplateOwnerInstance The instance number of the extension template which

auto-populated the current extension template into a procedure through use of the parameter to the APPLICATION attribute on a #EXTENSION

statement. Dependent on %ActiveTemplateInstance.

%ActiveTemplateParentInstance The instance number of the control template's parent

control template. This is the control template that it is

"attached" to. Dependent on %ActiveTemplateInstance.

%ActiveTemplatePrimaryInstance The instance number of the control template's

primary control template. This is the first control template in a succession of multiple related control templates. Dependent on %ActiveTemplateInstance.

%ActiveTemplateType The type of all control templates used in the

procedure. Multi-valued. Dependent on

%ActiveTemplate. Returns CODE, EXTENSION or

CONTROL.

%LocalData The labels of all local variable declarations made

through the Data button on the Procedure Properties window. Multi-valued. Dependent on %Procedure.

%LocalDataID Same as %LocalData

%LocalDataFull Returns full identifiers of variables or fields. For fields inside compound structures with prefixes %LocalDataFull returns prefixed field identifiers. %LocalDataStatement The variable's declaration statement (data type and all attributes). Dependent on %LocalData. %LocalDataDescription A short description of the field. Dependent on %LocalData. %LocalDataHeader The field's default report column header. Dependent on %LocalData. %LocalDataPicture Default display picture. Dependent on %LocalData. %LocalDataJustType Contains L, R, C, or D for the field's justification. Dependent on %LocalData. %LocalDataJustIndent The justification offset amount. Dependent on %LocalData. %LocalDataFormatWidth The default width for the field's ENTRY control. Dependent on %LocalData. %LocalDataUserOptions A string containing the entries the user made in the User Options text box on the Options tab for the local variable. Dependent on %LocalData. %Procedure The names of all procedures in the application. Multivalued. %ProcedureToDo Contains 1 if the procedure is "ToDo." Dependent on %Procedure. %ProcedureType Contains PROCEDURE or FUNCTION. Dependent on %Procedure. The data type returned, if the procedure is a %ProcedureReturnType FUNCTION. Dependent on %Procedure. %ProcedureDateCreated The procedure creation date (a Clarion standard date). Dependent on %Procedure. %ProcedureDateChanged The date the procedure was last changed (a Clarion standard date). Dependent on %Procedure. %ProcedureTimeCreated The time the procedure was created (a Clarion standard time). Dependent on %Procedure. The time the procedure was last changed (a Clarion %ProcedureTimeChanged standard time). Dependent on %Procedure. %ProcedureReadOnly Contains 1 if the procedure is read only. Dependent on %Procedure.

%ProcedureIsGlobal Contains 1 if the procedure is to be declared in the

global MAP. Dependent on %Procedure.

%Prototype The procedure's prototype for the MAP structure.

Dependent on %Procedure.

%ProcedureTemplate The name of the Procedure Template used to

generate the procedure. Dependent on %Procedure.

%ProcedureDescription A short description of the procedure. Dependent on

%Procedure.

%ProcedureCategory The procedure's category. Dependent on

%Procedure.

%ProcedureExported Contains 1 if the procedure is in a DLL and is

callable from outside the DLL. Dependent on

%Procedure.

%ProcedureLongDescription A long description of the procedure. Dependent on

%Procedure.

%ProcedureLanguage The target language the procedure template

generates. Dependent on %Procedure.

%ProcedureCalled The names of all procedures listed by the Procedures

button on the Procedure Properties window. Multi-

valued. Dependent on %Procedure.

## **Window Control Symbols**

%Window The label of the procedure's window. Dependent on %Procedure.

%WindowStatement The WINDOW or APPLICATION declaration statement (and all

attributes). Dependent on %Window.

%MenuBarStatement The MENUBAR declaration statement (and all attributes).

Dependent on %Window.

%ToolbarStatement The TOOLBAR declaration statement (and all attributes).

Dependent on %Window.

%WindowEvent All field-independent events, as listed in the EQUATES.CLW file

(without EVENT: prepended). Multi-valued. Dependent on

%Window.

%Control The field equate labels of all controls in the window. Multi-valued.

Dependent on %Window.

%ControlUse The control's USE variable (not field equate). Dependent on

%Control.

%ControlStatement The control's declaration statement (and all attributes). This may

contain multiple lines of code if the declaration is too long to fit on

a single line. Dependent on %Control.

%ControlUnsplitStatement The control's declaration statement (and all attributes) without

line spliting. Dependent on %Control.

%ControlType The type of control (MENU, ITEM, ENTRY, BUTTON, etc.).

Dependent on %Control.

%ControlTemplate The name of the control template which populated the control

onto the window. Dependent on %Control.

%ControlTool Contains 1 if the control is in a TOOLBAR. Dependent on

%Control.

%ControlParent Contains the field equate label of the control's parent, if it is in a

control structure (OPTION, GROUP, etc.). Dependent on

%Control.

%ControlParentType Contains the type of control of the control's parent, if it is in a

control structure (OPTION, GROUP, etc.). Dependent on

%ControlParent.

%ControlParentTab Contains the field equate label of the TAB on which the control

has been placed. Dependent on %Control.

%ControlParameter The control's parameter (the value ion the parentheses).

Dependent on %Control.

%ControlHasIcon Contains 1 if the LIST or COMBO control contains any icon attributes. Dependent on %Control. %ControlHasColor Contains 1 if the LIST or COMBO control contins any color attributes. Dependent on %Control. %ControlHasStyle Contains 1 if the LIST or COMBO control contains any style attributes. Dependent on %Control. %ControlHasTip Contains 1 if the LIST or COMBO control contains any tool tip attributes. Dependent on %Control. %ControlHasTree Contains 1 if the LIST or COMBO control contains any tree attributes. Dependent on %Control. %ControlDefaultWidth The control's estimated default width. Dependent on %Control. %ControlDefaultHeight The control's estimated default height. Dependent on %Control. Contains 1 if the control is in a MENUBAR. Dependent on %ControlMenu %Control. %ControlToolBar Contains the TOOLBAR declaration statement (and all attributes) if the control is the first control in a toolbar. Dependent on %Control. %ControlMenuBar Contains the MENUBAR declaration statement (and all attributes) if the control is the first control in a menu. Dependent on %Control. %ControlIndent The control declaration's indentation level in the generated data structure. Dependent on %Control. %ControlInstance The instance number of the control template which populated the control onto the window. Dependent on %Control. %ControlOriginal The original field equate label of the control as listed in the control template from which it came. Dependent on %Control. %ControlFrom The FROM attribute of a LIST or COMBO control. Dependent on %Control. %ControlAlert All ALRT attributes for the control. Multi-valued. Dependent on %Control. %ControlEvent All field-specific events appropriate for the control, as listed in the EQUATES.CLW file (without the EVENT: prepended). Multivalued. Dependent on %Control. %ControlField All fields populated into the LIST, COMBO, or SPIN control. Multi-valued. Dependent on %Control. %ControlFieldHasIcon Contains 1 if the field in the LIST or COMBO control is formatted to have an icon. Dependent on %ControlField.

%ControlFieldHasColor	Contains 1 if the field in the LIST or COMBO control is formatted to have colors. Dependent on %ControlField.
%ControlFieldHasTree	Contains 1 if the field in the LIST or COMBO control is formatted to be a tree. Dependent on %ControlField.
%ControlFieldHasLocator	Contains 1 if the field in the LIST or COMBO control is formatted to be a locator. Dependent on %ControlField.
%ControlFieldHasTip	Contains 1 if the field in the LIST or COMBO control is formatted to have a tool tip. Dependent on %ControlField.
%ControlFieldDefaultTip	A string value that contains value of the column default tip if it is given, or an empty string otherwise.
%ControlFieldPicture	Contains the picture token of the field in the LIST or COMBO control. Dependent on %ControlField.
%ControlFieldHeader	Contains the heading text of the field in the LIST or COMBO control. Dependent on %ControlField.
%ControlFieldFormat	Contains the portion of the FORMAT attribute string that applies to the field in the LIST or COMBO control. Dependent on %ControlField.

## **Report Control Symbols**

%Report The label of the procedure's report. Dependent on %Procedure.

%ReportStatement The REPORT declaration statement (and all attributes). Dependent on

%Report.

%ReportControl The field equate labels of all controls in the report. Multi-valued.

Dependent on %Report.

%ReportControlUse The control's USE variable (not field equate). Dependent on

%ReportControl.

%ReportControlStatement The control's declaration statement (and all attributes). Dependent on

%ReportControl.

%ReportControlType The type of control (STRING, IMAGE, LIST, TEXT, etc.). Dependent on

%ReportControl.

%ReportControlTemplate The name of the control template which populated the control onto the

report. Dependent on %ReportControl.

%ReportControlIndent The control declaration's indentation level in the generated data structure.

Dependent on %ReportControl.

%ReportControlInstance The instance number of the control template which populated the control

onto the report. Dependent on %ReportControl.

%ReportControlOriginal The original field equate label of the control as listed in the control

template from which it came. Dependent on %ReportControl.

%ReportControlLabel The label of the report STRING control. Dependent on %ReportControl.

%ReportControlField All fields populated into the LIST, COMBO, or SPIN control. Multi-valued.

Dependent on %ReportControl.

# **Formula Symbols**

%Formula The label of the result field for each formula. Multi-valued. Dependent on

%Procedure.

%FormulaDescription A description of the formula.

%FormulaClass An identifier for the position in generated source to place the formula.

%FormulaInstance The control template instance number for a formula whose class has been

declared in a control template.

%FormulaExpression The expression to conditionally evaluate or assign to the result field for

each formula. Multi-valued. Dependent on %Formula.

%FormulaExpressionType Contains =, IF, ELSE, CASE, or OF. Dependent on %FormulaExpression.

%FormulaExpressionTrue Contains the line number of the true expression in the generated formula.

Dependent on %FormulaExpression.

%FormulaExpressionFalse Contains the line number of the false expression in the generated formula.

Dependent on %FormulaExpression.

%FormulaExpressionOf Contains the line number of the OF expression in the generated formula.

Dependent on %FormulaExpression.

%FormulaExpressionCase Contains the line number of the assignment in the generated formula.

Dependent on %FormulaExpression.

## **File Schematic Symbols**

%Primary The label of a Primary file listed in the procedure's Data / Tables Pad for

the procedure or a control template used in the procedure.

%PrimaryKey The label of the access key for the primary file. Dependent on %Primary.

%PrimaryInstance The control template instance number for which the file is primary.

Dependent on %Primary.

%Secondary The labels of all Secondary files listed in the Data / Tables Pad for the

procedure or a control template used in the procedure. Multi-valued.

Dependent on %Primary.

%SecondaryTo The label of the Secondary or Primary file to which the Secondary file is

related (thefile above it as listed in the procedure's Data / Tables Pad).

Dependent on %Secondary.

%SecondaryType Contains 1:MANY or MANY:1. Dependent on %Secondary.

%SecondaryCustomJoin Contains 1 if the JOIN is a custom join. Dependent on %Secondary.

%SecondaryCustomText Contains the text defining the custom join. Dependent on %Secondary.

%SecondaryInner Contains a 1 if the custom relationship uses an INNER join.

%OtherFiles The labels of all Other Data files listed for the procedure. Multi-valued.

## **File Driver Symbols**

%Driver The names of all registered file drivers.

%DriverDLL The name of the driver's .DLL file. Dependent on %Driver.

%DriverLIB The name of the driver's .LIB file. Dependent on %Driver.

%DriverDescription A description of the file driver. Dependent on %Driver.

%DriverCreate Contains 1 if the driver supports the CREATE attribute. Dependent on

%Driver.

%DriverOwner Contains 1 if the driver supports the OWNER attribute. Dependent on

%Driver.

%DriverEncrypt Contains 1 if the driver supports the ENCRYPT attribute. Dependent on

%Driver.

%DriverReclaim Contains 1 if the driver supports the RECLAIM attribute. Dependent on

%Driver.

%DriverMaxKeys The maximum number of keys the driver supports for each data file.

Dependent on %Driver.

%DriverUniqueKey Contains 1 if the driver supports unique (no DUP attribute) keys.

Dependent on %Driver.

%DriverRequired Contains 1 if the driver supports the OPT attribute. Dependent on %Driver.

%DriverMemo Contains 1 if the driver supports MEMO fields. Dependent on %Driver.

%DriverBinMemo Contains 1 if the driver supports the BINARY attribute on MEMO fields.

Dependent on %Driver.

%DriverSQL Contains 1 if the driver is an SQL driver. Dependent on %Driver.

%DriverOEM Contains 1 if the driver supports the OEM attribute. Dependent on

%Driver.

%DriverType All data types supported by the driver. Multi-valued. Dependent on

%Driver.

%DriverOpcode All operations supported by the driver. Multi-valued. Dependent on

%Driver.

## **Miscellaneous Symbols**

%BytesOutput Contains the number of bytes written to the current output file. This can be used

to detect empty embed points (if no bytes were written, it contained nothing).

%CommentColumn Contains the column where comments (#<) are generated.

%ConditionalGenerate Contains 1 if the Conditional Generation box is checked on the Application

Options window.

%CWRoot Contains the value of the "Root" key found in the CW section of the WIN.INI file.

%CWVersion Contains the current version release number of Clarion for Windows. For

example, for the first release of version 2.0, this contains 2000.

%EmbedID Contains the current embed point's identifying symbol.

%EmbedDescription The current embed point's description.

%EmbedParameters The current embed point's current instance, as a comma-delimited list.

%EOF Contains the value that flags the end of file when reading a file with #READ.

%False Contains an empty string (").

%Null Contains nothing. This is used for comparison to detect empty symbols.

%OutputOffset Same as %BytesOutput.

%OutputIndent Contains the implicit indentation level.

%OutputColumn Current column in the output file. Could be used for aligning to different columns.

%True Contains 1.

%UtilityArguments Set to the parameter when executing a Utility template from a DDE call.

%Win32 Contains 1 if #RUNDLL with the WIN32 attribute can be executed.

## **Annotated Examples**

## **Procedure Template: Window**

The *Window* Procedure template is the generic template that creates any window handling procedure. Since most (if not all) procedures in a Windows application have a window, the type of code this template generates forms the basis of the generated source code for most procedures.

The Window template is also the fundamental template upon which all the other Procedure templates are built. For example, the Browse template is actually a Window template with BrowseBox and BrowseUpdateButtons Control templates pre-defined for the procedure.

The following template language code is all the code for the Window Template:



For this and all other code examples in this book, the template line continuation character (%|) is used to split code lines that are too long to fit on the page. In the template files on disk these characters are not (and should not be) used to continue a template code line; they are used here only for readability. These templates are from the Clarion template chain, not ABC.

```
#PROCEDURE(Window, 'Generic Window Handler'), WINDOW, HLP('~TPLProcWindow')
#LOCALDATA
LocalRequest
                     LONG, AUTO
OriginalRequest
                     LONG, AUTO
LocalResponse
                     LONG, AUTO
WindowOpened
                     LONG
WindowInitialized
                     LONG
ForceRefresh
                     LONG, AUTO
#ENDLOCALDATA
#CLASS('Procedure Setup','Upon Entry into the Procedure')
#CLASS('Before Lookups', 'Refresh Window ROUTINE, before lookups')
#CLASS('After Lookups', 'Refresh Window ROUTINE, after lookups')
#CLASS('Procedure Exit', 'Before Leaving the Procedure')
#PROMPT('&Parameters:', @s255), %Parameters
#ENABLE (%ProcedureType='FUNCTION')
  #PROMPT('Return Value:',FIELD),%ReturnValue
#ENDENABLE
#PROMPT('Window Operation Mode:',DROP('Use WINDOW setting|Normal|MDI|Modal')) % |
         ,%WindowOperationMode
#ENABLE (%INIActive)
  #BOXED('INI File Settings')
    #PROMPT('Save and Restore Window Location',CHECK) %|
             ,%INISaveWindow,DEFAULT(1),AT(10,,150)
  #ENDBOXED
#ENDENABLE
#AT(%CustomGlobalDeclarations)
  #INSERT (%StandardGlobalSetup)
#INSERT (%StandardWindowCode)
```

This code starts with the #PROCEDURE statement, which names the Procedure template and indicates that it will have a WINDOW (or APPLICATION) structure, but no REPORT. The #LOCALDATA section defines six local variables that generate automatically as part of the procedure. These are common local variables for most generated procedures.

The #CLASS statements define the formula classes for the Formula Editor. These identify the source code positions at which formulas generate.

The #PROMPT statements create the prompts on the **Procedure Properties** window. The first allows the programmer to name the parameters passed into the procedure. The #ENABLE structure enables its #PROMPT only when the %ProcedureType symbol contains "FUNCTION." This occurs only when the **Prototype** prompt (standard on all procedures) contains a procedure prototype with a return data type.

The next #PROMPT allows the programmer to override the window's operation mode as specified on the WINDOW structure. The next #ENABLE structure enables its #BOXED #PROMPT only when the %INIActive symbol contains a value. This symbol comes from a check box on the Global Settings window.

The #AT structure calls the %StandardGlobalSetup #GROUP. This contains code to determine if the procedure is using any .VBX controls. It so, they are added to the list of files to ship with the application that generates into the *ProgramName*.SHP file.

You will note that none of these statements generates any target language (Clarion) source code other than the six variable declarations. The last #INSERT statement places all the code the %StandardWindowCode #GROUP generates at the end of these statements. This is the #GROUP that handles all the source generation for the template.

**See Also:** %StandardWindowCode #GROUP, %StandardWindowHandling #GROUP, %StandardAcceptedHandling #GROUP, %StandardControlHandling #GROUP

#### %StandardWindowCode #GROUP

This #GROUP actually generates all the source code for the Window template. This includes all the local data declarations, standard window handling code, and provides all the "hooks" for all the control and extension templates to attach into the generated procedure.

```
#GROUP (%StandardWindowCode)
#IF(NOT %Window)
  #ERROR(%Procedure & ' Error: No Window Defined!')
  #RETURN
#ENDIF
#DECLARE (%FirstField)
#DECLARE (%LastField)
#DECLARE (%ProgressWindowRequired)
#INSERT(%FieldTemplateStandardButtonMenuPrompt)
#INSERT(%FieldTemplateStandardEntryPrompt)
#INSERT(%FieldTemplateStandardCheckBoxPrompt)
#EMBED(%GatherSymbols,'Gather Template Symbols'),HIDE
#INSERT (%FileControlInitialize)
%Procedure %ProcedureType%Parameters
#FOR(%LocalData)
%[20]LocalData %LocalDataStatement
#ENDFOR
#INSERT (%StandardWindowGeneration)
#IF(%ProgressWindowRequired)
#INSERT (%StandardProgressWindow)
#ENDIF
  CODE
  PUSHBIND
  #EMBED(%ProcedureInitialize, 'Initialize the Procedure')
  LocalRequest = GlobalRequest
  OriginalRequest = GlobalRequest
  LocalResponse = RequestCancelled
  ForceRefresh = False
  CLEAR (GlobalRequest)
  CLEAR (GlobalResponse)
  #EMBED(%ProcedureSetup,'Procedure Setup')
  IF KEYCODE() = MouseRight
    SETKEYCODE (0)
  #INSERT(%StandardFormula,'Procedure Setup')
  #INSERT(%FileControlOpen)
  #INSERT(%StandardWindowOpening)
  #EMBED(%PrepareAlerts,'Preparing Window Alerts')
  #EMBED(%BeforeAccept,'Preparing to Process the Window')
  #MESSAGE('Accept Handling',3)
  ACCEPT
    #EMBED(%AcceptLoopBeforeEventHandling,'Accept Loop, Before CASE EVENT() handling')
    CASE EVENT()
    #EMBED(%EventCaseBeforeGenerated,'CASE EVENT() structure, before generated code')
    #INSERT (%StandardWindowHandling)
    #EMBED(%EventCaseAfterGenerated,'CASE EVENT() structure, after generated code')
    #EMBED(%AcceptLoopAfterEventHandling,'Accept Loop, After CASE EVENT() handling')
    #SUSPEND
    #?CASE ACCEPTED()
    #INSERT (%StandardAcceptedHandling)
    #?END
    #RESUME
```

```
#EMBED(%AcceptLoopBeforeFieldHandling,'Accept Loop, Before CASE FIELD() handling')
   #SUSPEND
   #?CASE FIELD()
   #EMBED(%FieldCaseBeforeGenerated,'CASE FIELD() structure, before generated code')
   #INSERT(%StandardControlHandling)
   #EMBED(%FieldCaseAfterGenerated,'CASE FIELD() structure, after generated code')
   #?END
   #RESUME
    #EMBED(%AcceptLoopAfterFieldHandling,'Accept Loop, After CASE FIELD() handling')
 END
 DO ProcedureReturn
1-----
ProcedureReturn ROUTINE
!| This routine provides a common procedure exit point for all template
!| generated procedures.
! 1
!| First, all of the files opened by this procedure are closed.
! |
!| Next, if it was opened by this procedure, the window is closed.
! [
!| Next, GlobalResponse is assigned a value to signal the calling procedure
! | what happened in this procedure.
1 |
!| Next, we replace the BINDings that were in place when the procedure initiali
zed
!| (and saved with PUSHBIND) using POPBIND.
! |
#IF(%ReturnValue)
!| Finally, we return to the calling procedure, passing %ReturnValue back.
#ELSE
!| Finally, we return to the calling procedure.
#ENDIF
! |
 #INSERT(%FileControlClose)
 #INSERT (%StandardWindowClosing)
 #EMBED(%EndOfProcedure,'End of Procedure')
 #INSERT(%StandardFormula,'Procedure Exit')
 IF LocalResponse
   GlobalResponse = LocalResponse
 ELSE
   GlobalResponse = RequestCancelled
 END
 POPBIND
 #IF(%ProcedureType='FUNCTION')
 RETURN (%ReturnValue)
 #ELSE
 RETURN
  #ENDIF
InitializeWindow ROUTINE
!| This routine is used to prepare any control templates for use. It should be called
!| once per procedure.
! |
 #EMBED(%WindowInitializationCode,'Window Initialization Code')
 DO RefreshWindow
RefreshWindow ROUTINE
```

```
!| This routine is used to keep all displays and control templates current.
 IF %Window(Prop:AcceptAll) THEN EXIT.
 #EMBED(%RefreshWindowBeforeLookup,'Refresh Window routine, before lookups')
 #INSERT(%StandardFormula,'Before Lookups')
 #INSERT (%StandardSecondaryLookups)
 #INSERT(%StandardFormula,'After Lookups')
 #EMBED(%RefreshWindowAfterLookup,'Refresh Window routine, after lookups')
 #EMBED(%RefreshWindowBeforeDisplay,'Refresh Window routine, before DISPLAY()')
 DISPLAY()
 ForceRefresh = False
!-----
SyncWindow ROUTINE
 #EMBED(%SyncWindowBeforeLookup,'Sync Record routine, before lookups')
 #INSERT(%StandardFormula,'Before Lookups')
 #INSERT(%StandardSecondaryLookups)
 #INSERT(%StandardFormula,'After Lookups')
 #EMBED(%SyncWindowAfterLookup,'Sync Record routine, after lookups')
1-----
#EMBED(%ProcedureRoutines,'Procedure Routines')
#EMBED(%LocalProcedures,'Local Procedures'),HIDE
```

This starts with the required #GROUP statement which identifies the group for use in #INSERT statements.

The #IF(NOT %Window) error check detects whether the programmer has forgotten to create a window for the procedure. The #ERROR statement alerts the programmer to the mistake and #RETURN immediately aborts any further source generation for the procedure. The #DECLARE statements declare two template symbols for internal use by other #GROUPs that are called to generate source for the procedure, and a "flag" that determines whether a "progress" window is required by the procedure.

The next three #INSERT statements insert #GROUPs that contain #FIELD structures to define the standard prompts that appear on the **Actions** tab for BUTTON, ENTRY and CHECK controls placed on the procedure's window. These prompts allow the programmer to specify the standard actions these controls can take from this procedure.

The %GatherSymbols #EMBED statement has the HIDE attribute. This means that it will not appear in the list of available embed points for the programmer to insert code, making the embed point only available for internal use (for Code, Control, or Extension templates to generate code into).

The #INSERT(%FileControllnitialize) statement inserts a #GROUP that updates the symbols that keep track of the files used in the application with the files used by this procedure.

The %Procedure %ProcedureType%Parameters statement generates the first Clarion language source code for the procedure. It generates the procedure's PROCEDURE statement, with or without a parameter list, as appropriate.

The #FOR(%LocalData) loop generates all the local variable declarations for the procedure. The %[20]LocalData syntax means that the %LocalData symbol expands to fill at least 20 spaces before the %LocalDataStatement symbol expands. This aligns the data types for each variable declaration starting in column 22.

The #INSERT(%StandardWindowGeneration) statement generates the procedure's WINDOW or APPLICATION data structure. This #GROUP also contains two #EMBED statements that allow the programmer to embed code either before or after the window structure.

The #IF(%ProgressWindowRequired) statement conditionally #INSERTs the %StandardProgressWindow group, which generates the ProgressWindow WINDOW structure for the procedure.

Next, the CODE statement generates, to begin the procedure's executable code section, which starts with a PUSHBIND statement to eliminate any BIND scoping problems. The %ProcedureInitialize #EMBED statement is the first programmer-available embed point in the executable code portion of the procedure.

The next six Clarion language statements are directly generated into the procedure to set it up for the action it should perform, as signaled to the procedure through the GlobalRequest variable. The %ProcedureSetup #EMBED statement is the next programmer-available embed point in the executable code portion of the procedure.

The IF KEYCODE() = MouseRight structure detects when the procedure has been called as a result of a RIGHT-CLICK popup menu. If so, it ensures that the keycode is cleared to prevent multiple execution.

The %StandardFormula #INSERT statement generates all the "Procedure Setup" class formulas. Following that, the #INSERT(%FileControlOpen) generates the code to open all the files used in the procedure (if they are not already open). This #GROUP also contains two #EMBED statements that allow the programmer to embed code either before or after the files are opened.

The #INSERT(%StandardWindowOpening) generates the OPEN(window) statement, and the .INI file handling code (if the programmer has checked the **Use .INI file to save and restore program settings** box). This #GROUP also includes two #EMBED statements that allow the programmer to embed code either before or after opening the window.

The next two #EMBED statements allow the programmer to embed code before entering the procedure's ACCEPT loop. #MESSAGE displays its message during source generation.

The ACCEPT loop is Clarion's event handling structure. The next #EMBED (%AcceptLoopBeforeEventHandling) allows the programmer to add code that will be the first to "see" any event that ACCEPT passes on. The CASE EVENT() structure contains all the code to handle field-independent events, generated from the #INSERT(%StandardWindowHandling) statement. This #GROUP is discussed in detail in its own section. The two #EMBED statements that surround this #INSERT and the one following the CASE EVENT structure all give the programmer the opportunity to explicitly handle anyt field-independent event not covered by the generated code.

The #SUSPEND statement means that conditional code statements (those prefaced with #?) will only generate if an explicit code statement (without #?) is also generated for the event, or if the programmer has placed some embedded source or used a Code template in an embed point associated with the event being processed. This is the mechanism that allows Clarion's Template Language to only generate code that is actually required for the procedure, eliminating unnecessary generated code.

The #?CASE ACCEPTED() structure contains all the code to handle all the Accepted events for menu items. Since menu items only generate Accepted events, this structure keeps the following CASE FIELD() structure from becoming unwieldy. This line of code, since it is prefaced with #?, will only generate if there is some other code generated within it, eliminating an empty CASE structure. The code for the CASE structure is generated by the #INSERT(%StandardAcceptedHandling) statement. This #GROUP is also discussed in detail in its own section. The #?END statement will only generate an END statement if other code has already been generated.

The #RESUME statement terminates the #SUSPEND section. If no source code has actually been generated, none of the conditional source statements (prefaced by #?) between the #SUSPEND and the #RESUME generate.

The #?CASE FIELD() structure (also bracketed within #SUSPEND and #RESUME statements) contains all the code to handle all the field-specific events. The code for the CASE structure is generated by the #INSERT(%StandardControlHandling) statement (between its two #EMBED statements). This #GROUP is also discussed in detail in its own section. The #?END statement

will only generate an END statement if other code has already been generated. The #EMBED immediately following #RESUME provides an embed point at the bottom of the ACCEPT loop.

The END statement terminates the ACCEPT loop. This statement is always generated (as is the ACCEPT) because every window requires an ACCEPT loop directly associated with it to process the events for that window. The DO ProcedureReturn statement calls the "cleanup code" for the procedure.

The ProcedureReturn ROUTINE begins with a comment block that generates into the Clarion code to explain the ROUTINE's purpose. The first line of code in the ROUTINE is the #INSERT(%FileControlClose) statement. This generates the code to close the files that were opened by the procedure. This #GROUP also contains two #EMBED statements that allow the programmer to embed code either before or after the files are closed.

The #INSERT(%StandardWindowClosing) generates the CLOSE(window) statement, and the .INI file handling code (if the programmer has checked the **Use .INI file to save and restore program settings** box). This #GROUP also includes two #EMBED statements that allow the programmer to embed code either before or after closing the window.

The next #EMBED allows the programmer to embed code before closing the procedure's window. The next #INSERT statement generates all the "Procedure Exit" class formulas. The next five Clarion language statements set up the procedure to alert the calling procedure to the action it performed, signaled back to the calling procedure through the GlobalRequest variable. The POPBIND statement eliminates any BIND scoping problems. The #IF structure then determines whether the procedure returns a value and generates the correct RETURN statement.

The InitializeWindow ROUTINE is a standard routine in all of Clarion's shipping Templates. It starts with a comment block, then the #EMBED allows the programmer to perform any initialization code for themselves, and provides Code, Control, and Extension templates a place to generate their window initialization code. The DO RefreshWindow statement calls the routine to display the current contents of all the controls' USE variables at the time the window is initialized.

The RefreshWindow ROUTINE is another standard routine in all of Clarion's shipping Templates that performs the procedure's MANY:1 lookups and refreshes the screen to ensure any changed data correctly displays to the user at all times. The ROUTINE starts with a comment block then the IF %Window{PROP:AcceptAll} THEN EXIT. statement. This detects when the procedure is on "non-stop" mode performing all data validity checks prior to writing a record to disk, and aborts the re-display.

The first #EMBED allows the programmer to embed code before the lookups. The next #INSERT generates all the "Before Lookups" class formulas, then

#INSERT(%StandardSecondaryLookups) generates the code to get all the related records for the procedure. The next #INSERT generates all the "After Lookups" class formulas, then comes a #EMBED to allow the programmer to embed code after the lookups. The DISPLAY statement puts any changed values on screen, and ForceRefresh = False turns off the procedure's screen refresh flag.

The SyncWindow ROUTINE is also a standard routine in all of Clarion's shipping Templates. It performs the same lookups as the RefreshWindow ROUTINE, with similar embed points, but does not refresh the screen. Instead, it ensures all record buffers contain correct data. This ROUTINE is usually called before executing some action that may require the currently highlighted record in a LIST.

The next to last #EMBED statement allows the programmer to embed any ROUTINEs they have called from their code within other embed points. The last #EMBED statement allows any other templates to embed any local PROCEDUREs that are called from their code.

#### **%StandardWindowHandling #GROUP**

This #GROUP generates all the code to handle field-independent events for the procedure. It generates its code inside the Window template's CASE EVENT() structure.

```
#GROUP (%StandardWindowHandling)
#FOR(%WindowEvent)
  #SUSPEND
#?OF EVENT: %WindowEvent
  #EMBED(%WindowEventHandling,'Window Event Handling'),%WindowEvent
  #CASE (%WindowEvent)
  #OF('OpenWindow')
  IF NOT WindowInitialized
   DO InitializeWindow
    WindowInitialized = True
    #IF(%FirstField)
  SELECT (%FirstField)
    #ENDIF
  #OF('GainFocus')
  ForceRefresh = True
  IF NOT WindowInitialized
    DO InitializeWindow
    WindowInitialized = True
  ELSE
    DO RefreshWindow
  END
  #OF('Sized')
  ForceRefresh = True
  DO RefreshWindow
  #ENDCASE
  #EMBED(%PostWindowEventHandling,'Window Event Handling, after generated code') %|
         ,%WindowEvent
  #RESUME
#ENDFOR
OF Event:Rejected
  #EMBED(%WindowEventHandlingBeforeRejected,'Window Event Handling - Before Rejected')
 DISPLAY (?)
  SELECT(?)
  #EMBED(%WindowEventHandlingAfterRejected,'Window Event Handling - After Rejected')
#SUSPEND
#?ELSE
  #EMBED(%WindowOtherEventHandling,'Other Window Event Handling')
#RESUME
```

This #GROUP starts with #FOR(%WindowEvent). This means it will loop through every instance of the %WindowEvent symbol, generating code (if required) for each field-independent event in the procedure.

The #SUSPEND statement begins the section of code that will only conditionally generate code if an explicit code statement (without #?) generates, or if the programmer has placed some embedded source or used a Code or Extension template to generate code into an embed point.

The #?OF EVENT:%WindowEvent statement conditionally generates an OF clause to the CASE EVENT() structure for the currently processing instance of %WindowEvent. This line of code, since it is prefaced with #?, will only generate if there is some other code generated within it, eliminating an empty OF clause.

The #EMBED statement is the key to the source generation process, and to the Procedure template's interaction with Code, Control, and Extension templates. Because it has the ",%WindowEvent" appended to the end, the programmer will have a separate embed point available for every instance of the %WindowEvent symbol. This means programmers can write their own code for any field-independent event. It also means any Code, Ccontrol, or Eextension templates the programmer places in the procedure can generate code into these embed points, as needed, to produce the code necessary to support their functionality. These embed points are the targets of the #AT statements used in the Code, Control, and Extension templates.

The #CASE(%WindowEvent) structure generates explicit source code for the field-independent events in its structure. The #OF('OpenWindow') checks for EVENT:OpenWindow and generates the check on the WindowInitialized variable to conditionally initialize the windowand set WindowInitialized to true. This code executes if no EVENT:GainFocus has already occurred (such as opening a second window on the same execution thread that currently has focus). The SELECT(%FirstField) statement is generated only if there are any controls that can receive focus in the window.

The #OF('GainFocus') statement checks for EVENT:GainFocus and generates the ForceRefresh = True, then checks to see if the window has already been initialized (if the user is switching between active threads it would have been). If not, it initializes the window, otherwise it simply refreshes it. The #OF('Sized') statement checks for EVENT:Sized and generates ForceRefresh = True and DO RefreshWindow to refresh the window after the user has resized it.

The #ENDCASE statement terminates the #CASE structure. The next #EMBED allows the programmer an opportunity to embed their own code following the generated code for any of these events. The #RESUME statement terminates the #SUSPEND section. If no source code has actually been generated, no conditional source statements (prefaced by #?) between the #SUSPEND and the #RESUME are generated.

#ENDFOR terminates the #FOR loop, then OF EVENT:Rejected generates and offers before and after embed points surrounding standard code to alert the user that the data input into the current control has been rejected (usually the data is out of range) and leave them on the same control.

The #SUSPEND statement begins another conditional generation section. This means the #?ELSE statement only generates an ELSE if source code is generated by the #EMBED statement. #RESUME terminates this #SUSPEND section.

#### %StandardAcceptedHandling #GROUP

This #GROUP generates all the code to handle field-specific events for the procedure. It generates its code inside the Window Template's CASE FIELD() structure.

This code starts with the #FOR(%Control),WHERE(%ControlMenu) statement. The WHERE attribute limits this #FOR loop to only those instances of %Control that contain menu items. The #FIX statement ensure that this code only deals with Accepted events.

The #MESSAGE statement displays its message during source generation. #SUSPEND begins a conditional source generation section.

The #?OF %Control statement conditionally generates an OF clause to the CASE ACCEPTED() structure for the currently processing instance of %Control. This line of code, since it is prefaced with #?, will only generate if there is some other code generated within it, eliminating an empty OF clause.

All three #EMBED statements have ",%Control,%ControlEvent" appended to the end, so the programmer will have a separate embed point available for every instance of the %ControlEvent symbol within every instance of the %Control symbol. For this group, this only means the Accepted event.

The #INSERT(%FieldTemplateStandardHandling) statement generates code to handle all the Actions dialog selections the programmer has made for the menu item. The next two #EMBED statements also have ",%Control,%ControlEvent" appended to the end. The first has the HIDE attribute, so it is available only for Code, Control, and Extension template use. These three #EMBEDs give the programmer an embed point both before and after any code automatically generated for them by the Actions tab prompts.

#RESUME terminates this #SUSPEND section. #ENDFOR terminates the %Control loop.

#### %StandardControlHandling #GROUP

This #GROUP generates all the code to handle field-specific events for the procedure. It generates its code inside the Window template's CASE FIELD() structure.

```
#GROUP(%StandardControlHandling)
#FOR(%Control), WHERE(%Control)
 #MESSAGE('Control Handling: ' & %Control,3)
  #SUSPEND
#?OF %Control
  #EMBED(%ControlPreEventCaseHandling,'Control Handling, before event handling') % |
        ,%Control
  #?CASE EVENT()
    #IF(NOT %ControlMenu)
      #FOR (%ControlEvent)
        #SUSPEND
  #?OF EVENT:%ControlEvent
    #EMBED(%ControlPreEventHandling, 'Control Event Handling, Before Generated Code') % |
          , %Control, %ControlEvent
    #INSERT(%FieldTemplateStandardHandling)
   #EMBED(%ControlEventHandling,'Internal Control Event Handling') % |
          ,%Control,%ControlEvent,HIDE
    #EMBED(%ControlPostEventHandling,'Control Event Handling, After Generated Code') % |
          , %Control, %ControlEvent
        #RESUME
      #ENDFOR
    #ELSE
  #?OF EVENT: Accepted
    #ENDIF
    #SUSPEND
  #PELSE
    #EMBED(%ControlOtherEventHandling,'Other Control Event Handling'),%Control
  #RESUME
  #?END
  #EMBED(%ControlPostEventCaseHandling,'Control Handling, after event handling') % |
        ,%Control
  #RESUME
#ENDFOR
```

This code starts with the #FOR(%Control),WHERE(%Control) statement. The WHERE clause may at first seem redundant, since #FOR will only loop through existing instances of %Control. However, since some controls do not need (and so do not have) field equate labels, there are valid instances of %Control that do not contain a value for %Control itself. Therefore, the WHERE attribute limits this #FOR loop to those instances of %Control that do contain a field equate label for the control.

The #MESSAGE statement displays its message during source generation. #SUSPEND begins a conditional source generation section.

The #?OF %Control statement conditionally generates an OF clause to the CASE FIELD() structure for the currently processing instance of %Control. This line of code, since it is prefaced with #?, will only generate if there is some other code generated within it, eliminating an empty OF clause.

The first #EMBED allows the programmer to handle any situation that needs to be handled before any generated code for the control. The #?CASE EVENT() conditionally generates a CASE EVENT() structure for the control. The #IF(NOT %ControlMenu) statement filters out all the menu items, since they are handled by the %StandardAcceptedHandling #GROUP. #FOR(%ControlEvent) loops through all the possible events that the control being processed can generate.

#SUSPEND begins another conditional source generation section, nested within the previous one. This allows multiple levels of conditional source code generation. The outer section is automatically generated if any code is generated from the inner section.

The #?OF EVENT:%ControlEvent statement conditionally generates an OF clause to the CASE EVENT() structure for the currently processing instance of %Control. This line of code, since it is prefaced with #?, will only generate if there is some other code generated within it, eliminating an empty OF clause.

This next #EMBED statement has ",%Control,%ControlEvent" appended to the end, so the programmer will have a separate embed point available for every instance of the %ControlEvent symbol within every instance of the %Control symbol. This means programmers can write their own code for any field-specific event, for any control . It also means any Code templates, Control templates, or Extension templates the programmer places in the procedure can generate code into these embed points, as needed, to produce the code necessary to support their functionality. These embed points are the targets of the #AT statements used in the Code, Control, and Extension templates.

The #INSERT(%FieldTemplateStandardHandling) statement generates code to handle all the Actions tab selections the programmer has made for the control. The prompts on the Actions tab come from the #FIELD structures that were #INSERTed at the beginning of the Window template.

The next two #EMBED statements also have ",%Control,%ControlEvent" appended to the end, so the programmer will have a separate embed point available for every instance of the %ControlEvent symbol within every instance of the %Control symbol. The first has the HIDE attribute, so it is available only for Code, Control, and Extension template use. These three #EMBEDs give the programmer an embed point both before and after any code automatically generated for them by the Actions tab prompts.

#RESUME terminates the inner conditional source generation section, then #ENDFOR terminates the %ControlEvent loop. The #ELSE refers back to the #IF(NOT %ControlMenu) and will generate an empty OF EVENT:Accepted followed by an ELSE statement for a Menu item if the programmer has entered code into the Other Control Event Handling embed point. This eliminates any duplication between EVENT:Accepted code for a menu item while still allowing the programmer to process any user-defined events for them.

The #SUSPEND statement begins another nested conditional generation section. This means the #?ELSE statement only generates an ELSE if source code is generated by the #EMBED statement. #RESUME terminates this #SUSPEND section.

The #?END generates the END statement for the CASE FIELD() structure, if any code has been generated, then the #RESUME statement terminates the outer #SUSPEND section. #ENDFOR terminates the %Control loop.

## **Code Template: ControlValueValidation**

The ControlValueValidation Code template performs data entry validation for an entry-type control (ENTRY, SPIN, or COMBO) by looking up the value entered by the user in another data file. If the lookup is successful, the entered value is valid. If not, it calls another procedure to allow the user to select a valid value from the lookup file. This Code template is designed to generate code only into EVENT:Selected or EVENT:Accepted embed points of an ENTRY, SPIN, or COMBO control. These are the controls into which a user can directly type in data.

```
#CODE (ControlValueValidation, 'Control Value Validation')
  #RESTRICT
    #CASE (%ControlType)
    #OF('ENTRY')
    #OROF('SPIN')
    #OROF ('COMBO')
      #CASE (%ControlEvent)
      #OF('Accepted')
      #OROF('Selected')
        #ACCEPT
      #ELSE
        #REJECT
      #ENDCASE
    #ELSE
      #REJECT
    #ENDCASE
  #ENDRESTRICT
#DISPLAY('This Code Template is used to perform a control value')
#DISPLAY('validation. This Code Template only works for')
#DISPLAY('the Selected or Accepted Events for an Entry Control.')
#DISPLAY('')
#PROMPT('Lookup Key', KEY), %LookupKey, REQ
#PROMPT('Lookup Field', COMPONENT), %LookupField, REQ
#PROMPT('Lookup Procedure', PROCEDURE), %LookupProcedure
#DISPLAY('')
#DISPLAY('The Lookup Key is the key used to perform the value validation.')
#DISPLAY('If the Lookup Key is a multi-component key, you must insure that')
#DISPLAY('other key elements are primed BEFORE this Code Template is used.')
#DISPLAY('')
#DISPLAY('The Lookup field must be a component of the Lookup Key. Before')
#DISPLAY('execution of the lookup code, this field will be assigned the value of')
#DISPLAY('the control being validated, and the control will be assigned the value')
#DISPLAY('of the lookup field if the Lookup procedure is successful.')
#DISPLAY('')
#DISPLAY('The Lookup Procedure is called to let the user to select a value. ')
#DISPLAY('Request upon entrance to the Lookup will be set to SelectRecord, and ')
#DISPLAY('successful completion is signalled when Response = RequestCompleted.')
#IF(%ControlEvent='Accepted')
 IF %Control{PROP:Req} = False AND NOT %ControlUse #<! If not required and empty
ELSE
 #INSERT (%CodeTPLValidationCode)
#ELSIF(%ControlEvent='Selected')
 #INSERT (%CodeTPLValidationCode)
  #ERROR('This Code Template must be used for Accepted or Selected Events!')
```

A Code template always starts with the #CODE statement, which identifies it within the template set and defines the description which appears in the list of available Code templates for a given embed point.

The #RESTRICT structure defines the embed points where the code template will appear as a choice. The #CASE(%ControlType) structure limits the embed points to the ENTRY, SPIN, and COMBO controls, and the #CASE(%ControlEvent) structure limits the embed points to EVENT:Accepted and EVENT:Selected.

The #ACCEPT statement indicates these are appropriate embed points, while the #REJECT indicates all other control type and event embed points are not valid for the Code template to appear in as a choice.

All the #DISPLAY statements display their text to the programmer on the code template's prompt dialog. These describe the information the programmer needs to supply in the prompts.

The first #PROMPT asks for the name of the key to use in the file that will be used to validate the user's input. The REQ attribute indicates the programmer must supply this information.

The second #PROMPT asks for the name of the field in the key that contains the same information the user should enter into the control. Again, the REQ attribute indicates the programmer must supply this information.

The third #PROMPT asks for the name of the procedure to call if the lookup is unsuccessful. This would usually be a Browse procedure for the lookup file with a Select button to allow the user to choose the record containing the value they want for the control.

Again, the #DISPLAY statements display text to the programmer on the prompt dialog to describe the information the programmer needs to supply in the prompts.

The #IF(%ControlEvent='Accepted') structure generates an IF structure for EVENT:Accepted that detects when the control has the REQ attribute or the user has entered a value and #INSERTs the %CodeTPLValidationCode #GROUP to generate the source code for the data validation. The #ELSIF just unconditionally #INSERTs the %CodeTPLValidationCode #GROUP to generate the source code for the data validation.

If the event is anything other than EVENT:Accepted or EVENT:Selected, an error message is the only output generated.

See Also: %CodeTPLValidationCode #GROUP

#### %CodeTPLValidationCode #GROUP

This #GROUP is the "workhorse" of the Code template. It generates the actual file lookup code to validate the data entry. It takes the information provided in the prompts and combines it with the %ControlUse symbol to generate a GET statement into the lookup file. If the GET is successful, the data is valid. If not, it calls the lookup procedure.

```
#GROUP(%CodeTPLValidationCode)
 %LookupField = %ControlUse
                                                    #<! Move value for lookup
#FIND(%Field,%LookupField)
                                                    #! FIX field for lookup
GET(%File,%LookupKey)
                                                    #<! Get value from file
                                                    #<! IF record not found
IF ERRORCODE()
   GlobalRequest = SelectRecord
                                                    #<! Set Action for Lookup
   %LookupProcedure
                                                    #<! Call Lookup Procedure
  LocalResponse = GlobalResponse
                                                    #<! Save Returned Action
   GlobalResponse = RequestCancelled
                                                    #<! Clear the Action Value
   IF LocalResponse = RequestCompleted
                                                    #<! IF Lookup successful
     %ControlUse = %LookupField
                                                    #<! Move value to control field
#IF(%ControlEvent='Accepted')
                                                    #! IF a Post-Edit Validation
   ELSE
                                                    #<! ELSE (IF Lookup NOT...)
     SELECT (%Control)
                                                    #<! Select the control
     CYCLE
                                                    #<! Go back to ACCEPT
#ENDIF
                                                    #! END (IF a Pre-Edit...)
                                                    #<! END (IF Lookup successful)
#IF(%ControlEvent='Selected')
                                                    #! IF a Pre-Edit Validation
  SELECT (%Control)
                                                    #<! Select the control
#ENDIF
                                                    #! END (IF a Pre-Edit...)
END
                                                    #<! END (IF record not found)</pre>
```

This #GROUP starts by generating the %LookupField = %ControlUse assignment. This assigns the control's USE variable to the field named in the second prompt; the key field that should contain the correct value.

The #FIND(%Field,%LookupField) statement looks through all the fields in the data dictionary, looking for a matching field to the one contained in %LookupField. This fixes %Field and %File to the correct values to generate the GET(%File,%LookupKey) statement. This becomes a GET(file,key) form of the GET statement to get a single record from the lookup file with matching key field values.

The IF ERRORCODE() structure checks for a successful GET operation. If an error occurred, the GET was unsuccessful and the GlobalRequest = SelectRecord statement sets up the call to the lookup procedure, generated by the %LookupProcedure statement.

After return from the lookup procedure, LocalResponse = GlobalResponse saves the lookup procedure's response code. Then the GlobalResponse = RequestCancelled statement cleans up so any other execution thread does not get an incorrect response. This must be done immediately, before the user has a chance to change execution threads.

The IF LocalResponse = RequestCompleted structure detects a user choice from the lookup procedure and the %ControlUse = %LookupField statement assigns the choice to the control's USE variable.

The #IF(%ControlEvent='Accepted') detects when the Code template is generating for EVENT:Accepted and adds the ELSE clause to SELECT the control and CYCLE back to the top of the ACCEPT loop.

The END statement terminates the IF LocalResponse = RequestCompleted structure. The #IF(%ControlEvent='Selected') structure generates the SELECT statement for the control when generating for EVENT:Selected.

The END statement terminates the IF ERRORCODE() structure. Obviously, if there was no error on the GET statement, the data is valid and no further code is necessary.

## **Control Template: DOSFileLookup**

The *DOSFileLookup* Control template adds an ellipsis (...) button which leads the end user to a standard **Open File** dialog. You can specify a file mask, and a return variable to hold the end user's choice.

```
#CONTROL(DOSFileLookup, 'Lookup a DOS file name'), WINDOW, MULTI
  CONTROLS
    BUTTON('...'), AT(,,12,12), USE(?LookupFile)
#BOXED('DOS File Lookup Prompts')
  #PROMPT('&File Dialog Header:',@S60),%DOSFileDialogHeader,REQ,DEFAULT('Choose File')
  #PROMPT('&DOS FileName Variable:',FIELD), %DOSFileField,REQ
  #PROMPT('D&efault Directory:',@S80),%DOSInitialDirectory
  #PROMPT('&Return to original directory when done.', CHECK), %ReturnToOriginalDir, AT(10)
  #PROMPT('&Use a variable to specify the file mask(s).', CHECK), %DOSVariableMask, AT(10)
  #ENABLE (%DOSVariableMask)
    #PROMPT('Vari&able Mask Value:',FIELD),%DOSVariableMaskValue
  #ENDENABLE
  #ENABLE (NOT %DOSVariableMask)
    #PROMPT('F&ile Mask Description:',@S40),%DOSMaskDesc,REQ,DEFAULT('All Files')
    #PROMPT('Fi&le Mask',@S50),%DOSMask,REQ,DEFAULT('*.*')
    #BUTTON('More Fil&e Masks'), MULTI(%DOSMoreMasks,%DOSMoreMaskDesc&'-'&%DOSMoreMask)
      #PROMPT('File Mask Description:',@S40),%DOSMoreMaskDesc,REQ
      #PROMPT('File Mask',@S50),%DOSMoreMask,REQ
    #ENDBUTTON
  #ENDENABLE
#ENDBOXED
#LOCALDATA
DOSDialogHeader
                     CSTRING (40)
DOSExtParameter
                     CSTRING (250)
                     CSTRING(80)
DOSTargetVariable
#ENDLOCALDATA
#ATSTART
  #DECLARE (%DOSExtensionParameter)
  #DECLARE (%DOSLookupControl)
  #FOR(%Control), WHERE(%ControlInstance = %ActiveTemplateInstance)
    #SET(%DOSLookupControl,%Control)
  #ENDFOR
  #IF(NOT %DOSVariableMask)
    #SET(%DOSExtensionParameter,%DOSMaskDesc & '|' & %DOSMask)
    #FOR (%DOSMoreMasks)
      #SET(%DOSExtensionParameter,%DOSExtensionParameter & '|' & %DOSMoreMaskDesc &|
           & '|' & %DOSMoreMask)
    #ENDFOR
  #END
#ENDAT
#AT(%ControlEventHandling,%DOSLookupControl,'Accepted')
IF NOT %DOSFileField
  #INSERT(%StandardValueAssignment,'DOSTargetVariable',%DOSInitialDirectory)
ELSE
 DOSTargetVariable = %DOSFileField
#INSERT(%StandardValueAssignment,'DOSDialogHeader',%DOSFileDialogHeader)
#IF(%DOSVariableMask)
DOSExtParameter = %DOSVariableMaskValue
#ELSE
DOSExtParameter = '%DOSExtensionParameter'
#ENDIF
#IF(%ReturnToOriginalDir)
```

This starts, as all Control templates must, with a #CONTROL statement. The WINDOW attribute allows you to populate it onto a window, but not onto a report. The MULTI attribute specifies that the template may be populated multiple times onto the same window. The CONTROLS section pre-defines the BUTTON control for the window.

The #BOXED structure places a box around all the prompts that display on the Actions tab for this Control template. The first #PROMPT asks for the text for the caption of the **Open File** dialog, and the next asks for the name of a variable to receive the end user's choice. The third allows you to explicitly set the directory in which the **Open File** dialog starts.

The fourth #PROMPT is a check box asking whether the program should return to the directory from which it started from the **Open File** dialog. The fifth #PROMPT is a check box asking whether the programmer will explicitly set the file mask(s) for the **Open File** dialog, or use a variable to determine them at run time. When checked, the first #ENABLE activates the Variable Mask Value #PROMPT to get the name of the variable toi use at run time. If not checked, the second #ENABLE activates its set of prompts to get each explicit file mask to pass to the **Open File** dialog.

The #LOCALDATA section defines three local variables that generate automatically as part of the procedure. These local variables are only used in the code generated by this Control template as the actual variables passed as parameters to the FILEDIALOG procedure.

The #ATSTART statement begins a section of template code that executes before any source code generates for the procedure. This means it is only appropriate to initialize user-defined template symbols and perform any necessary set up to generate correct source for the control template into the procedure. This section does not generate source code. The #DECLARE statements declare two symbols used only during source generation for this Control template.

#FOR(%Control),WHERE(%ControlInstance=%ActiveTemplateInstance) executes the enclosed #SET statement only for the single control populated by this Control template. The #SET statement then places the field equate label of the control into %DOSLookupControl.

The #IF structure checks whether the programmer checked the **Use a Variable to specify the file mask(s)** box and if not, sets up the specific file masks the programmer chose to pass to the FILEDIALOG procedure. The #ENDAT statement terminates the #ATSTART section.

The next #AT generates Clarion code into the embed point for the Accepted event for the control populated by this Control template to perform the file lookup. The IF NOT %DOSFileField structure detects whether the user has performed the lookup. If they haven't the initial directory is assigned to the DOSTargetVariable. If the user has performed the lookup, the ELSE clause assigns the result of the previous lookup as the starting point for the next.

The #INSERT statement creates assignment statements to initialize the **File Open** dialog's title. Next, the #IF(%DOSVariableMask) conditionally generates an assignment to initialize the file mask to pass to the **File Open** dialog.

The #IF (%ReturnToOrigianlDir) generates the correct IF FILEDIALOG structure performs the actual lookup for the file, either to return to the original directory or not. If the user selects a file from the **File Open** dialog, the selected filename is assigned to variable the user selected in the **DOS FileName Variable** prompt, then he DO RefreshWindow statement ensures that all data on the window is current. The #ENDAT statement terminates the #AT section.

## **Extension Template: DateTimeDisplay**

The *DateTimeDisplay* Extension template displays the date and/or time in either a display-only STRING control or a section of the status bar. Of course, the status bar should be declared on the window.

```
#EXTENSION(DateTimeDisplay,'Display the date and/or time in the current window') % |
          ,HLP('~TPLExtensionDateTimeDisplay'),PROCEDURE
#BUTTON('Date and Time Display'), AT(10,,180)
  #BOXED('Date Display...')
    #PROMPT('Display the current day/date in the window',CHECK) %|
           , %DisplayDate, DEFAULT(0), AT(10,,150)
    #ENABLE (%DisplayDate)
      #PROMPT('Date Picture:',DROP('October 31, 1959|OCT 31,1959|10/31/59| %|
                                 10/31/1959|31 OCT 59|31 OCT 1959|31/10/59| %|
                                           31/10/1959|Other')), %DatePicture %|
                                    ,DEFAULT('October 31, 1959')
      #ENABLE(%DatePicture = 'Other')
        #PROMPT('Other Date Picture:',@S20),%OtherDatePicture,REQ
      #ENDENABLE
      #PROMPT('Show the day of the week before the date', CHECK), %ShowDayOfWeek %|
              ,DEFAULT(1),AT(10,,150)
      #PROMPT('&Location of Date Display:',DROP('Control|Status Bar')) %|
              , %DateDisplayLocation
      #ENABLE(%DateDisplayLocation='Status Bar')
        #PROMPT('Status Bar Section:',@n1),%DateStatusSection,REQ,DEFAULT(1)
      #ENDENABLE
      #ENABLE(%DateDisplayLocation='Control')
        #PROMPT('Date Display Control:',CONTROL), %DateControl,REQ
      #ENDENABLE
    #ENDENABLE
  #ENDBOXED
  #BOXED('Time Display...')
    #PROMPT('Display the current time in the window', CHECK), %DisplayTime % |
            ,DEFAULT(0),AT(10,,150)
    #ENABLE (%DisplayTime)
      #PROMPT('Time Picture:',DROP('5:30PM|5:30:00PM|17:30|17:30:00| %|
                                    1730|173000|Other')),%TimePicture %|
                                    ,DEFAULT('5:30PM')
      #ENABLE(%TimePicture = 'Other')
        #PROMPT('Other Time Picture:',@S20),%OtherTimePicture,REQ
      #ENDENABLE
      #PROMPT('&Location of Time Display:',DROP('Control|Status Bar')) %|
              ,%TimeDisplayLocation
      #ENABLE(%TimeDisplayLocation='Status Bar')
        #PROMPT('Status Bar Section:',@n1),%TimeStatusSection,REQ,DEFAULT(2)
      #ENDENABLE
      #ENABLE (%TimeDisplayLocation='Control')
        #PROMPT('Time Display Control:',CONTROL),%TimeControl,REQ
      #ENDENABLE
    #ENDENABLE
  #ENDBOXED
#ENDBUTTON
#ATSTART
  #DECLARE (%TimerEventGenerated)
  #IF(%DisplayDate)
    #DECLARE (%DateUsePicture)
    #CASE (%DatePicture)
    #OF('10/31/59')
      #SET(%DateUsePicture,'@D1')
```

```
#OF('10/31/1959')
      #SET(%DateUsePicture,'@D2')
    #OF('OCT 31,1959')
      #SET(%DateUsePicture,'@D3')
    #OF('October 31, 1959')
      #SET(%DateUsePicture,'@D4')
    #OF('31/10/59')
      #SET(%DateUsePicture,'@D5')
    #OF('31/10/1959')
      #SET(%DateUsePicture,'@D6')
    #OF('31 OCT 59')
      #SET(%DateUsePicture,'@D7')
    #OF('31 OCT 1959')
      #SET (%DateUsePicture, '@D8')
    #OF('Other')
      #SET(%DateUsePicture,%OtherDatePicture)
    #ENDCASE
  #ENDIF
  #IF(%DisplayTime)
    #DECLARE (%TimeUsePicture)
    #CASE (%TimePicture)
    #OF('17:30')
      #SET(%TimeUsePicture,'@T1')
    #OF('1730')
      #SET(%TimeUsePicture,'@T2')
    #OF('5:30PM')
      #SET(%TimeUsePicture,'@T3')
    #OF('17:30:00')
      #SET(%TimeUsePicture,'@T4')
    #OF('173000')
      #SET(%TimeUsePicture,'@T5')
    #OF('5:30:00PM')
      #SET(%TimeUsePicture,'@T6')
    #OF('Other')
      #SET (%TimeUsePicture, %OtherTimePicture)
    #ENDCASE
  #ENDIF
#ENDAT
#AT (%DataSectionBeforeWindow)
  #IF(%DisplayDate AND %ShowDayOfWeek)
DisplayDayString STRING('Sunday
                                   Monday
                                             Tuesday WednesdayThursday % |
                          Friday
                                   Saturday ')
DisplayDayText
                 STRING(9),DIM(7),OVER(DisplayDayString)
  #ENDIF
#ENDAT
#AT(%BeforeAccept)
  #IF(%DisplayTime OR %DisplayDate)
IF NOT INRANGE(%Window{Prop:Timer},1,100)
  %Window{Prop:Timer} = 100
END
#INSERT(%DateTimeDisplayCode)
  #ENDIF
#ENDAT
#AT(%WindowEventHandling,'Timer')
  #SET(%TimerEventGenerated,%True)
  #IF(%DisplayDate OR %DisplayTime)
#INSERT(%DateTimeDisplayCode)
  #ENDIF
#ENDAT
#AT(%WindowOtherEventHandling)
```

```
#IF(%DisplayDate OR %DisplayTime)
    #IF(NOT %TimerEventGenerated)

IF EVENT() = EVENT:Timer
    #INSERT(%DateTimeDisplayCode)

END
    #ENDIF
#ENDIF
#ENDAT
```

An Extension template starts with the #EXTENSION statement. The PROCEDURE attribute specifies the Extension template is available only at the procedure level, not the global level of the application.

The #BUTTON structure creates a separate page for all the prompts for this Extension template. These prompts ask the programmer for the format of the date and/or time to display, and whether to display them in a control or the status bar.

The #ATSTART statement begins a section of template code that executes before any source code generates for the procedure. This means it is only appropriate to initialize user-defined template symbols and perfrom any necessary set up to generate correct source for the control template into the procedure. This section does not generate source code.

The #DECLARE(%TimerEventGenerated) statement declares a symbol used only in this Extension template. It is used to flag whether an OF EVENT:Timer clause has been generated for the procedure.

The #IF(%DisplayDate) structure sets up to display the date by declaring a symbol to contain the programmer's choice of date formats. The #CASE structure assigns that choice to the %DateUsePicture symbol. The #IF(%DisplayTime) structure sets up to display the time by declaring a symbol to contain the programmer's choice of date formats. The #CASE structure assigns that choice to the %TimeUsePicture symbol. The #ENDAT statement terminates the #ATSTART section.

The next #AT generates code into the embed point that appears immediately before the window data structure. The #IF(%DisplayDate AND %ShowDayOfWeek) structure generates two local variable declarations for the procedure if the programmer is displaying the date with the day of week.

The next #AT generates code into the embed point that appears immediately before the ACCEPT loop. The #IF(%DisplayTime OR %DisplayDate) structure generates code that ensures the window has its TIMER attribute set. The IF NOT INRANGE(%Window{Prop:Timer},1,100) detects the lack of the attribute, then %Window{Prop:Timer} = 100 sets it to one second. The #INSERT(%DateTimeDisplayCode) adds the code that updates the display.

The next #AT generates code into the embed point for EVENT:Timer. This embed point only appears if the programmer has placed a TIMER attribute on the window. Therefore, the #SET(%TimerEventGenerated,%True) statement signals that code was generated in this embed point. The #IF(%DisplayTime OR %DisplayDate) structure ensures the #INSERT(%DateTimeDisplayCode) statement generates the code that updates the display every time EVENT:Timer is processed.

The next #AT generates code into the "Other Window Event Handling" embed point. This is the ELSE clause of the CASE EVENT() structure to handle field-independent events. #IF(NOT %TimerEventGenerated) detects that the previous #AT did not generate code because the programmer did not place the TIMER attribute on the window. Therefore, the IF EVENT() = EVENT:Timer structure is necessary for the code that updates the display whenever EVENT:Timer occurs.

#### %DateTimeDisplayCode #GROUP

This #GROUP generates the code to actually display the Date and/or Time.

```
#GROUP(%DateTimeDisplayCode)
    #IF(%DisplayDate)
      #IF(%ShowDayOfWeek)
        #CASE (%DateDisplayLocation)
        #OF('Control')
  %DateControl(Prop:Text) = CLIP(DisplayDayText[(TODAY()%%7)+1]) & ', ' & %|
                                 FORMAT(TODAY(), %DateUsePicture)
 DISPLAY(%DateControl)
        #ELSE
  %Window{Prop:StatusText, %DateStatusSection} = CLIP(DisplayDayText[( %|
          TODAY()%%7)+1]) & ', ' & FORMAT(TODAY(),%DateUsePicture)
        #ENDCASE
      #ELSE
        #CASE (%DateDisplayLocation)
        #OF('Control')
  %DateControl{Prop:Text} = FORMAT(TODAY(), %DateUsePicture)
 DISPLAY (%DateControl)
        #ELSE
  %Window{Prop:StatusText,%DateStatusSection} = FORMAT(TODAY(),%DateUsePicture)
        #ENDCASE
      #ENDIF
    #ENDIF
    #IF(%DisplayTime)
      #CASE(%TimeDisplayLocation)
      #OF('Control')
  %TimeControl{Prop:Text} = FORMAT(CLOCK(),%TimeUsePicture)
 DISPLAY (%DateControl)
      #ELSE
  %Window{Prop:StatusText,%TimeStatusSection} = FORMAT(CLOCK(),%TimeUsePicture)
      #ENDCASE
    #ENDIF
```

The #IF(%DisplayDate) structure generates the code to display the date. The #IF(%ShowDayOfWeek) structure detects the programmer's choice to display the day along with the date, then #CASE(%DateDisplayLocation) generates the code to display into a STRING display-only control for the #OF('Control') clause.

The assignment statement concatenates the day of the week (from the DisplayDayText[(TODAY() %% 7)+1] expression) with the formatted date (from the FORMAT(TODAY(),%DateUsePicture) expression) into the STRING(text) property (the %DateControl{Prop:Text} property). The %% generates as a single % (modulus operator) for the TODAY() % 7 + 1 expression to get the correct day of the week text from the DisplayDayText array. The #ELSE clause of the #CASE(%DateDisplayLocation) assigns the same expression to the status bar section the programmer chose for the date display.

The #ELSE clause of the #IF(%ShowDayOfWeek) structure performs the same assignments, without the day of the week. The #IF(%DisplayTime) structure performs the same type of assignments of the formatted time to either a STRING display-only control or the status bar.

# Index

#\$ (embededitor comment)13	#DEBUG	160
#?141	#DEBUG (toggle debug generation)	160
#? (conditional source line)141	#DECLARE	160
#<161	#DECLARE (declare a user-defined sym	,
#< (aligned target language comments)161	#DEFAULT	
#ABORT161		160
#ABORT (abort source generation)161	#DEFAULT (default procedure starting point)	160
#ACCEPT161	#DEFINE (user defined macro)	
#ACCEPT (section valid for use)161	#DELETE	
#ADD163	#DELETE (delete a multi-valued symbol	
#ADD (add to multi-valued symbol)163	instance)	160
#ALIAS163	#DELETEALL	160
#ALIAS (access a symbol from another instance)163	#DELETEALL (delete multiple multi-value symbol instances)	
#APPEND163	#ENABLE	160
#APPEND (add to source file)163	#ENABLE (enable/disable prompts)	160
#BOXED163	#ENDBOXED	163
#BOXED (prompt group box)163	#ENDBUTTON	163
#BREAK163	#ENDCONTEXT	160
#BREAK (break out of a loop)163	#ENDDEFAULT	160
#BUTTON163	#ENDENABLE	160
#BUTTON (call another page of prompts)	#ENDFIELD	163
163	#ENDPREPARE	165
#CODE163	#ENDREPORTS	165
#CODE (define a code template)163	#ENDSECTION	165
#COMMENT160	#ENDSHEET	165
#COMMENT (specify comment column).160	#ENDWITH	165
#CONTEXT160	#EQUATE	163
#CONTEXT (set template code generation context)160	#EQUATE (declare and assign value to a user-defined symbol)	
#CONTROL160	#FIELD	163
#CONTROL (define a control template)160	#FIELD (control prompts)	163
#CREATE160	#FIELDS	
#CREATE (create source file)160	#FIND	
#CYCLE160	#FIND (	
#CYCLE (cycle to top of loop)160	#LINK	

#ORDINAL160	#SET (assign value to a user-defined symbol)	165
#ORIG160	#SHEET	
#PREEMBED165		
#PREEMBED (generate beginning embed point comments)165	#SHEET (declare a group of #TAB control	165
#PREPARE165	#SUSPEND	
#PREPARE (setup prompt symbols)165	#SUSPEND (begin conditional source)	
#PRINT165	#SYSTEM	
#PRINT (print a source file)165	#SYSTEM (template registration and loa	,
#PROMPT 106, 107, 108, 109, 110, 111,	#TRYALIAS	
112, 113, 114, 115, 116, 117, 118, 119, 120, 121, 122, 123, 124, 125, 126, 127, 128	#WITH	
#RELEASE165	#WITH (assscoiate prompts with a symb	
#RELEASE (commit conditional source	instance)	
generation)165	%	
#REMOVE165	%#	
#REMOVE (delete a source file)165	%%189,	235
#REPLACE165	%(expression)	
#REPLACE (conditionally replace source file)165	%@picture@symbol	189
,	%[number]symbol	189
#REPORTS165	%	189
#REPORTS (default report structures)165	%ActiveTemplate	205
#REQ160	%ActiveTemplateInstance	205
#RESUME165	%ActiveTemplateOwnerInstance	205
#RESUME (delimit conditional source)165	%ActiveTemplateParentInstance	205
#RETURN165	%ActiveTemplatePrimaryInstance	205
#RETURN (return from #GROUP)165	%AliasFile 193,	196
#RUN165	%BytesOutput	214
#RUN (execute program)165	%CodeTPLValidationCode #GROUP	229
#RUNDLL165	%CommentColumn	214
#RUNDLL (execute DLL procedure)165	%ConditionalGenerate	214
#SECTION165	%Control	205
#SECTION (define code section)165	%ControlAlert	205
#SELECT165	%ControlDefaultHeight	205
#SELECT (fix a multi-value symbol)165	%ControlDefaultWidth	
#SEQ160	%ControlEvent	
#SERVICE165	%ControlField	
#SERVICE (TopSpeed internal use only)165	%ControlFieldDefaultTip	
#QET 165		

%ControlFieldFormat205	%DriverEncrypt	212
%ControlFieldHasColor205	%DriverLIB	212
%ControlFieldHaslcon205	%DriverMaxKeys	212
%ControlFieldHasLocator205	%DriverMemo	212
%ControlFieldHasTip205	%DriverOpcode	212
%ControlFieldHasTree205	%DriverOwner	212
%ControlFieldHeader205	%DriverReclaim	212
%ControlFieldPicture205	%DriverRequired	212
%ControlFrom205	%DriverSQL	212
%ControlHasColorContains205	%DriverType	212
%ControlHasIconContains205	%DriverUniqueKey	212
%ControlHasStyleContains205	%EmbedDescription	214
%ControlHasTipContains205	%EmbedID	214
%ControlHasTree205	%EmbedParameters	214
%ControlIndent205	%EOF	214
%ControlInstance205	%False	214
%ControlMenu205	%Field	193, 196, 198
%ControlMenuBar205	%FieldChoices	198
%ControlOriginal205	%FieldDescription	198
%ControlParameter205	%FieldDimension1	198
%ControlParent205	%FieldDimension2	198
%ControlParentTab205	%FieldDimension3	198
%ControlParentType205	%FieldDimension4	198
%ControlStatement205	%FieldDisplayPicture	198
%ControlTemplate205	%FieldFile	198
%ControlTool205	%FieldFormatWidth	198
%ControlToolBar205	%FieldHeader	198
%ControlType205	%FieldHelpID	198
%ControlUnsplitStatement205	%FieldID	198
%ControlUse205	%FieldIdent	198
%CWVersion214	%FieldInitial	198
%DateTimeDisplayCode #GROUP235	%FieldJustIndent	198
%Driver212	%FieldJustType	198
%DriverBinMemo212	%FieldLongDesc	198
%DriverCreate212	%FieldLookup	198
%DriverDescription212	%FieldMemoImage	198
%DriverDLL212	%FieldMemoSize	198

%FieldName	198	%FilePrefix	. 193,	196
%FieldPicture	198	%FilePrimaryKey	. 193,	196
%FieldPlaces	198	%FileQuickOptions	. 193,	196
%FieldQuickOptions	198	%FileReclaim	. 193,	196
%FieldRangeHigh	198	%FileRelationType		199
%FieldRangeLow	198	%FileStatement	. 193,	196
%FieldRecordPicture	198	%FileStruct	. 193,	196
%FieldReportControl	198	%FileStructEnd	. 193,	196
%FieldReportControlHeight	198	%FileStructRec	. 193,	196
%FieldReportControlWidth	198	%FileStructRecEnd	. 193,	196
%FieldScreenControl	198	%FileThreaded	. 193,	196
%FieldScreenControlHeight	198	%FileType	. 193,	196
%FieldScreenControlWidth	198	%FileUserOptions	. 193,	196
%FieldStatement	198	%Formula		209
%FieldStruct	198	%FormulaClass		209
%FieldType	198	%FormulaDescription		209
%FieldUserOptions	198	%FormulaExpression		209
%FieldValidation	198	%FormulaExpressionCase		209
%FieldValues	198	%FormulaExpressionFalse		209
%File	193, 196	%FormulaExpressionOf		209
%File32BitOnly	193, 196	%FormulaExpressionTrue		209
%FileBindable	193, 196	%FormulaExpressionType		209
%FileCreate	193, 196	%FormulaInstance		209
%FileDescription	193, 196	%Key193,	, 196,	199
%FileDriver	193, 196	%KeyAuto		199
%FileDriverParameter	193, 196	%KeyDescription		199
%FileEncrypt	193, 196	%KeyDuplicate		199
%FileExternal	193, 196	%KeyExcludeNulls		199
%FileExternalModule	193, 196	%KeyField		199
%FileIdent	193, 196	%KeyFieldSequence		199
%FileKey	199	%KeyFile		199
%FileKeyField	199	%KeyID		199
%FileKeyFieldLink	199	%Keyldent		199
%FileLastModified	193, 196	%KeyIndex		199
%FileLongDesc	193, 196	%KeyLongDesc		199
%FileName	193, 196	%KeyName		199
%FileOwner	193. 196	%KeyNoCase		199

%KeyPrimary199	%ProcedureExported	205
%KeyQuickOptions199	%ProcedureIsGlobal	205
%KeyStatement199	%ProcedureLanguage	205
%KeyStruct199	%ProcedureLongDescription	205
%KeyUserOptions199	%ProcedureReadOnly	205
%LocalData205	%ProcedureReturnType	205
%LocalDataFull205	%ProcedureTemplate	205
%LocalDataID205	%ProcedureTimeChanged	205
%LocalDataStatement205	%ProcedureTimeCreated	205
%MenuBarStatement205	%ProcedureToDo	205
%Module204	%ProcedureType	205
%ModuleBase204	%Prototype	205
%ModuleChanged204	%Relation193, 196,	199
%ModuleData204	%RelationAlias	199
%ModuleDataFull204	%RelationConstraintDelete	199
%ModuleDataID204	%RelationConstraintUpdate	199
%ModuleDataStatement204	%RelationKey	199
%ModuleExtension204	%RelationKeyField	199
%ModuleExternal204	%RelationKeyFieldLink	199
%ModuleInclude204	%RelationPrefix	199
%ModuleLanguage204	%RelationQuickOptions	199
%ModuleProcedure204	%RelationUserOptions	199
%ModuleReadOnly204	%Report	206
%ModuleTemplate204	%ReportControl	206
%Null214	%ReportControlField	206
%OtherFiles212	%ReportControlIndent	206
%OutputColumn214	%ReportControlInstance	206
%OutputIndent214	%ReportControlLabel	206
%OutputOffset214	%ReportControlOriginal	206
%Primary212	%ReportControlStatement	206
%PrimaryInstance212	%ReportControlTemplate	206
%PrimaryKey212	%ReportControlType	206
%Procedure205	%ReportControlUse	206
%ProcedureCalled205	%ReportStatement	206
%ProcedureDateChanged205	%Secondary	212
%ProcedureDateCreated205	%SecondaryTo	212
%ProcedureDescription205	%SecondaryType	212

%StandardAcceptedHandling #GROUP .224	Add to logical procedure tree124
%StandardControlHandling #GROUP226	add to multi-valued symbol - template 163
%StandardWindowCode #GROUP217	add to source file163
%StandardWindowHandling #GROUP219	add-in utilities - template2
%'symbol189	Adding New Template Sets11
%ToolbarStatement205	adding your own features10
%True214	Additional Language Support 184
%UtilityArguments214	ADJUST165
%ViewFile198	AFTER 160, 163
%ViewFileField198	aligned target language comments 161
%ViewFileFields198	assign value to a user-defined symbol 165
%ViewFiles193, 196, 198	asterisk (*) 171
%ViewFileStruct198	AT 163
%ViewFileStructEnd198	attribute string delimiter position 177
%ViewFilter193, 196	BEFORE 160, 163
%ViewJoinedTo198	Begin conditional source - template 165
%ViewPrimary193, 196	Break out of a loop - template 163
%ViewPrimaryField193, 196	Built-in Symbols 190
%ViewPrimaryFields193, 196	Built-in Symbols - template 2
%ViewStatement193, 196	built-in template functions 163, 165
%ViewStruct193, 196	Built-in Template Procedures99
%ViewStructEnd193, 196	Call listbox formatter 115
%Win32214	Call named #GROUP as a function 171
%Window205	Call Open File dialog 120
%WindowEvent205	Call Save File dialog126
%WindowStatement205	changes to the template code files 10
*171	check boxes4
*.TPL2	Check boxes - template 7
*.TPW2	CLEAR 160, 163
.TPL9, 10	code template 6, 163, 227
.TPW9, 10	ControlValueValidation227
.TXA file format160	code templates2, 3
Abort source generation - template161	command buttons4
Access to the embed points6	Command buttons - template7
Actions dialog - template7	comment block10
Actions popup menu6	comment column160
Actions dialog163	

Commit conditional source generation -	Disable prompts	160
template165	Display radio buttons	122
COMPONENT106	DROP	108
COMPONENT (list of KEY fields)106	DROP (droplist of items)	108
conditional control structures - template2	Droplist of items	108
Conditional source line - template141	EDIT - single line TEXT box - PROMF	PT. 109
conditionally replace source file165	edit the template source code	
continuation189	EMBED	
Control107	EMBED (enter embedded source)	110
CONTROL (list of window fields)107	Embed point existence - template	
Control prompts163	Embed Points	
control template160, 231	EMBEDBUTTON	
DOSFileLookup231	Embeds button	
control templates2, 3, 6	Enable/disable prompts	
CONTROLS160	entry controls	
Create source file - template160	EVALUATE()16	
custom code6	EXISTS	-
custom dialog boxes4	EXISTS (return embed point existence	
customizations4	expand a symbol	•
customize the templates2	Expansion Symbols	
Customizing Default Templates10	EXPR	
CW.TPL9	EXPR (appended data fields)	
Cycle to top of loop - template160	extension template	
Data Dictionary Interface8	DateTimeDisplay	
declare a user-defined symbol - template160	extension templates	
declare and assign value to a user-defined	EXTRACT	
symbol163	EXTRACT (return attribute)	
default procedure starting point160	FIELD	
default procedures	FIELD (list of data fields)	
Default report structures - template165	FILE	
Defaults in the Template Registry9	FILE (list of files)	
delete a multi-valued symbol instance160	File Driver Symbols	
delete a source file165	file existence	
delete multiple multi-valued symbol instances160	File lookup code - template	
Delimit conditional source - template165	File Schematic Symbols	
dependent symbols - template160	FileDrop control template	
DESCRIPTION160, 163	FILEEXISTS	166

FILEEXISTS (return file existence)166	List of choices for input - template 7
FIRST160, 163	List of data fields112, 113, 121
fix a multi-value symbol - template165	List of files 114
FORMAT115	List of KEY fields106
FORMAT (call listbox formatter)115	List of keycodes119
Format a symbol189	List of keys118
Formula Symbols209	List of symbol values116
FROM116, 163	List of window fields107
FROM (list of symbol values)116	Listbox formatter 115
FULLNAME (return file path)168	matched set of controls
HIDE163	Miscellaneous Symbols 214
HLP160, 163	modulus division operator % - used in
HSCROLL165	template language163, 165
ICON call Icon selection dialog117	Modulus operator235
INLINE163	MULTI 160, 163
INLIST169	multi-valued symbol instances 172
INLIST (return item exists in list)169	multi-valued symbols190
input from the developer - template2	Named #SECTIONS 165
INSTANCE170	Open File dialog - template language 120
INSTANCE %symbol160, 170	OPENDIALOG 120
INVOKE171	OPENDIALOG (call Open File dialog) 120
Built-in Template function171	OPTFIELD 121
INVOKE (call a named #GROUP as a	OPTFIELD (optional text or data field) 121
function)171	OPTION 122
item exists in list169	OPTION - template language 122
ITEMS172	ORDINAL 160
ITEMS (return multi-valued symbol instances)172	ORIG160
KEY118	Page of prompts163
KEY (list of keys)118	parameters passed 171
KEYCODE119	percent (%) 189
KEYCODE (list of keycodes)119	percent sign (%)4
LAST160, 163	PICTURE 123, 189
line continuation character189	PICTURE (call picture formatter) 123
LINK160	positioning of the control160
LINKNAME173	pound (#) 189
LINKNAME (return mangled procedure	Pre-defined template variables 2
name)173	pre-processes the templates 10

Pre-Processing and Source Code	return attribute	165
Generation5	return attribute string delimiter position	177
pre-processing template code5	Return embed point existence - template	166
PRIMARY160, 163	return file existence	166
print a source file165	return from #GROUP	165
PRIORITY160, 163	return item exists in list	169
PROCEDURE124	return multi-valued symbol instances	172
PROCEDURE (add to logical procedure tree)124	return symbol existence	184
PROCEDURE attribute233	return template registration	175
Procedure Properties dialog4, 6, 10	ROUTINE	163
procedure template2	Save File dialog	126
Procedure templates3	SAVEDIALOG	126
PROMPT entry types7	SAVEDIALOG (call Save File dialog)	126
Prompt group box - template163	SECTION160,	163
QUOTE174	SEPARATOR	177
QUOTE - template language174	SEPARATOR (return attribute string delimiter position)	177
RADIO125	SEQ	
RADIO (one radio button)125	Setup prompt symbols	
Radio button125	SHOW	
radio buttons4	Show on Properties box	
Radio buttons - template7	SINGLE	
Regenerate button10	SLICE	
re-generated templates from the registry2	SLICE (return substring from string)	
REGISTERED175	sorted insert - template	
REGISTERED (return template registration)	source code generation time	
175	SPIN	
Registry Options dialog10	SPIN (spin box)	
REGISTRY.TRF2, 9	SPLIT	
RELEASE165		103
REPLACE175	SPLIT - seperate single line string to multiple lines	183
REPLACE (replace attribute)175	standard customizations	4
replace attribute175	String Slicing	. 177
REPORT160	super-fix multi-value symbols	165
Report Control Symbols206	symbol	
REQ160, 163	symbol existence	
Re-register When Changed10	Symbol Hierarchy	
RETAIN165	Symbol Hierarchy Overview	
	- · · · · · · · · · · · · · · · · · · ·	

Symbol Management Statements160	TEXT (text box)	. 128
Symbols - Miscellaneous214	TIMER attribute	. 233
Symbols Dependent on %Field198	union operation - template	. 163
Symbols Dependent on %File193, 196	UNIQUE	. 160
Symbols Dependent on %Formula209	UNQUOTE	. 184
Symbols Dependent on %Key199	UNQUOTE template language	. 184
Symbols Dependent on %Procedure205	UNSPLIT	. 184
Symbols Dependent on %Report206	UNSPLIT - merge multiple line string to	
Symbols Dependent on %ViewFiles198	single line	
Symbols Dependent on %Window205	update the registry	
TAILNAME184	User Options	
target language - template2	user-defined symbol - template	
target language source code4	Value-parameters	. 171
targets for control and extension templates 6	VAREXISTS	. 184
Template170	VAREXISTS (return symbol existence) .	. 184
INSTANCE170	Variable-parameters	. 171
Template Built-In Procedures99	WAIT	. 165
Template code files9	What Templates Are	2
Template controls231	What Templates Do	4
Template Prompts7	WHENACCEPTED	. 163
Template Properties dialog10	WHERE	. 163
Template Registry9, 10, 11	WIN32	. 165
template registry file2	WINDOW - template attribute	. 160
Template set11	Window Control Symbols	. 205
Template Types3	Window Definition Template GROUPs 219, 224, 226	217,
template variable (symbol)4	Window Formatter	6
Templates - Using Clarion Language184	WRAP	. 160
TEXT 128		