Controller Synthesis

DESKTOP-H800RKQ

November 14, 2024

Contents

1	Loop Shaping	1
2	Integral Control	2
3		
4	PID Controller	4

1 Loop Shaping

Translating control specifications of the closed loop system into constraints of the Bode plots of the open loop system is loop shaping.

The steps involved in loop shaping are:

- 1. turn specifications from the time domain behaviour of F(s) to the frequency domain behaviour of L(s)
- 2. design the transfer function of the controller C(s) so that L(s) = C(s)G(s) has the desired frequency domain behaviour

For robust stability, a high K_m and high ϕ_m are desirable.

Delay is negative phase shift, which can decrease the phase margin and so $\phi_m > 0$ may no longer hold.

Integral action in a controller, that is some L(s) where

$$L(s) = \frac{\mu}{s^{\rho}}$$

gives a steady state gain of 1 in the closed-loop system.

Low bandwidth gives a slow response, high bandwidth gives a fast response.

The crossover frequency ω_c helps find which frequencies pass through and which get attenuated. Frequencies within the crossover frequency are within the bandwidth and frequencies above the crossover frequency are not within the bandwidth. This is because the bandwidth of F(s) (the closed-loop transfer function) is approximated by the crossover frequency of L(s) (the open-loop transfer function).

The closed-loop transfer function F(s) is approximated by 1 for $\omega \ll \omega_c$ of L(s) and L(s) for $\omega \gg \omega_c$ of L(s).

The **lower bound** on ω_c of L(s) is used to filter out noise, not the reference. The disturbance signals contain low frequencies and noise signals contain high frequencies.

Consider a system with open-loop transfer function L(s) = C(s)G(s) and corresponding closed loop transfer function F(s). To reject disturbance:

$$\left| \frac{G(j\omega)}{1 + C(j\omega)G(j\omega)} \right|$$

which is the lower bound on ω_c for L(s), should be kept low for ω contained in D, specifically low frequencies.

To attenuate noise:

$$\left| \frac{C(j\omega)G(j\omega)}{1 + C(j\omega)G(j\omega)} \right|$$

which is the upper bound on ω_c for L(s), should be kept low for ω contained in N, specifically high frequencies.

For L(s) = C(s)G(s), where C(s) is proper (in order to be realizable in state-space form), the slope of $|L(j\omega)|$ should be at most the slope of $|G(j\omega)|$ as $\omega \to \infty$.

2 Integral Control

For a closed-loop system with open loop transfer function L(s) = C(s)G(s), for $C(s) = \frac{\mu}{s\rho}$:

- if $\rho > 0$, there is an integrator in the loop, so the closed-loop transfer function F(s) has F(0) = 1
- if $\rho = 0$, there is no integrator in the loop, so μ must be high for F(0) to approach 1

3 Lead-Lag Compensators

3.1 Lead Controller

Consider a controller with transfer function

$$C(s) = \mu \frac{1 + Ts}{1 + \alpha Ts}$$

for $\mu > 0, T > 0, 0 < \alpha < 1$. This controller has a zero at $-\frac{1}{T}$ and a pole at $-\frac{1}{\alpha T}$, which adds a phase lead between the zero and the pole, which is an increase in the phase margin.

This controller has high frequency gain $\frac{\mu}{\alpha}$. A good value of α is 0.1, since this gives a 55° phase lead.

As $\alpha \to 0$, C(s) becomes $\mu(1+Ts)$. When $C(s) = \frac{E(s)}{U(s)}$, then this gives that the control action u(t) is made of 2 terms:

$$u(t) = \mu e(t) + \mu T \frac{de}{dt}(t)$$

where one term is proportional to the error and the other is proportional to the time derivative of the error, so this is a PD controller. For a noncontinuous space, the control action can be written as

$$u(t_k) = \mu e(t_k) + \mu T \frac{e(t_k) - e(t_{k-1})}{t_k - t_{k-1}}$$

Adding poles/zeros makes the controller realizable to get this approximation of the derivative until the frequency of the pole of error.

3.2 Lag Controller

Consider a controller with transfer function

$$C(s) = \mu \frac{1 + Ts}{1 + \alpha Ts}$$

for $\mu > 0, T > 0, \alpha > 1$. This controller has a zero at $-\frac{1}{T}$ and a pole at $-\frac{1}{\alpha T}$, which adds a phase lag between the zero and the pole, which is an decrease in the phase margin. The lag controller helps to improve static performance without losing stability.

A good value of α is 10. For $\frac{10}{T} < \omega_c$, this gives -6° at ω_c . At $\mu = \alpha$, the high frequency behaviour is unchanged. For $\mu = 1$, there is a lower ω_c and which increases ϕ_m . As $\alpha \to \infty$, the corresponding increase of the steady-state gain μ such that $\frac{\mu}{\alpha} = c$ is constant, gives the lag controller

$$C(s) = c + \frac{c}{Ts}$$

which is a PI controller.

4 PID Controller

Placing the zero and pole of a lead controller $1/\alpha$ decade away from ω_c requires

$$\omega_c = \frac{1}{\sqrt{\alpha}T}$$

$$\zeta pprox rac{\phi_m}{100}$$

so if ϕ_m increases, there are less oscillations and less overshoot for the closed loop system.

For a lag controller, as $\alpha \to \infty$, the pole $-\frac{1}{\alpha T} \to 0$.