

Use Case 4: Lifecycle Management

Scenario: Optimize storage costs.

Tasks:

- o Implement S3 lifecycle policies for transitioning objects to Glacier.
- o Set up cross-region replication for compliance requirements.

Step 1: Prerequisites

1. Setup S3 Buckets:

- o Create an S3 bucket for primary storage (e.g., source-bucket).
- o Create a destination bucket in another AWS region for cross-region replication (e.g., destination-bucket).

2. IAM Role and Permissions:

- Ensure the appropriate IAM role has permissions to access and manage S3 object

3. Bucket Versioning:

- Enable **versioning** on both the source and destination buckets. Versioning is a prerequisite for lifecycle policies and cross-region replication.

Step 2: Implement S3 Lifecycle Policies for Cost Optimization

Lifecycle policies help optimize storage costs by automatically transitioning data to cheaper storage classes and eventually expiring unused objects.

1. Navigate to the S3 Console:

- Open the **source-bucket**.
- Go to the **Management** tab.
- Click on **Create lifecycle rule**.

2. Configure the Lifecycle Rule:

- **Rule Name:** Name the rule (e.g., TransitionToGlacier).

- **Scope:** Choose whether the rule applies to the entire bucket or a specific prefix (e.g., logs/).

3.Transition Actions:

- Add rules for transitioning objects:
 - Transition to **S3 Standard-IA** after 30 days (for infrequently accessed data).
 - Transition to **S3 Glacier** or **S3 Glacier Deep Archive** after 90 days.

4.Save the Rule:

- Activate the lifecycle policy.

Step 3: Set Up Cross-Region Replication for Compliance

Replication ensures data availability and durability across regions for compliance or disaster recovery.

1.Navigate to the S3 Console:

- Open the **source-bucket**.
- Go to the **Replication Rules** section under the **Management** tab.
- Click **Create replication rule**.

2.Replication Rule Configuration:

- **Rule Name:** Name the rule (e.g., ComplianceReplication).
- **Source Bucket:** Select source-bucket.
- **Destination Bucket:** Select the destination-bucket in a different region.
- **Choose Storage Class for Replicated Objects:**
 - Use **S3 Standard-IA** or **S3 Glacier** for replicated objects to reduce costs.

3.Filter Scope:

- Replicate either the entire bucket or specific prefixes (e.g., compliance/).

4.Encryption:

- Ensure **server-side encryption (SSE-S3 or SSE-KMS)** is enabled for both source and destination buckets.

5.Permissions:

- Assign the replication IAM role created earlier.

6.Replication Status Monitoring:

- Enable metrics and replication status events to monitor replication progress.

Step 4: Security Optimizations

1. **Encrypt Data at Rest:**

- Enable **SSE-S3 (AES-256)** or **SSE-KMS** encryption for objects in both buckets.

2. **Encrypt Data in Transit:**

- Use **HTTPS** for all data transfer between the source and destination.

3. **Restrict Bucket Access:**

- Use **bucket policies** to limit access based on:
 - IP addresses (e.g., restrict access to trusted IP ranges).
 - Specific IAM roles or users.

4. **Enable MFA Delete:**

- Protect versioned objects from accidental deletion by enabling **MFA Delete**.

5. **Monitor and Audit:**

- Enable **AWS CloudTrail** to log all S3 bucket activities.

- Use **AWS Config** to enforce compliance rules (e.g., ensuring buckets are versioned).
-

Step 5: Test and Validate

1. Test Lifecycle Policy:

- Upload objects to the bucket and monitor their transitions to different storage classes over time.

2. Test Replication:

- Verify that objects in the source-bucket are replicated to the destination-bucket.
- Check for replication status in the S3 console.

3. Cost Monitoring:

- Use **AWS Cost Explorer** to monitor storage costs.

4. Security Audit:

- Conduct a security audit using **AWS Trusted Advisor** to ensure best practices are followed.

