



Paiflow

● STELLAR TESTNET

Alpha Testing Guide

Thanks for helping test Paiflow. This guide takes you from an empty wallet to deploying and running real payment flows — no coding needed.

~45 min

END TO END

10 min

SETUP

7

TEST CASES

REPORT A BUG ↗

FEEDBACK SURVEY ↗

What Paiflow is

A visual builder for payments. You drag a trigger (“when money arrives”) and an action (“pay this person”, “split it”, “swap it”) onto a canvas, press **Deploy**, and Paiflow turns that into real smart contracts on the Stellar network.

It is non-custodial: you sign every transaction yourself, in your own wallet, and Paiflow never holds your keys.

This guide takes about **45 minutes** end to end: 10 minutes of setup, then a set of short test cases. You don't need to know how to code.

TESTNET ONLY

Everything in this round runs on Stellar testnet. Testnet money is free and worthless. You will never be asked for real funds, a card, or a seed phrase. If anything ever asks you for one, stop and report it.

CONTENTS

1 Before you start

Install Freightier, get free testnet XLM, create two recipient accounts.

2 Sign in to your test account

Use the username and password we sent you.

3 A quick tour of the builder

The parts of the screen you'll use in every test.

4 Test cases

T1–T7: swap, pay, split, and free exploration.

5 What not to test in this round

Features that aren't ready yet.

6 Known issues

Already on our list — no need to report.

7 Troubleshooting

Common messages and what to do.

8 Reporting a bug

The bug report form and the feedback survey.

01 Before you start

You need: a desktop or laptop with **Chrome** or **Brave**. Phones are not part of this round.

1.1 Install Freighter and switch it to testnet

- 1 Install the [Freighter wallet extension](#) and pin it to your toolbar.
- 2 Open Freighter → **Create new wallet**. Write down the recovery phrase somewhere safe — even for a test wallet, you'll want it if the extension gets reset.
- 3 In Freighter, open the network menu at the top and choose **Testnet**.

☐ Freighter shows **Testnet** at the top.

1.2 Fund your wallet with free testnet XLM

A brand-new Stellar account doesn't exist on the network until it holds some XLM. Friendbot is Stellar's free testnet faucet.

- 1 In Freighter, copy your address (it starts with `G`).
- 2 Open this link in a new tab, replacing `YOUR_ADDRESS` :
`https://friendbot.stellar.org/?addr=YOUR_ADDRESS`
(Freighter may also show a **Fund with Friendbot** button — that does the same thing.)

☐ Freighter shows a balance of **10,000 XLM**.

This account is your **Main** account. You'll deploy and trigger flows with it.

1.3 Create two recipient accounts

Your flows need somebody to pay. You'll pay yourself, into two extra accounts.

- 1 In Freighter, open the account menu → **Add a new wallet** (or **Create account**). Name it **Recipient A**.
- 2 Fund it with Friendbot exactly as in step 1.2.
- 3 Repeat for a third account named **Recipient B**.
- 4 Paste all three `G...` addresses into a note — you'll copy them into Paiflow later.

☐ Main, Recipient A and Recipient B all show 10,000 XLM.

1.4 Let Recipient A hold USDC

Some tests swap XLM into USDC (a testnet dollar token). A Stellar account has to opt in to a token before it can hold it — this is called adding a **trustline**.

- 1 In Freighter, switch to **Recipient A**.
- 2 Open **Manage assets** → **Add an asset** (the wording varies slightly by Freighter version).
- 3 Search for **USDC**, and pick the one whose issuer is `GBBD47IF6LWK7P7MDEVSCWR7DPUWV3NY3DTQEVFL4NAT4AQH3ZLLFLA5`. Confirm and sign.
- 4 Switch Freighter back to **Main**.

☐ Recipient A lists **USDC** with a balance of 0.

NOTE

Leave Recipient B **without** a USDC trustline.

02 Sign in to your test account

We'll send you a **username** and **password** for your test account.

- 1 Go to beta.paiflow.xyz and open the login page.
- 2 Enter your **Username** and **Password**, then click **SIGN IN**.

- ☐ You land on your dashboard ("Your flows.").
- ☐ One flow is already there: **Swap XLM to USDC**.

TIP

Bookmark each deployment page you create, so you can find it quickly for a bug report.

03 A quick tour of the builder

Open **Swap XLM to USDC**. Take a minute to find each of these — you'll use them in every test.

Blocks LEFT SIDEBAR

The palette. Drag a block onto the canvas. Triggers, Actions and Logic are grouped.

Canvas CENTRE

Your flow. Drag from one block's handle to another to connect them. Select a block and press Delete to remove it.

Settings panel

Click any block on the canvas to open its settings.

English Preview TOP

Your flow written out as a sentence. **Always read it before deploying** — it's the plain-language check on the money.

Errors button

Appears when something's wrong. Click it to list every problem. Fields with problems are also highlighted.

DEPLOY button

Greyed out until the flow has no errors.

Dev mode switch

Leave this off for every test.

Flow title

Click it to rename the flow. Changes save automatically; there is no Save button.

ONE TRIGGER PER FLOW

A flow always starts with exactly **one trigger**. Once you have one, the other triggers grey out.

04 Test cases

Do them in order — later tests reuse accounts and flows from earlier ones. For each one, tick the boxes as you go. **If a box doesn't match what you see, report it** with the [bug report form](#), unless it's listed under [known issues](#).

WHERE TO CHECK THAT MONEY REALLY MOVED

- The **live event feed** on the deployment page.
- **Freighter**: switch to the recipient account and look at its balance.
- **stellar.expert**: every deployment page links its contract to [stellar.expert/explorer/testnet](#), where you can see each transaction.

T1 Deploy and run the ready-made swap flow

GOAL The core of this round. Receive XLM, swap it to USDC on a real exchange (Soroswap), and pay it out.

- 1 Open **Swap XLM to USDC**. Don't change anything.
- 2 Read the **English Preview**.
 - ☐ It describes receiving XLM, swapping to USDC, and paying it out.
- 3 Click the **Swap** block.
 - ☐ Router shows **Soroswap (testnet)** and can't be changed.
 - ☐ A live quote appears, like *"10 XLM → ~1.05 USDC via Soroswap (live)"*, with a minimum amount under it.
- 4 Click **DEPLOY**. You're taken to **Review & deploy**.
 - ☐ A **TESTNET** chip is shown.
 - ☐ The page says how many contracts it will create, and shows the swap quote again.
- 5 Click **DEPLOY TO TESTNET**. Freighter pops up — check it says testnet, then **sign**.
 - ☐ A "Contract deployed" message appears and you're taken to the deployment page.
 - ☐ Within about a minute the status becomes **ACTIVE** and a QR code appears.
- 6 **Bookmark this page**. Click **OPEN TRIGGER PAGE**.
- 7 Enter **10** as the amount, click **CONFIRM AMOUNT**, then **CONNECT WALLET & TRIGGER**. Sign in Freighter (with your **Main** account).
 - ☐ You see progress messages ending in a success message.

8 Go back to the deployment page and watch the live event feed.

☐ A **RECEIVE** row for 10 XLM appears.

☐ A **PAYOUT** row for the swap shows amount in (XLM) and amount out (USDC), and the USDC amount is close to the quote from step 3.

☐ On stellar.expert, the trigger transaction shows a Soroswap **swap**.

This first flow pays a shared Paiflow demo account, so you won't see the USDC yourself — T2 fixes that.

T2 Swap into your own account

GOAL Confirm the swapped USDC lands where you told it to.

1 Back on the dashboard, open **Swap XLM to USDC** again.

2 Click the **Pay** block and replace the recipient with **Recipient A**'s address.

☐ The English Preview now shows Recipient A's address (shortened).

3 Deploy it (steps 4–5 of T1), then trigger it with **20 XLM** (steps 6–7 of T1).

☐ The live feed shows RECEIVE and PAYOUT rows.

4 In Freighter, switch to **Recipient A**.

☐ Recipient A now holds **about 2 USDC** (close to the quote).

5 Switch Freighter back to **Main**.

T3 The swap block refuses bad settings

GOAL Check that mistakes are caught *before* anything is deployed. You won't deploy in this test.

Open **Swap XLM to USDC** and try each change below. After each one, check the boxes, then **undo the change** before trying the next.

TRY	EXPECTED
a Set Asset Out to XLM (same as Asset In).	An error saying a swap has to exchange two different assets.
b Set Max slippage to 0.1 .	An error saying slippage must be at least 0.3% because of Soroswap's pool fee.

- | | | |
|----------|--|--|
| c | Set Deadline to 0 , then to 100000 . | The field refuses the value (the allowed range is 1–86,400 seconds). |
| d | Delete the connection between Swap and Pay . | An error saying a swap needs one next step. |
| e | Drag in a second Pay block and connect Swap to it too. | An error saying a swap sends its output to only one next step. |

FOR EVERY ROW

- ☐ The error is easy to understand and says how to fix it.
- ☐ **DEPLOY** is greyed out while the error is there.
- ☐ The error goes away once you undo the change.

T4 Receive XLM, pay a fixed amount

GOAL The simplest flow — money in, money out to one person.

- 1 On the dashboard, click **NEW FLOW**, name it **T4 Pay**, and click **CREATE FLOW**.
- 2 The new flow comes with an example (receive USDC, split to Alice / Bob / Charlie). Those are placeholder accounts that can't receive money, so **delete both blocks**.
- 3 Drag in **On Receive**. In its settings, set Asset to **XLM (native)**.
- 4 Drag in **Pay** and connect On Receive → Pay. In Pay's settings:
 - Asset: **XLM**
 - Recipient: **Recipient B's** address
 - Amount mode: **Fixed**, amount **5**☐ English Preview reads roughly: *when this contract receives XLM, pay 5 XLM to G...*
- 5 Deploy it and trigger it with **5 XLM**.
 - ☐ Live feed shows RECEIVE then PAYOUT.
 - ☐ Recipient B's XLM balance in Freighter went up by 5.
- 6 Open the flow again, change Pay to **Send full amount**, deploy, and trigger with **12 XLM**.
 - ☐ Recipient B's balance went up by 12.

T5

Receive XLM, split it between two people

GOAL Fan one payment out to several recipients.

- 1 **NEW FLOW** → name it **T5 Split**. Keep the example's two blocks this time.
- 2 Click **On Receive** and change Asset to **XLM (native)**. Click **Split** and change its Asset to **XLM**.
- 3 In Split, use **Percentage** mode with exactly two recipients:
 - Recipient A — **70%**, label **A**
 - Recipient B — **30%**, label **B**

☐ The allocation bar is full, and the English Preview shows 70% and 30%.
- 4 Deploy and trigger with **10 XLM**.
 - ☐ Live feed shows RECEIVE and two PAYOUT rows.
 - ☐ Recipient A received 7 XLM and Recipient B received 3 XLM.

Now try to break it (no need to deploy — just check the error, then undo):

	TRY	EXPECTED
a	Change 30% to 20% .	An error saying the percentages don't add up to 100%.
b	Set both recipients to Recipient A's address.	An error about a duplicate address.
c	Leave a recipient address empty, or type he llo .	The field is highlighted as invalid.

- ☐ Each error is clear, and DEPLOY stays greyed out until you undo it.

T6

Split USDC (uses the USDC from T2)

GOAL The same split, with a token instead of XLM, and a recipient that can't accept it.

- 1 **NEW FLOW** → **T6 USDC split**. Keep the example's **On Receive (USDC)** → **Split (USDC)**.
- 2 Replace the three recipients with a single one: **Recipient A, 100%**.
- 3 Deploy with **Main** as usual.

- 4 Open the trigger page. **Switch Freightier to Recipient A** (it holds the USDC from T2), enter **1**, and trigger.
- ☐ Live feed shows RECEIVE 1 USDC and a PAYOUT of 1 USDC.
- 5 Now change the flow so the single recipient is **Recipient B** (no USDC trustline), deploy, and trigger with **1 USDC** from Recipient A again.
- ☐ The trigger is refused **before** you're charged, with a message you can make sense of.
 - ☐ Recipient A still has its USDC.

Switch Freightier back to **Main** when you're done.

T7 Free exploration (10 minutes)

Build any flow you like using **On Receive**, **Pay**, **Split** and **Swap** — for example receive XLM → swap to USDC → split to two accounts that both have a USDC trustline. Deploy it, trigger it, and tell us what felt confusing, slow or surprising. There are no wrong answers here.

05 What not to test in this round

These features are in the app but aren't ready for alpha testing yet. You may see them in the palette or on a page — **please don't use them this round, and don't report problems with them.**

On Schedule, HTTP Webhook, Subscription and Payroll triggers — build your flows with **On Receive** only.

NOT THIS ROUND

Condition block

NOT THIS ROUND

Email Notify block — don't add it to a flow.

STILL BEING FINISHED

Fiat / bank payout in Pay and Split, and **Sender KYC** — keep payouts on **Crypto (wallet)**.

NOT THIS ROUND

Dev mode switch — leave it off.

NOT THIS ROUND

Ask AI (chat and voice)

NOT THIS ROUND

API access panel on deployment pages (developer API tokens)

NOT THIS ROUND

Passkeys on the Profile page — sign in with your username and password.

NOT THIS ROUND

Phones and mobile wallets (LOBSTR, xBull) — use desktop Freightier.

NOT THIS ROUND

06 Known issues

Already on our list — no need to report these.

The trigger page can report a failure even though the payment went through. Before reporting a failed trigger, check the live event feed and stellar.expert. Only report it if the money really didn't move.

The trigger page doesn't keep a record of a successful trigger after the message disappears. Use the deployment page's live feed instead.

The review page lists several wallets (Freightier, Albedo, xBull, LOBSTR, Hana), but only **Freightier** works for deploying right now.

The example flow created by NEW FLOW pays placeholder accounts (Alice, Bob, Charlie) that can't receive money. Always replace them with your own recipients.

The live feed can lag a few seconds to a minute behind the chain. Give it a minute before reporting a missing row.

07 Troubleshooting

YOU SEE

"Account ... is not funded" or "Minimum 2 XLM required"

TRY

Fund the account in Freighter with Friendbot (step 1.2).

YOU SEE

A Freighter network error, or the signature fails

TRY

Check Freighter is on **Testnet**, then try again.

YOU SEE

An error mentioning a **trustline**

TRY

The account receiving USDC hasn't added USDC yet (step 1.4).

YOU SEE

DEPLOY greyed out

TRY

Click the **Errors** button above the canvas and fix each item.

YOU SEE

"Invalid username or password"

TRY

Check both, including capital letters. After 5 wrong tries the account locks for 15 minutes — wait, then try again.

YOU

Forgot your password

TRY

There's no reset link yet. Contact us — the same people who sent you your test account — and we'll reset it.

YOU SEE

No Freighter pop-up

TRY

Click the Freighter icon in your toolbar — the request may be waiting there.

08 Reporting a bug

Bug report form

One form per bug, please.

forms.gle/c7AmbU61XbGpCPVXA ↗

Feedback survey

When you're finished (3–4 minutes). It's the most useful thing you can give us.

forms.gle/hdmpGNwUi6oh6stv6 ↗

It helps to have these ready before you open the bug report form:

- ☐ the test and step you were on (e.g. T5, step 4);
- ☐ the exact error message, if there was one;
- ☐ the deployment page URL, and the transaction link on stellar.expert if you have one;
- ☐ a screenshot or screen recording.

Thank you!