Oracle® Data Integrator

Getting Started with SAP ABAP ERP Adapter 10g Release 3 (10.1.3)

November 2009

Oracle Data Integrator: Getting Started with SAP ABAP ERP Adapter, 10g Release 3 (10.1.3)

Copyright © 2009, Oracle. All rights reserved.

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software--Restricted Rights (June 1987). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

Oracle, JD Edwards, PeopleSoft, and Siebel are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

Table of Contents

| Introduction | 4 |
|---|----|
| Overview | 5 |
| Setting up the Environment | 6 |
| Before You Begin | 6 |
| Validating FTP Setup | 7 |
| Validating SAP Privileges | 8 |
| Installing Oracle Data Integrator | 8 |
| Installing and Configuring the Oracle DB Target | 8 |
| Installing and Configuring JCo | 9 |
| Setting up an FTP Server | 9 |
| Configuring Oracle Data Integrator | 9 |
| Configuring the Topology | 12 |
| Configuring the Oracle Data Server | 12 |
| Configuring the SAP Source Server | 13 |
| Create a New Project | 16 |
| Reverse-Engineering the Data Models | 17 |
| Reverse-Engineering the Oracle Target | 17 |
| Reverse-Engineering the SAP Source Datastores | 18 |
| Create the Integration Interface | 25 |
| Create the Interface | 25 |
| Define the Source and Target Datastores | 26 |
| Define Joins between Sources | 27 |
| Create the Mappings | 28 |
| Define the Interface Flow | 29 |
| Running the Integration Interface | 31 |
| Running the Interface | 31 |
| Review the Interface Execution | 31 |
| Review the Resulting Data | 32 |
| Conclusion | 33 |
| Going further with Oracle Data Integrator | 33 |
| Appendix | 34 |
| Appendix A - SAP ABAP ERP Required Privileges | 34 |
| Appendix B - SAP Stand-Alone Connection Test | 42 |
| Appendix C - Uninstalling ODI SAP Components | 44 |

Introduction

The purpose of this document is to provide you with an overview of the possibilities offered by SAP ERP Knowledge Modules and how to use them in Oracle Data Integrator.

This document provides examples to help you understand how to achieve an ETL project with Oracle Data Integrator, loading a Data Warehouse with data from SAP systems, while validating data quality.

This project should take approximately 90 minutes to complete. You may save your work in order to pause and resume at any point in the project.

It is recommended that you use Oracle Data Integrator before proceeding with this guide. A good introduction to Oracle Data Integrator is the guide *Oracle Data Integrator - Getting Started with an ETL Project*.

It is recommended that you also review the SAP ABAP chapter of the *Oracle Data Integrator Knowledge Modules Reference Guide* for more information about the SAP ERP KMs.

Overview

The Oracle Data Integrator SAP ABAP Knowledge Modules provide integration from SAP ERP systems using SAP JCo libraries. This set of KMs has the following features:

- Reads SAP data from SAP ERP system
- Loads this SAP data into Oracle Staging Area
- Reverse-engineers SAP metadata and proposes a tree browser to pick up only the required metadata

This adapter includes two knowledge modules:

- RKM SAP ERP: Its main role is to perform customized reverse-engineering of SAP tables
 into ODI datastores (Models). The SAP ERP RKM is in charge of connecting to the SAP
 System, which provides the SAP table's metadata information, and transforming and writing
 the resulting metadata into Oracle Data Integrator's repository.
- The LKM SAP ERP to Oracle (SQLLDR) connects to SAP and retrieves data from the SAP tables defined in the SAP Model. It is used in the interfaces. The LKM is in charge of loading source data from a SAP System to an Oracle staging area.

Setting up the Environment

Before You Begin

System Requirements and Certification

Before performing any installation you should read the system requirements and certification documentation to ensure that your environment meets the minimum installation requirements for the products you are installing.

The Oracle Data Integrator requirements are listed in the *Oracle Data Integrator Installation Guide* available from the Oracle Technology Network (OTN).

The requirements specific to the Oracle Data Integrator SAP ABAP Adapter are:

- The minimum patch level for Oracle Data Integrator 10gR3 is version 10.1.3.5.1_01 (Metalink Patch #8610114) or above.
- A JCo version compatible with adapter must be used. The list of supported JCo versions
 is available in the <u>Compatibility Matrix</u> available from the Oracle Technology Network
 (OTN). A minimum version of JCo 3.0.2 is required.
- A JVM version compatible with both Oracle Data Integrator and JCo must be used. A minimum version of JVM 1.5 is required due to JCo pre-requisites.
- LKM SAP ERP to Oracle (SQLLDR) requires a FTP server to upload data from the SAP ERP system. This data is either read locally by the agent executing the interface (when this agent runs on the FTP server machine), or remotely (when this agent is located on a different machine than the FTP server). This FTP server must be accessible over the network from both the SAP ERP machine and the agent machine.
- SQL*Loader is required on the machine running the agent the executed interfaces using LKM SAP ERP to Oracle (SQLLDR). SQL*Loader is used for loading data extracted from SAP to the Oracle staging area.

Getting the Right Privileges

The SAP Adapter requires privileges to perform set up and execution operations. Please provide your administrators with the list of privileges listed in *Appendix A – SAP ABAP ERP Required Privileges*. These privileges are required for the SAP user that they will provide you to login the SAP System.

Gathering SAP Connection Information

In order to connect to the SAP ERP system, you must request the following information from your SAP administrators:

- SAP ERP System IP Address or Hostname: IP address/ Hostname is the technical name given to the host on which SAP is running.
- SAP User: SAP User is the unique user name given to a user for logging on the SAP System.
- SAP Password: Case-sensitive password used by the user to log in.

- **SAP Language**: Code of the language used when logging in For example: EN for English, DE for German.
- **SAP Client Number**: The three-digit number assigned to the self-contained unit which is called *Client* in SAP. A Client can be a training, development, testing or production client or represent different divisions in a large company.
- SAP System Number: The two-digit number assigned to a SAP instance which is also called Web Application Server or WAS.
- SAP System ID: The three-character, unique identifier of a SAP system in a landscape.
- SAP SNC Connection Properties (optional) SAP Router String (optional): SAP is enhancing security through SNC and SAP router. It is used when these securities are implemented.

Note: All the connection data listed above (except SAP SNC Connection Properties and SAP Router String) are mandatory and should be requested from the SAP Administrators. You may consider requesting support during connection setup from your SAP administrators.

Validating FTP Setup

This section describes how to verify the FTP setup and needs to be performed before any subsequent steps in this guide can be performed. This validation is typically performed by your SAP Basis team.

Step 1: Validating SAPFTPA destination

- 1. Start the SAPGUI.
- 2. Use the ODI SAP user and password to connect to the SAP system and client.
- 3. Go to transaction SM59.
- 4. Expand TCP/IP connections.
- 5. Open the SAPFTPA destination.
- 6. Click Test connection.

This should report a successful connection. If not, please contact your SAP basis team. Do not continue until this test passes.

7. Print screen.

Step 2: Testing FTP connection

- 1. Go to transaction SE38.
- 2. View the function module RSFTP002.
- 3. Hit F8 to run the ABAP program.
- 4. Enter the FTP userID and password.
- 5. Enter the FTP server host name or IP address.
- 6. Enter cd / or cd <ODI target directory>.
- 7. In the RFC_DESTINATION field, enter SAPFTPA.
- 8. Hit F8 to run the test.

This should report a successful connection. Similar to this 250 CWD successful. "/" is current directory. If not, please contact your SAP basis team. Do not continue until this test passes.

9. Print screen.

Validating SAP Privileges

This section describes how to test some of the key SAP privileges. Proceed with the subsequent steps in this guide only after successful validation of these tests. This validation is typically performed by your SAP Basis team.

Please find the steps below to validate whether a SAP user has appropriate dev rights and owns a dev license key:

- 1. Start SAPGUI.
- 2. Use the ODI SAP user and password to connect to the SAP system and client.
- Go to transaction SE38.
- 4. Enter any sample program name like ZSAP_TEST in the program name field.
- 5. Click Create.
- 6. Perform similar tests for the transaction SE37 and SE11.

If a transaction allows the creation of a program without asking for any key or other authorization message, then the SAP user has validated that it has the appropriate dev rights and license key. Otherwise your SAP basis team needs to register the SAP user in service.sap.com to get the license key and a Basis person can help him with Dev rights.

Installing Oracle Data Integrator

Before starting with this project, you need to install and configure Oracle Data Integrator. Refer to the guide *Oracle Data Integrator - Getting Started with an ETL Project* and the *Oracle Data Integrator Installation Guide* for more information.

Installing and Configuring the Oracle DB Target

This project uses an Oracle database engine as the target and as the staging area for the integration interfaces. You can download for example an Oracle XE database from the <u>Oracle Technology Network</u> (OTN). Install and configure this database.

This project targets an Oracle table that can be created using the following script:

```
-- Create demo target schema
CREATE USER ODI_SAP_DEMO IDENTIFIED BY ODI_SAP_DEMO DEFAULT TABLESPACE
USERS TEMPORARY TABLESPACE TEMP;
GRANT CONNECT, RESOURCE TO ODI_SAP_DEMO;

-- Create demo target table
CREATE TABLE ODI_SAP_DEMO.W_GEO_DS (
    LANGUAGE_KEY CHAR(20),
    COUNTRY VARCHAR(50),
    COUNTY VARCHAR(50),
    STATE_PROV VARCHAR(50),
    NATIONALITY VARCHAR(50));

ALTER TABLE ODI_SAP_DEMO.W_GEO_DS ADD CONSTRAINT PK_W_GEO_DS PRIMARY
KEY (LANGUAGE_KEY);
```

Installing and Configuring JCo

The SAP adapter uses JCo to connect to the SAP system. JCo must be configured before proceeding with the project.

To install and configure JCo:

- Download a supported JCo version for your configuration from http://service.sap.com/connectors. Check the supported JCo version in the <u>Compatibility Matrix</u> available at Oracle Technology Network. Note that a minimum version of JCo 3.0.2 is required.
- 1. Unzip the appropriate distribution package into an arbitrary directory {sapjco-install-path}.
- 2. Follow the installation instructions in {sapjco-install-path}/javadoc/installation.html for the respective platform.
- 3. Copy sapjco3.jar and sapjco3.dll (or respective binary) into the oracledi/drivers directory.
- 4. Check the JCo installation. This will be also checked later in this guide.

Note: Changing the JCo library installed in the {windows-dir}\system32 directory of a machine running other SAP tools or components may cause issues with these components. Please check with your machine administrator before performing this change.

Setting up an FTP Server

The SAP adapter extracts SAP data and uploads it to an FTP server. Configure an FTP server or use an existing FTP server. You must create a user in this FTP server and a directory into which this user will be able to upload files.

Configuring Oracle Data Integrator

Set up the Topology

Perform the following operations after installing or upgrading your Oracle Data Integrator version:

- 1. Connect to Topology Manager.
- 2. If this SAP ABAP technology does not exist in your Master Repository, import the SAP ABAP technology in Synonym INSERT_UPDATE mode from the /impexp folder.
- 3. Perform an upgrade of the Master Repository. Refer to the <u>Oracle Data Integrator Installation Guide</u> on OTN for more information on the Master Repository upgrade process.
- 4. In Topology Manager, open the JavaBeanShell technology and check on the Language tab that the JYTHON language is listed. If not, add it.
- 5. Create a File data server pointing to an existing FTP server into which the extraction file will be pushed from SAP and picked up for SQL*Loader. Set the parameters for this data server as follows:
 - Host (Data Server): FTP server IP host name or IP address.

- User: Username to log into FTP server.
- Password: Password for the user.
- 6. In this File data server create a Physical Schema representing the folder in the FTP host where the extraction file will be pushed. Specify the Data and Work Schemas as follows:
 - Data Schema: Path on the FTP server to upload or download extraction files from the remote location. This path is used when uploading extraction files from the SAP ERP system into the FTP server. It is also used by a remote agent to download the extraction files. Note that this path must use slashes and must end with a slash character.
 - Work Schema: Local path on the FTP server's machine. This path is used by an
 agent installed on this machine to access the extraction files without passing via the
 FTP server. This access method is used if the FTP_TRANSFER_METHOD
 parameter of the LKM SAP ERP to Oracle (SQLLDR) is set to NONE. As Work
 Schema is an OS file name, slashes/ backslashes should be used according to OS.
 Path names need to end on slash/ backslash.

Path names given on Data and Work schemas are not necessarily the same: the FTP service may provide access to a FTP directory named /sapfiles while the files can be stored locally in c:\inetpub\ftproot\sapfiles.

Refer to the *File Transfer Configurations* section in the *SAP ABAP* chapter of the *Oracle Data Integrator Knowledge Modules Reference Guide*.


7. If the corresponding Logical Schema called File Server for SAP ABAP does not exist yet, create it. This Logical Schema name is fixed and must be mapped to the Physical Schema created in the previous step.

Add the Open Tool

The complete process of installing and adding an Open Tool to ODI is described in *the Oracle Data Integrator Tools Reference* guide. This section details only the SAP ABAP specific steps.

- 1. Connect to Designer.
- 2. Select File > Add/Remove Open Tools...
- 3. In the Add/remove Open Tools window, enter the following name in the Open Tool class name field:
 - oracle.odi.sap.km. OdiSapAbapExecute
- 4. Click Add Open Tool.

5. The Open Tool appears as shown below.



6. Click OK.


Configuring the Topology

This project will integrate the following source and target data:

- Source tables T005T and T005U are the tables from SAP containing geographical information.
- Target W_GEO_DS is a dimension table in an Oracle database that needs to be loaded from the SAP Sources. This table contains geographical information such as Continent name, Country name, Region, State, Country, City and Zip code.

Configuring the Oracle Data Server

- 1. Connect to Topology Manager.
- 2. In the Physical Architecture tree view, expand the Technologies node and select the Oracle technology.
- 3. Right-click and select Insert Data Server.
- 4. Enter the data server Definition as shown below:



5. Select the JDBC tab, and enter the JDBC connection information to your data server as shown below:



Make sure to change the URL to match your Oracle instance configuration.

- 6. Click **Test** to test the connection to this data server.
- 7. Click **OK** to save your data server.
- 8. In the Physical Schema windows that appears, select the ODI_SAP_DEMO for both Schema and Work Schema, as shown below:



If you already have a Work Schema for ODI defined for this data server, you can use it instead of the <code>ODI_SAP_DEMO</code> Schema.

- 9. Go to the Context tab.
- 10. Click Add and enter in the Logical Schema field the value ODI_SAP_DEMO.



11. Click OK to save.

Configuring the SAP Source Server


Configuring the Data Server

1. In the Physical Architecture tree view, expand the Technologies node, select the SAP ABAP technology.

- 2. Right-click and select Insert Data Server.
- 3. Enter the data server definition. Set the parameters for this data server as follows:
 - Name: SAP_ERP. The name of the data server as it will appear in ODI.
 - Host (Data Server): SAP ERP System IP Address or Hostname.
 - User: SAP User, as provided by the SAP Administrator.
 - Password: This user's SAP Password. This password is case-sensitive.



4. Set the Flexfield values for this data server in the Flexfields tab.



- **SAP Language**: Code of the language used when logging in. For example EN for English, DE for German.
- **SAP Client Number**: The three-digit number assigned to the self-contained unit which is called *Client* in SAP. A Client can be a training, development, testing or production client or represent different divisions in a large company.
- **SAP System Number**: The two-digit number assigned to a SAP instance which is also called Web Application Server or WAS.
- **SAP System ID**: The three-character, unique identifier of a SAP system in a landscape.

- **SAP SNC Connection Properties**: SNC Connection Properties. This parameter is optional and can be left empty.
- **SAP Router String**: Router String. This parameter is optional and can be left empty.
- 2. Click OK.

Note: The **Test** button for validating SAP Connection definition is not supported for this connection.


Except for the data server name, all the parameters that you provide while defining the SAP Data server should be provided by the SAP Administrators. See *Getting the Right Privileges* section for more information.

The SAP Adapter requires privileges to perform set up and execution operations. Please provide your administrators with the list of privileges listed in *Appendix A - SAP ABAP ERP Required Privileges*. These privileges are required for the SAP user that they will provide you to login the SAP System.

See *Gathering SAP Connection Information* in the *Before You Begin* section for more information about these parameters.

Configuring the Logical Schema

- 1. In the Physical Schema window, do not edit the Definition tab.
- 2. Select the Context tab, click **Add** and enter the Logical Schema name LOGICAL_SAP_ERP.



3. Click OK.

Create a New Project

In order to work with the data servers you have created, you must create a project and import the appropriate knowledge modules for reverse-engineering the data structures and integrating the data.

To create a new Project for SAP:


- 1. Connect to Designer.
- 2. In the Projects tree view click Insert Project.
- 3. In the Definition tab, enter SAP Demo for the Project name.
- 4. Click **OK** to save your project.
- 5. Expand the SAP Demo Project, select the First Folder node.
- 6. Rename this folder to SDE_SAP_GeoDimension.
- 7. Right-click the SAP Demo Project in the Projects tree view.
- 8. Right-click and select Import Knowledge Modules.
- 9. Select in the File import directory the directory containing your KMs. By default, they are located in the .../impexp directory.
- 10. Select the following KMs:
 - IKM Oracle Incremental Update
 - LKM SAP ERP to Oracle (SQLLDR)
 - RKM SAP ERP
 - RKM SAP ERP Connection Test
- 11. Click **OK** to perform the import.

Reverse-Engineering the Data Models


Reverse-Engineering the Oracle Target

To reverse-engineer the Oracle data model:

- 1. Connect to Designer.
- 2. In the Models tree view, click Insert Model.
- 3. In the Definition tab, enter the model parameters as shown below:



4. In the Reverse tab, select the Global context.



5. Click **Reverse**, then **OK** to save your model.

6. The WS_GEO_DS datastore appears in your Oracle model, as shown below.




Reverse-Engineering the SAP Source Datastores

To reverse-engineer the SAP Source datastores you need to perform the following tasks:

- 1. Create the Data Model
- 2. Validate the SAP Connection
- 3. Start the Reverse-Engineering Process

Creating the Data Model

- 1. In the Models tree view, click **Insert Model**.
- 2. In the Definition tab, enter the model parameters as shown below. You must select the SAP ABAP technology and the Logical Schema previously created (in our example it is the LOGICAL_SAP_ERP Logical Schema).




- 3. In the Reverse tab:
 - a. Select the Global context.
 - b. Select Customized option.
 - c. Select the RKM SAP ERP Connection Test you have imported in the SAP ERP Demo project.

Validating the SAP Connection

1. In the Models tree view, open the ${\tt SAP}\ {\tt ERP}\ {\tt Source}\ {\tt Model}.$

- 2. Click **Reverse** and confirm the start of the reverse-engineering process. This process runs two tests:
 - Establish a test connection to the SAP system and
 - Validate the proper setup of SAP JCo by displaying the About dialog.
- 3. In a few seconds, you should see the SAP JCo-About dialog as shown here:



Please verify the JCo version number (See the Pre-requisites section for more details.) and verify that a path for the JCo Library is given (.dll for Windows). If this is not the case or you see any error message in this about dialog, please review the SAP JCo installation, as described in your SAP JCo package and run this test again.

Note: Closing the JCo-About-Dialog will also close ODI.

- 4. Once you have validated SAP JCo installation, open ODI Operator.
- 5. In the Operator, expand the Reverse-Engineering session down to the task level.
- 6. Verify whether the task "Test SAP Connection" has been executed successfully. If not, view the task details to identify the connection problem.


Do not continue until you have successfully validated the SAP connection!

Note: If you want to validate the SAP connectivity independent of ODI, please see Appendix B - SAP Stand-Alone Connection Test.

Starting the Reverse-Engineering Process

To start the reverse-engineering process of the SAP ERP datastores:

- 1. In the Models tree view, open the SAP ERP Source Model.
- 2. In the Reverse tab:
 - a. Select the Global context.
 - b. Select the Customized option.
 - c. Select the RKM SAP ERP you have imported in the SAP ERP Demo project.
 - d. Set the USE_GUI KM option to Yes.
 - e. Set other parameters according to your SAP configuration. Refer to the *Oracle Data Integrator Knowledge Modules Reference Guide* for more information on the RKM options.




- 3. Click **Apply** to save your changes.
- 4. Click **Reverse** to start the reverse-engineering process.
- 5. Click OK.
- 6. The Sessions Started Dialog is displayed.
- 7. Click OK.

Using the SAP Metadata Browser

As you have set the USE_GUI option to Yes, the RKM displays in the **SAP Metadata Browser** the SAP objects organized in the tree view as shown below.

Note: In case that the below dialog does not show up, see ODI Operator for details and read the log files <System Temp Dir>/sap_rkm_erp_<ODI Session Number>.log and <System Temp Dir>/sap_rkm_erp_<ODI Session Number>.log.


Refer to the *Log Files* section in the *SAP ABAP* chapter of the *Oracle Data Integrator Knwoledge Modules Reference* Guide for more details.



The Tree View

The SAP Modules are organized into a tree view. Only the SAP Modules available to the current user are diaplyed. By expanding the tree view, you can see SAP tables, and select those that you want to reverse-engineer.

Note that only the tables selected in the tree view are reverse-engineered.



The Search Panel

The **Search** option group allows you search specific objects in the browser, based on:

- Table Name
- Short Description
- Application Component
- Package

For the example project, the T005T and T005U country tables are used:

- 1. Enter T005T in the Table Name field and click **Search** to find the first table to reverse-engineer. Select this table.
- 2. Enter T005U in the Table Name field and click **Search** to find the second table to reverse-engineer. Select this table.
- Click Reverse.
- 4. Oracle Data Integrator starts the reverse-engineering process on the selected datastores. The reverse-engineered datastores appear under the Model.

Reverse-Engineering without GUI

If you want to perform a reverse-engineering without using the SAP Metadata Browser, you can enter the following parameters in the SAP ERP KM options:

- USE GUI: No
- SAP TABLES NAME: T005T, T005U

With this configuration, the tables will be reverse-engineered without displaying the SAP Metadata Browser.

By using the appropriate KM options, you can also select a filter for the reversed tables based on for example a SAP Module or a Package name. You can also specify a table name mask in the **Mask** field of the Reverse tab to filter table names.

Refer to the *Oracle Data Integrator Knowledge Modules Reference Guide* for more information on the RKM options.

Note: It is not possible to view the data in the SAP ERP tables from Oracle Data Integrator.

What happens when you reverse-engineer SAP ERP tables?

First, Oracle Data Integrator uploads in the SAP system ABAP code allowing for retrieving the SAP metadata. This RFC is uploaded only if the UPLOAD_ABAP_CODE option is selected (this option is typically activated only once). The ABAP programs are generated in the SAP function group given in the SAP_FUNCTION_GROUP RKM option.

Once this code is set up on SAP, Oracle Data Integrator is able to retrieve the SAP metadata and to display it in the SAP Metadata Browser. Selected metadata is then reverse-engineered from SAP into the Oracle Data Integrator repository. The repository only contains the description of the SAP metadata, and no data at all.

In addition to the table definitions organized and enriched with user-friendly information, the keys and indexes definitions are also retrieved. The model appearing in Oracle Data Integrator shows all the information required for performing integration tasks on the SAP ERP Model.

Create the Integration Interface

Now that the source and target data models are created, it is possible to create an interface to integrate data from the T005T and T005U SAP tables to the WS_GEO_DS Oracle table.

Create the Interface

- 1. Open Designer.
- 2. In the Projects tree view, expand the SAP Demo Project.
- 3. Expand the SDE_SAP_GeoDimension folder.
- 4. Select the Interfaces node.
- 5. Right-click and select **Insert Interface**.
- 6. In the Interface Definition tab, enter the interface name: SDE_SAP_GeoDimension.W_GEO_DS.
- 7. Select the Diagram tab.
- 8. Click **OK** if the following information window appears.



The interface diagram looks as follows:

| The interface diagram looks as follows:
| The interface of the in

Define the Source and Target Datastores

<u>H</u>elp


To define the source and target datastores:

<u>C</u>ancel

Apply


 In the Models tree view, select the WS_GEO_DS datastore from the Oracle Target Model. Execute

2. Drag this datastore into the Target Datastore panel (right area of the Diagram tab). This panel appears now as shown below:



- 3. In the Models tree view, select the T005T Country Names datastore from the SAP ERP Source model.
- 4. Drag this datastore into the Sources diagram panel (left area of the diagram tab).
- If a popup window prompting "Do you want to perform Automatic Mapping?" appears, click No.
- 6. Perform the same operation for the T005U Taxes: Region Key datastore from the SAP ERP Source model.

The Sources diagram should look as shown below:




Define Joins between Sources


To create joins between the source datastores of an interface:

1. In the Sources diagram drag the SPRAS column from the T005T Country Name datastore onto the SPRAS column in the T005U Taxes: Region Key table. This

defines the first join on the Language Key identifier, as shownbelow:



- 2. Drag the LAND1 column from the T005T Country Name table onto the LAND1 column in the T005U Taxes: Region Key table. The join is extended with the new columns. In the Properties panel, you can see the join clause: (T005T.SPRAS=T005U.SPRAS) AND T005T.LAND1=T005U.LAND1\$
- 3. In the Properties panel, select Ordered join and make sure that this join is executed on the **Source** as shown below:




4. Make sure that table number of T005U is smaller than that of T005T. In 1:n relationships the parent table has to be the first in a join.

Create the Mappings

To create the mappings of the target datastore:

- 1. Select the LANGUAGE KEY column from the target datastore.
- 2. Drag the SPRAS column from the T005T Country Names source table into the Implementation field of the Properties panel.

Make sure that the Execution On is set to Source. The mapping should look as shown below:




- 4. Repeat this operation to perform the following simple mappings:
 - W_GEO_DS.COUNTRY = T005T.LAND1
 - W_GEO_DS.COUNTY = T005T.LANDX
 - W_GEO_DS.STATE_PROV = T005U.BLAND
 - W_GEO_DS.NATIONALITY = T005T.NATIO

Define the Interface Flow


To define the interface flow:

1. Select the Flow tab. The Flow diagram looks as shown below;



- 2. Select the source set SS_0 (SAP_ERP) that contains both the T005T and T005U tables. This source set represents the source dataset made up of two joined SAP_ERP tables.
- 3. In the LKM Selection box, select LKM SAP ERP to Oracle (SQLLDR).
- 4. Select the **Target + Staging Area** box. This represents the target Oracle database, which is also used as the staging area for this interface.
- 5. In the LKM Selection, select LKM SAP ERP to Oracle (SQLLDR).
- 6. In the IKM Selection, select IKM Oracle Incremental Update.
- 7. Set the IKM options as follows:

- a. Select No for the FLOW CONTROL option.
- b. Leave other options as is. The flow should look as shown below:



8. Click **OK** to save and close your interface.

Running the Integration Interface

Running the Interface

To run the integration interface:

- 1. In the Projects tree view, expand the SAP Demo Project
- 2. Expand the SDE_SAP_GeoDimension folder.
- 3. Expand the Interfaces node.
- 4. Select the SDE_SAP_GeoDimension.W_GEO_DS interface.
- 5. Right-click and select Execute.
- 6. In the Execution window that appears, click **OK**.
- 7. Click **OK** in the Session Started window.

What happens when you run the interface?

First, Oracle Data Integrator creates an ABAP program that does the following:

- 1. It performs the extraction of the data on the SAP engine. In this example, the extraction joins the two source tables and then returns the joined resultset in an extraction file.
- 2. It uploads the extraction file into a FTP data server. This FTP host is specified via the File Logical Schema called File Server for SAP ABAP. This Logical Schema is mapped to a Physical Schema and therefore a data server in the given context. This data server contains the connection information for the FTP host.

Then, the ABAP code is uploaded using the *OdiSapAbapExecute* tool. The ABAP program is pushed into the SAP Function group given in the SAP_FUNCTION_GROUP_NAME LKM option. This phase can be suppressed by setting the UPLOAD_ABAP_CODE LKM option to No.

The ABAP code is executed also by the *OdiSapAbapExecute* tool. At the end of the ABAP code execution, the extraction file is available in the FTP host.

The Oracle Data Integrator agent is able to download this extraction file from the FTP host, or directly access it, depending on the FTP_TRANSFER_METHOD specified in the IKM option.


Finally, when the agent accesses the extraction file, it uses *SQL*Loader* to load this file into the Oracle staging area. The rest of the integration process takes place within the Oracle engine.

Review the Interface Execution

To review the interface execution:

1. Connect to Operator.

- 2. In the Operator, select the Session List tree view.
- 3. Expand the All Executions node in this tree view.
- 4. The latest session is the first entry of this list and appears as shown below.



5. Double click the SDE_SAP_GeoDimension.W_GEO_DS node to see the session details and the number of lines processed.

Review the Resulting Data

To review the resulting data:

- 1. In the Designer, in the Models tree view, expand the Oracle Target Model.
- 2. Select the W_GEO_DS datastore, right-click and select **Data** to view the data integrated into the target Oracle table.

Conclusion

You have now completed a project extracting data from a SAP ERP system! In this project, you have:

- Set up the environment and topology to work with SAP ERP.
- Created and reverse-engineered a SAP ERP data model
- Created an interface to load the data from several joined SAP ERP tables into the Oracle database.

Refer to the *Oracle Data Integrator Knowledge Modules Reference Guide* for more information on the SAP ERP KM features and options.

Note: In case the execution did not complete successfully, please check the Operator details for the error message. In addition to this, the following log files will contain execution information.

- <System Temp Dir>/ODI_<Interface Id>_<SrcSet>.genlog
- <System Temp Dir>SAPAbapExecuteOpenTool_<Interface Id>.log
- <System Temp Dir or local FTP dir>/ ZODI_<Interface Id>_<SrcSet>_<Context>.log
- <System Temp Dir or local FTP dir>/ ZODI_<Interface Id>_<SrcSet>_<Context>.out
- <System Temp Dir or local FTP dir>/ ZODI_<Interface Id>_<SrcSet>_<Context>.err

Refer to the Log Files section in the SAP ABAP chapter of the Oracle Data Integrator Knwoledge Modules Reference Guide for more details.

Going further with Oracle Data Integrator

Use the demonstration environment to familiarize yourself with Oracle Data Integrator. You can go further with Oracle Data Integrator by taking advantage of the samples available on the Oracle Technology Network.

Appendix A - SAP ABAP ERP Required Privileges

For connecting to the SAP system a SAP dialog user is required for RKM installation and LKM execution during development. A SAP RFC user is NOT sufficient.

This user has to have a developer license key. License keys can be retrieved from http://service.sap.com.

Later for RKM execution and LKM execution in production a SAP RFC user is sufficient.

The following tables list the privileges required for using SAP ABAP Knowledge Modules.

Authorizations Required for RKM SAP ERP Setup

The following authorizations are required for setting up the configuration for the **RKM SAP ERP** and install the required RFC programs to retrieve the metadata about SAP tables.

| Object | Field Name | Value |
|------------|------------|-------|
| S_ADMI_FCD | S_ADMI_FCD | * |
| S_ADMI_FCD | S_ADMI_FCD | NADM |
| S_ADMI_FCD | S_ADMI_FCD | PADM |
| S_CTS_ADMI | CTS_ADMFCT | EPS1 |
| S_CTS_ADMI | CTS_ADMFCT | EPS2 |
| S_CTS_ADMI | CTS_ADMFCT | PROJ |
| S_C_FUNCT | ACTVT | 16 |
| S_C_FUNCT | CFUNCNAME | * |
| S_C_FUNCT | PROGRAM | * |
| S_CTS_ADMI | CTS_ADMFCT | TABL |
| S_TCODE | TCD | SU53 |
| S_TCODE | TCD | SE38 |
| S_TCODE | TCD | SE80 |
| S_DATASET | ACTVT | 6 |
| S_DATASET | ACTVT | 33 |
| S_DATASET | ACTVT | 34 |
| S_DATASET | FILENAME | * |
| S_TCODE | TCD | SE91 |

| S_TCODE | TCD | ST22 |
|------------|------------|----------|
| S_DATASET | PROGRAM | * |
| S_RFC | RFC_TYPE | * |
| S_RFC | RFC_NAME | * |
| s_RFC | ACTVT | 16 |
| S_DEVELOP | ACTVT | * |
| S_DEVELOP | DEVCLASS | * |
| S_DEVELOP | OBJNAME | * |
| S_DEVELOP | OBJTYPE | * |
| S_DEVELOP | P_GROUP | * |
| S_DOKU_AUT | DOKU_ACT | RAW_VERS |
| S_DOKU_AUT | DOKU_DEVCL | TEST |
| S_DOKU_AUT | DOKU_MODE | MAINTAIN |
| S_RFC_ADM | ACTVT | 3 |
| S_RFC_ADM | ICF_VALUE | * |
| S_RFC_ADM | RFCDEST | * |
| S_RFC_ADM | RFCTYPE | * |
| S_RZL_ADM | ACTVT | * |
| S_TABU_DIS | ACTVT | 3 |
| S_TABU_DIS | DICBERCLS | * |
| S_TCODE | TCD | ■ AL11 |
| S_TCODE | TCD | SE10 |
| S_TCODE | TCD | SE11 |
| S_TCODE | TCD | SE16 |
| S_TCODE | TCD | SE37 |
| S_TCODE | TCD | SM58 |
| S_TCODE | TCD | SM59 |
| S_TRANSPRT | ACTVT | 1 |
| S_TRANSPRT | ACTVT | 2 |
| S_TRANSPRT | ACTVT | 3 |
| S_TRANSPRT | ACTVT | 5 |

| S_TRANSPRT | ACTVT | 6 |
|------------|-------|------|
| S_TRANSPRT | ACTVT | 23 |
| S_TRANSPRT | ACTVT | 43 |
| S_TRANSPRT | ACTVT | 65 |
| S_TRANSPRT | ACTVT | 78 |
| S_TRANSPRT | ACTVT | 90 |
| S_TRANSPRT | TTYPE | CUST |
| S_TRANSPRT | TTYPE | DTRA |
| S_TRANSPRT | TTYPE | MOVE |
| S_TRANSPRT | TTYPE | PIEC |
| S_TRANSPRT | TTYPE | TASK |
| S_TRANSPRT | TTYPE | TRAN |
| | | |

| Transaction code |
|------------------|
| SU53 |
| SE38 |
| SE80 |
| SE91 |
| ST22 |
| AL11 |
| SE10 |
| SE11 |
| SE16 |
| SE37 |
| SM58 |
| SM59 |

Authorizations Required for RKM Execution

The following authorizations are required for running a reverse-engineering using the **RKM SAP ERP**.

| S_ADMI_FCD | S_ADMI_FCD | * |
|------------|------------|----------|
| S_ADMI_FCD | S_ADMI_FCD | NADM |
| S_ADMI_FCD | S_ADMI_FCD | PADM |
| S_CTS_ADMI | CTS_ADMFCT | EPS1 |
| S_CTS_ADMI | CTS_ADMFCT | EPS2 |
| S_CTS_ADMI | CTS_ADMFCT | PROJ |
| S_C_FUNCT | ACTVT | 16 |
| S_C_FUNCT | CFUNCNAME | * |
| S_C_FUNCT | PROGRAM | * |
| S_CTS_ADMI | CTS_ADMFCT | TABL |
| S_TCODE | TCD | SU53 |
| S_TCODE | TCD | SE38 |
| S_TCODE | TCD | SE80 |
| S_DEVELOP | ACTVT | 16 |
| S_DATASET | ACTVT | 33 |
| S_DATASET | FILENAME | * |
| S_TCODE | TCD | SE91 |
| S_TCODE | TCD | ST22 |
| S_DATASET | PROGRAM | * |
| S_RFC | RFC_TYPE | * |
| S_RFC | RFC_NAME | * |
| S_RFC | ACTVT | 16 |
| S_DEVELOP | ACTVT | 3 |
| S_DEVELOP | DEVCLASS | * |
| S_DEVELOP | OBJNAME | * |
| S_DEVELOP | OBJTYPE | * |
| S_DEVELOP | P_GROUP | * |
| S_DOKU_AUT | DOKU_ACT | RAW_VERS |
| S_DOKU_AUT | DOKU_DEVCL | TEST |
| S_DOKU_AUT | DOKU_MODE | MAINTAIN |
| S_RFC_ADM | ACTVT | 3 |

| S_RFC_ADM | ICF_VALUE | * |
|------------|-----------|------|
| S_RFC_ADM | RFCDEST | * |
| S_RFC_ADM | RFCTYPE | * |
| S_RZL_ADM | ACTVT | 3 |
| S_TABU_DIS | ACTVT | 3 |
| S_TABU_DIS | DICBERCLS | * |
| S_TCODE | TCD | AL11 |
| S_TCODE | TCD | SE10 |
| S_TCODE | TCD | SE11 |
| S_TCODE | TCD | SE16 |
| S_TCODE | TCD | SE37 |
| S_TCODE | TCD | SM58 |
| S_TCODE | TCD | SM59 |
| S_TRANSPRT | ACTVT | 3 |
| S_TRANSPRT | TTYPE | CUST |
| S_TRANSPRT | TTYPE | DTRA |
| S_TRANSPRT | TTYPE | MOVE |
| S_TRANSPRT | TTYPE | PIEC |
| S_TRANSPRT | TTYPE | TASK |
| S_TRANSPRT | TTYPE | TRAN |

Authorizations Required for LKM Execution

The following authorizations are required for using the **LKM SAP ERP to Oracle (SQLLDR)**. This set of authorization is needed to install the ABAP code generated by the LKM and execute it.

| Object | Field Name | Value |
|------------|------------|-------|
| S_ADMI_FCD | S_ADMI_FCD | * |
| S_ADMI_FCD | S_ADMI_FCD | NADM |
| S_ADMI_FCD | S_ADMI_FCD | PADM |
| S_CTS_ADMI | CTS_ADMFCT | EPS1 |
| S_CTS_ADMI | CTS_ADMFCT | EPS2 |
| S_CTS_ADMI | CTS_ADMFCT | PROJ |

| S_C_FUNCT | ACTVT | 16 |
|------------|------------|------|
| S_C_FUNCT | CFUNCNAME | * |
| S_C_FUNCT | PROGRAM | * |
| S_CTS_ADMI | CTS_ADMFCT | TABL |
| S_TCODE | TCD | SU53 |
| S_TCODE | TCD | SE38 |
| S_TCODE | TCD | SE80 |
| S_DEVELOP | ACTVT | 16 |
| S_DATASET | ACTVT | 33 |
| S_DEVELOP | ACTVT | 7 |
| S_DATASET | FILENAME | * |
| S_DEVELOP | ACTVT | 1 |
| S_TCODE | TCD | SE91 |
| S_TCODE | TCD | ST22 |
| S_DEVELOP | ACTVT | 40 |
| S_DEVELOP | ACTVT | 41 |
| S_DATASET | ACTVT | 34 |
| S_DEVELOP | ACTVT | 94 |
| S_DEVELOP | ACTVT | 2 |
| S_TRANSPRT | ACTVT | 2 |
| S_TRANSPRT | ACTVT | 1 |
| S_TRANSPRT | ACTVT | 60 |
| S_TABU_DIS | ACTVT | 2 |
| S_RZL_ADM | ACTVT | 1 |
| S_DATASET | PROGRAM | * |
| S_RFC | RFC_TYPE | * |
| S_RFC | RFC_NAME | * |
| S_RFC | ACTVT | 16 |
| S_DEVELOP | ACTVT | 3 |
| S_DEVELOP | DEVCLASS | * |
| S_DEVELOP | OBJNAME | * |

| S_DEVELOP | OBJTYPE | * |
|------------|------------|----------|
| S_DEVELOP | P_GROUP | * |
| S_DOKU_AUT | DOKU_ACT | RAW_VERS |
| S_DOKU_AUT | DOKU_DEVCL | TEST |
| S_DOKU_AUT | DOKU_MODE | MAINTAIN |
| S_RFC_ADM | ACTVT | 3 |
| S_RFC_ADM | ICF_VALUE | * |
| S_RFC_ADM | RFCDEST | * |
| S_RFC_ADM | RFCTYPE | * |
| S_RZL_ADM | ACTVT | 3 |
| S_TABU_DIS | ACTVT | 3 |
| S_TABU_DIS | DICBERCLS | * |
| S_TCODE | TCD | AL11 |
| S_TCODE | TCD | SE10 |
| S_TCODE | TCD | SE11 |
| S_TCODE | TCD | SE16 |
| S_TCODE | TCD | SE37 |
| S_TCODE | TCD | SM58 |
| S_TCODE | TCD | SM59 |
| S_TRANSPRT | ACTVT | 3 |
| S_TRANSPRT | TTYPE | CUST |
| S_TRANSPRT | TTYPE | DTRA |
| S_TRANSPRT | TTYPE | MOVE |
| S_TRANSPRT | TTYPE | PIEC |
| S_TRANSPRT | TTYPE | TASK |
| S_TRANSPRT | TTYPE | TRAN |

Authorizations Required for LKM Execution for Production

The following authorizations are required for using the **LKM SAP ERP to Oracle (SQLLDR)** in a production environment. In such environment, the ABAP code generated by the LKM is not installed by the LKM but simply executed.

| Object | Field Name | Value |
|------------|------------|----------|
| S_ADMI_FCD | S_ADMI_FCD | * |
| S_ADMI_FCD | S_ADMI_FCD | NADM |
| S_ADMI_FCD | S_ADMI_FCD | PADM |
| S_CTS_ADMI | CTS_ADMFCT | EPS1 |
| S_CTS_ADMI | CTS_ADMFCT | EPS2 |
| S_CTS_ADMI | CTS_ADMFCT | PROJ |
| S_C_FUNCT | ACTVT | 16 |
| S_C_FUNCT | CFUNCNAME | * |
| S_C_FUNCT | PROGRAM | * |
| S_CTS_ADMI | CTS_ADMFCT | TABL |
| S_TCODE | TCD | SU53 |
| S_TCODE | TCD | SE38 |
| S_TCODE | TCD | SE80 |
| S_DEVELOP | ACTVT | 16 |
| S_DATASET | ACTVT | 33 |
| S_DATASET | FILENAME | * |
| S_TCODE | TCD | SE91 |
| S_TCODE | TCD | ST22 |
| S_DATASET | PROGRAM | * |
| S_RFC | RFC_TYPE | * |
| S_RFC | RFC_NAME | * |
| S_RFC | ACTVT | 16 |
| S_DEVELOP | ACTVT | 3 |
| S_DEVELOP | DEVCLASS | * |
| S_DEVELOP | OBJNAME | * |
| S_DEVELOP | OBJTYPE | * |
| S_DEVELOP | P_GROUP | * |
| S_DOKU_AUT | DOKU_ACT | RAW_VERS |
| S_DOKU_AUT | DOKU_DEVCL | TEST |
| S_DOKU_AUT | DOKU_MODE | MAINTAIN |

| S_RFC_ADM | ACTVT | 3 |
|------------|-----------|------|
| S_RFC_ADM | ICF_VALUE | * |
| S_RFC_ADM | RFCDEST | * |
| S_RFC_ADM | RFCTYPE | * |
| S_RZL_ADM | ACTVT | 3 |
| S_TABU_DIS | ACTVT | 3 |
| S_TABU_DIS | DICBERCLS | * |
| S_TCODE | TCD | AL11 |
| S_TCODE | TCD | SE10 |
| S_TCODE | TCD | SE11 |
| S_TCODE | TCD | SE16 |
| S_TCODE | TCD | SE37 |
| S_TCODE | TCD | SM58 |
| S_TCODE | TCD | SM59 |
| S_TRANSPRT | ACTVT | 3 |
| S_TRANSPRT | TTYPE | CUST |
| S_TRANSPRT | TTYPE | DTRA |
| S_TRANSPRT | TTYPE | MOVE |
| S_TRANSPRT | TTYPE | PIEC |
| S_TRANSPRT | TTYPE | TASK |
| S_TRANSPRT | TTYPE | TRAN |

Appendix B - SAP Stand-Alone Connection Test

In addition to the Connection Testing described above, a test can be performed outside of ODI using a standalone java utility:

To use a standalone java utility to test the connection:

- 1. Open a command window.
- 2. Change to oracledi/drivers directory.
- 3. Make sure that JAVA_HOME points to a JVM (at least 1.5).
- 4. Make sure that you have installed SAP Java Connector and that the sapjar3.jar and the sapjco3 library are in the oracledi/drivers directory.

5. Launch the utility using the following command:
 java -cp sapjarco3.jar;odi-sap.jar oracle.odi.sap.km.test.JCoTest
This should result in an output similar to this:

```
JCO3 Libraray available!!
JCO Version: 3.0.2 (2009-03-29)
Creating connection Pool...
Error: com.sap.conn.jco.JCoException: (102) RFC_ERROR_COMMUNICATION: Connect to SAP gateway failed
Connection parameters: IYPE=A DEST=ODI_SAP_CON_POOL ASHOST=(SAP Application Server) SYSNR=00 PCS=1

LOCATION CPIC (TCP/IP) on local host with Unicode
ERROR hostname '(SAP Application Server)' unknown

IIME Tue Sep 08 16:07:27 200

RELEASE 71

COMPONENT NI (network interface)
UERSION 39

RC -2

MODULE ninti.c
LINE 895

DETAIL NIPGetHostByName: '(SAP Application Server)' not found
SYSIEM CALL getaddrinfo
COUNTER 2
```

6. Use a text editor to open the ODI_SAP_CON_POOL.jcoDestination file in the oracledi/drivers directory. The file should look like this:

```
#for tests only!
jco.client.lang=EN
jco.destination.peak_limit=10
jco.client.client=800
jco.client.passwd=<SAP Password>
jco.client.user=<SAP User>
jco.client.sysnr=00
jco.destination.pool_capacity=5
jco.client.ashost=<SAP Application Server>
```

7. Enter you SAP connection information, which you have received from your SAP administrator. The file will then look similar to this (use your connection information!):

```
#for tests only !
jco.client.lang=EN
jco.destination.peak_limit=10
jco.client.client=800
jco.client.passwd=ODI123
jco.client.user=ODI
jco.client.sysnr=00
jco.destination.pool_capacity=5
jco.client.ashost=123.123.123.123.
```

8. Launch the utility again using the following command: java -cp sapjarco3.jar;odi-sap.jar oracle.odi.sap.km.test.JCoTest This should result in an output similar to this:

```
EXCLWINDOWS\system32\cmd.exe

SYSTEM CALL getaddrinfo
COUNTER 2

D:\Oracledi\drivers\java -cp odi-sap.jar;sapjco3.jar oracle.odi.sap.km.test.JCoTest
JCO3 Libraray available!!
JCO3 Libraray available!!
JCO4 Uersion: 3.0.2 (2809-83-29)
GC STATE CONTROL FOR CON
```

In addition to just testing the SAP connection, the utility will also validate the existence of certain Function Modules required for the RKM. These are installed during first execution of the RKM (UPLOAD_ABAP = Yes).

9. Delete the ODI_SAP_CON_POOL.jcoDestination file after execution, as it contains the SAP login credentials.

Appendix C - Uninstalling ODI SAP Components

In case of upgrading to a newer ODI SAP Connector release or for permanently removing ODI connectivity, please follow the steps described in this section.

Please note that this will delete ALL components including generated extractor programs.

To upgrad to a newer ODI SAP Connector release or to permanently remove the ODI connectivity:

- 1. Start the SAP GUI.
- 2. Connect to the SAP systems you want to uninstall.
- 3. Go to the transaction SE80.
- 4. Select the package or development class option from the drop down box.
- 5. Type ZODIBW_PCKG in the package or development class field.
- 6. Expand the ZODIBW_PCKG package or class.
- 7. Select the ZODI_FGR function group.

- 8. Right-click and select delete ZODI FGR.
- 9. Confirm the question "Do you really want to delete function group <code>ZODI_FGR</code>" by selecting **Yes**.
- 10. Select the ZODI_SAP_KM_FGRP function group.
- 11. Right-click, select delete ZODI_SAP_KM_FGRP.
- 12. Confirm the question "Do you really want to delete function group ZODI_SAP_KM_FGRP" by selecting **Yes**.
- 13. Select ZODI_MSG message class.
- 14. Right-click, select delete ZODI_MSG.
- 15. Confirm the question "Do you really want to delete message class <code>ZODI_MSG</code>" by selecting Yes.
- 16. Mark all structures.
- 17. Right-click, select Delete.
- 18. Confirm the question "Do you really want to delete structure ZRETURN" by clicking **Delete**AII.
- 19. If asked for new transport request, assign a new transport request number.
- 20. All objects are deleted from ZODIBW_PCKG. Select ZODIBW_PCKG.
- 21. Right-click, select Delete.
- 22. Confirm the question "Do you really want to delete package ZODIBW_PCKG" by selecting Yes.