
# Chapter 3 Transport Layer



#### A note on the use of these ppt slides:

We're making these slides freely available to all (faculty, students, readers). They're in PowerPoint form so you can add, modify, and delete slides (including this one) and slide content to suit your needs. They obviously represent a *lot* of work on our part. In return for use, we only ask the following:

☐ If you use these slides (e.g., in a class) in substantially unaltered form, that you mention their source (after all, we'd like people to use our book!) ☐ If you post any slides in substantially unaltered form on a www site, that you note that they are adapted from (or perhaps identical to) our slides, and note our copyright of this material.

Thanks and enjoy! JFK/KWR

All material copyright 1996-2009

J.F Kurose and K.W. Ross, All Rights Reserved

Computer Networking: A Top Down Approach 5<sup>th</sup> edition. Jim Kurose, Keith Ross Addison-Wesley, April 2009.

# Chapter 3: Transport Layer

#### Our goals:

- understand principles behind transport layer services:
  - multiplexing/ demultiplexing
  - o reliable data transfer
  - flow control
  - congestion control

- learn about transport layer protocols in the Internet:
  - UDP: connectionless transport
  - TCP: connection-oriented transport
  - TCP congestion control


# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - oreliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
  - send side: breaks app messages into segments, passes to network layer
  - rcv side: reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
  - Internet: TCP and UDP



# Transport vs. network layer


- network layer: logical communication between hosts
- transport layer: logical communication between processes
  - relies on, enhances, network layer services

#### Household analogy:

- 12 kids sending letters to 12 kids
- processes = kids
- app messages = letters in envelopes
- hosts = houses
- transport protocol = Ann and Bill
- network-layer protocolpostal service

# Internet transport-layer protocols

- reliable, in-order delivery (TCP)
  - congestion control
  - flow control
  - connection setup
- unreliable, unordered delivery: UDP
  - no-frills extension of "best-effort" IP
- services not available:
  - delay guarantees
  - bandwidth guarantees



# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - o segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# Multiplexing/demultiplexing


#### <u>Demultiplexing at rcv host:</u>

delivering received segments to correct socket

= socket = process


#### Multiplexing at send host: -

gathering data from multiple sockets, enveloping data with header (later used for demultiplexing)



### How demultiplexing works

- host receives IP datagrams
  - each datagram has source IP address, destination IP address
  - each datagram carries 1 transport-layer segment
  - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

# Connectionless demultiplexing

Create sockets with port numbers:

```
DatagramSocket mySocket1 = new
  DatagramSocket(12534);
```


- DatagramSocket mySocket2 = new
   DatagramSocket(12535);
- UDP socket identified by two-tuple:

(dest IP address, dest port number)

- When host receives UDP segment:
  - checks destination port number in segment
  - directs UDP segment to socket with that port number
- ☐ IP datagrams with different source IP addresses and/or source port numbers directed to same socket

# Connectionless demux (cont)

DatagramSocket serverSocket = new DatagramSocket (6428);




SP provides "return address"

### Connection-oriented demux


- TCP socket identified by 4-tuple:
  - source IP address
  - source port number
  - dest IP address
  - dest port number
- receiving host uses all four values to direct segment to appropriate socket

- Server host may support many simultaneous TCP sockets:
  - each socket identified by its own 4-tuple
- Web servers have different sockets for each connecting client
  - on non-persistent HTTP will have different socket for each request

# Connection-oriented demux (cont)



# Connection-oriented demux: Threaded Web Server



# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - oreliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

### UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
  - lost
  - delivered out of order to app
- connectionless:
  - no handshaking between UDP sender, receiver
  - each UDP segment handled independently of others

#### Why is there a UDP?

- no connection establishment (which can add delay)
- simple: no connection state at sender, receiver
- small segment header
- no congestion control: UDP can blast away as fast as desired

### UDP: more

often used for streaming multimedia apps

loss tolerant

• rate sensitive

other UDP uses

DNS

SNMP

reliable transfer over UDP:
 add reliability at
 application layer

application-specific error recovery!

Length, in bytes of UDP segment, including header

→ 32 bits →	
source port #	dest port #
→length	checksum
Application	
data	
(message)	

UDP segment format

# UDP checksum

Goal: detect "errors" (e.g., flipped bits) in transmitted segment

#### Sender:


- treat segment contents as sequence of 16-bit integers
- checksum: addition (1's complement sum) of segment contents
- sender puts checksum value into UDP checksum field

#### Receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
  - NO error detected
  - YES no error detected. But maybe errors nonetheless? More later ....

# Internet Checksum Example

- Note
  - When adding numbers, a carryout from the most significant bit needs to be added to the result
- Example: add two 16-bit integers




# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# Principles of Reliable data transfer


- important in app., transport, link layers
- top-10 list of important networking topics!



- (a) provided service
- characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

### Principles of Reliable data transfer


- important in app., transport, link layers
- top-10 list of important networking topics!



characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)


### Principles of Reliable data transfer

- important in app., transport, link layers
- top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

### Reliable data transfer: getting started




### Reliable data transfer: getting started

#### We'll:


- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
  - but control info will flow on both directions!
- use finite state machines (FSM) to specify sender, receiver

state: when in this "state" next state uniquely determined by next event



#### Rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
  - ono bit errors
  - ono loss of packets
- separate FSMs for sender, receiver:
  - sender sends data into underlying channel
  - receiver read data from underlying channel



sender

receiver

#### Rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
  - checksum to detect bit errors
- the question: how to recover from errors:
  - o acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
  - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
  - sender retransmits pkt on receipt of NAK
- new mechanisms in rdt2.0 (beyond rdt1.0):
  - error detection
  - receiver feedback: control msgs (ACK,NAK) rcvr->sender

### rdt2.0: FSM specification

rdt\_send(data)
snkpkt = make\_pkt(data, checksum)
udt\_send(sndpkt)

Wait for
call from
above

rdt\_rcv(rcvpkt) &&
isNAK(rcvpkt)

udt\_send(sndpkt)

rdt\_rcv(rcvpkt) && isACK(rcvpkt)


A

sender


#### receiver

rdt\_rcv(rcvpkt) && corrupt(rcvpkt) udt send(NAK) Wait for call from below rdt\_rcv(rcvpkt) && notcorrupt(rcvpkt) extract(rcvpkt,data) deliver\_data(data) udt send(ACK)

### rdt2.0: operation with no errors



### rdt2.0: error scenario



### rdt2.0 has a fatal flaw!

#### What happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate


#### Handling duplicates:

- sender retransmits current pkt if ACK/NAK garbled
- sender adds sequence *number* to each pkt
- receiver discards (doesn't deliver up) duplicate pkt


#### -stop and wait

Sender sends one packet, then waits for receiver response

# rdt2.1: sender, handles garbled ACK/NAKs



### rdt2.1: receiver, handles garbled ACK/NAKs



### rdt2.1: discussion

#### Sender:

- seq # added to pkt
- → two seq. #'s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
  - state must "remember" whether "current" pkt has 0 or 1 seq. #


#### Receiver:

- must check if received packet is duplicate
  - state indicates whether O or 1 is expected pkt seq#
- note: receiver can not know if its last ACK/NAK received OK at sender

# rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
  - receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

### rdt2.2: sender, receiver fragments




#### rdt3.0: channels with errors and loss


#### New assumption:

- underlying channel can also lose packets (data or ACKs)
  - checksum, seq. #, ACKs, retransmissions will be of help, but not enough
- Approach: sender waits "reasonable" amount of time for ACK
- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
  - retransmission will be duplicate, but use of seq. #'s already handles this
  - receiver must specify seq # of pkt being ACKed
- requires countdown timer


#### rdt3.0 sender




#### rdt3.0 in action



(a) operation with no loss



#### rdt3.0 in action



## Performance of rdt3.0

- rdt3.0 works, but performance stinks
- ex: 1 Gbps link, 15 ms prop. delay, 8000 bit packet:


$$d_{trans} = \frac{L}{R} = \frac{8000 \text{bits}}{10^9 \text{bps}} = 8 \text{ microseconds}$$

O U sender: utilization - fraction of time sender busy sending

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

- 1KB pkt every 30 msec -> 33kB/sec thruput over 1 Gbps link
- o network protocol limits use of physical resources!

## rdt3.0: stop-and-wait operation




$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

## Pipelined protocols

Pipelining: sender allows multiple, "in-flight", yet-tobe-acknowledged pkts

- orange of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation

Two generic forms of pipelined protocols: go-Back-N, selective repeat

## Pipelining: increased utilization



# Pipelining Protocols

#### Go-back-N: overview

- sender: up to N unACKed pkts in pipeline
- receiver: only sends cumulative ACKs
  - doesn't ACK pkt if there's a gap
- sender: has timer for oldest unACKed pkt
  - if timer expires: retransmit all unACKed packets


#### Selective Repeat: overview

- sender: up to N unACKed packets in pipeline
- receiver: ACKs individual pkts
- sender: maintains timer for each unACKed pkt
  - o if timer expires: retransmit only unACKed packet

## Go-Back-N

#### Sender:

- k-bit seq # in pkt header
- "window" of up to N, consecutive unACKed pkts allowed




- $\square$  ACK(n): ACKs all pkts up to, including seq # n "cumulative ACK"
  - may receive duplicate ACKs (see receiver)
- timer for each in-flight pkt
- timeout(n): retransmit pkt n and all higher seq # pkts in window

#### GBN: sender extended FSM

```
rdt send(data)
                        if (nextseqnum < base+N) {
                          sndpkt[nextseqnum] = make pkt(nextseqnum,data,chksum)
                          udt send(sndpkt[nextseqnum])
                          if (base == nextsegnum)
                            start timer
                          nextseqnum++
                        else
   Λ
                         refuse data(data)
  base=1
  nextseqnum=1
                                           timeout
                                           start timer
                             Wait
                                           udt send(sndpkt[base])
                                           udt send(sndpkt[base+1])
rdt rcv(rcvpkt)
 && corrupt(rcvpkt)
                                           udt send(sndpkt[nextsegnum-
                         rdt_rcv(rcvpkt) &&<sup>1])</sup>
                            notcorrupt(rcvpkt)
                         base = getacknum(rcvpkt)+1
                         If (base == nextsegnum)
                            stop timer
                           else
                            start timer
```


#### GBN: receiver extended FSM



# ACK-only: always send ACK for correctly-received pkt with highest *in-order* seq #

- may generate duplicate ACKs
- only remember expected sequum
- out-of-order pkt:
  - discard (don't buffer) -> no receiver buffering!
  - Re-ACK pkt with highest in-order seq #


# GBN in action



## Selective Repeat

- receiver individually acknowledges all correctly received pkts
  - buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender only resends pkts for which ACK not received
  - sender timer for each unACKed pkt
- sender window
  - N consecutive seq #'s
  - ogain limits seq #s of sent, unACKed pkts

#### Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers

# Selective repeat

#### -sender

#### data from above:

if next available seq # in window, send pkt


#### timeout(n):

- resend pkt n, restart timer
- ACK(n) in [sendbase,sendbase+N]:
- mark pkt n as received
- if n smallest unACKed pkt, advance window base to next unACKed seq #

#### -receiver

- pkt n in [rcvbase, rcvbase+N-1]
- $\Box$  send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order pkts), advance window to next not-yet-received pkt
- pkt n in [rcvbase-N,rcvbase-1]
- $\Box$  ACK(n)
- otherwise:
- 🗖 ignore


### Selective repeat in action



# Selective repeat: dilemma

#### Example:

- seq #'s: 0, 1, 2, 3
- window size=3
- receiver sees no difference in two scenarios!
- incorrectly passes duplicate data as new in (a)
- Q: what relationship between seq # size and window size?



# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - oreliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

### TCP: Overview

RFCs: 793, 1122, 1323, 2018, 2581

- point-to-point:
  - one sender, one receiver
- reliable, in-order byte
  steam:
  - ono "message boundaries"
- pipelined:
  - TCP congestion and flow control set window size
- □ send & receive buffers

- full duplex data:
  - bi-directional data flow in same connection
  - MSS: maximum segment size
- connection-oriented:
  - handshaking (exchange of control msgs) init's sender, receiver state before data exchange
- flow controlled:
  - sender will not overwhelm receiver



## TCP segment structure


URG: urgent data (generally not used)

ACK: ACK # valid

PSH: push data now (generally not used)

RST, SYN, FIN: connection estab (setup, teardown commands)

> Internet checksum (as in UDP)



counting
by bytes
of data
(not segments!)

# bytes rcvr willing to accept


## TCP seq. #'s and ACKs

#### <u>Seq. #'s:</u>

 byte stream "number" of first byte in segment's data

#### ACKs:

- seq # of next byte expected from other side
- cumulative ACK
- Q: how receiver handles out-of-order segments
  - A: TCP spec doesn't say, - up to implementer



simple telnet scenario

time

## TCP Round Trip Time and Timeout

- $\mathbb{Q}$ : how to set TCP timeout value?
- longer than RTT
  - but RTT varies
- too short: premature timeout
  - unnecessary retransmissions
- too long: slow reaction to segment loss

- Q: how to estimate RTT?
- SampleRTT: measured time from segment transmission until ACK receipt
  - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
  - average several recent measurements, not just current SampleRTT


## TCP Round Trip Time and Timeout

EstimatedRTT =  $(1-\alpha)$ \*EstimatedRTT +  $\alpha$ \*SampleRTT

- Exponential weighted moving average
- influence of past sample decreases exponentially fast
- $\Box$  typical value:  $\alpha = 0.125$

## Example RTT estimation:

RTT: gaia.cs.umass.edu to fantasia.eurecom.fr



## TCP Round Trip Time and Timeout

#### Setting the timeout

- EstimtedRTT plus "safety margin"
  - Iarge variation in EstimatedRTT -> larger safety margin
- first estimate of how much SampleRTT deviates from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

#### Then set timeout interval:

```
TimeoutInterval = EstimatedRTT + 4*DevRTT
```

# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

## TCP reliable data transfer

- TCP creates rdt service on top of IP's unreliable service
- pipelined segments
- cumulative ACKs
- TCP uses single retransmission timer

- retransmissions are triggered by:
  - timeout events
  - duplicate ACKs
- initially consider simplified TCP sender:
  - ignore duplicate ACKs
  - ignore flow control, congestion control

## TCP sender events:

#### data rcvd from app:

- create segment with seq#
- □ seq # is byte-stream number of first data byte in segment
- □ start timer if not already running (think of timer as for oldest unACKed segment)
- expiration interval:

TimeOutInterval

#### timeout:

- retransmit segment that caused timeout
- restart timer

#### ACK rcvd:

- if acknowledges previously unACKed segments
  - update what is known to be ACKed
  - start timer if there are outstanding segments


```
NextSeqNum = InitialSeqNum
SendBase = InitialSeqNum
loop (forever) {
  switch(event)
  event: data received from application above
     create TCP segment with sequence number NextSeqNum
     if (timer currently not running)
         start timer
      pass segment to IP
     NextSeqNum = NextSeqNum + length(data)
  event: timer timeout
     retransmit not-yet-acknowledged segment with
          smallest sequence number
     start timer
  event: ACK received, with ACK field value of y
     if (y > SendBase) {
         SendBase = y
        if (there are currently not-yet-acknowledged segments)
              start timer
 } /* end of loop forever */
```

# TCP sender (simplified)


#### Comment:

- SendBase-1: last cumulatively
   ACKed byte
   Example:
- SendBase-1 = 71;
  y= 73, so the rcvr
  wants 73+;
  y > SendBase, so
  that new data is
  ACKed

#### TCP: retransmission scenarios



### TCP retransmission scenarios (more)



Cumulative ACK scenario


## TCP ACK generation [RFC 1122, RFC 2581]

Event at Receiver	TCP Receiver action
Arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	Delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
Arrival of in-order segment with expected seq #. One other segment has ACK pending	Immediately send single cumulative ACK, ACKing both in-order segments
Arrival of out-of-order segment higher-than-expect seq. # . Gap detected	Immediately send duplicate ACK, indicating seq. # of next expected byte
Arrival of segment that partially or completely fills gap	Immediate send ACK, provided that segment starts at lower end of gap

## Fast Retransmit

- time-out period often relatively long:
  - long delay before resending lost packet
- detect lost segments via duplicate ACKs.
  - sender often sends many segments back-toback
  - if segment is lost, there will likely be many duplicate ACKs for that segment

- If sender receives 3 ACKs for same data, it assumes that segment after ACKed data was lost:
  - fast retransmit: resend segment before timer expires



## Fast retransmit algorithm:

```
event: ACK received, with ACK field value of y
          if (y > SendBase) {
             SendBase = y
             if (there are currently not-yet-acknowledged segments)
                 start timer
          else {
               increment count of dup ACKs received for y
               if (count of dup ACKs received for y = 3) {
                   resend segment with sequence number y
```

a duplicate ACK for already ACKed segment

fast retransmit


# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - o reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# TCP Flow Control

receive side of TCP connection has a receive buffer:



□ app process may be slow at reading from buffer


#### flow control

sender won't overflow receiver's buffer by transmitting too much,

too fast

speed-matching service: matching send rate to receiving application's drain rate

# TCP Flow control: how it works



(suppose TCP receiver discards out-of-order segments)

- unused buffer space:
- = rwnd
- = RcvBuffer-[LastByteRcvd LastByteRead]

- receiver: advertises unused buffer space by including rwnd value in segment header
- sender: limits # of unACKed bytes to rwnd
  - guarantees receiver's buffer doesn't overflow

# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

### TCP Connection Management

- Recall: TCP sender, receiver establish "connection" before exchanging data segments
- initialize TCP variables:
  - o seq. #s
  - buffers, flow control info (e.g. RcvWindow)
- client: connection initiator Socket clientSocket = new Socket ("hostname", "port number");
- server: contacted by client Socket connectionSocket = welcomeSocket.accept();

#### Three way handshake:

- Step 1: client host sends TCP SYN segment to server
  - specifies initial seq #
  - o no data
- Step 2: server host receives SYN, replies with SYNACK segment
  - server allocates buffers
  - specifies server initial seq. #
- **Step 3:** client receives SYNACK, replies with ACK segment, which may contain data


## TCP Connection Management (cont.)

#### Closing a connection:

client closes socket:
 clientSocket.close();

Step 1: client end system sends TCP FIN control segment to server\_

<u>Step 2:</u> server receives FIN, replies with ACK. Closes connection, sends FIN.




## TCP Connection Management (cont.)

<u>Step 3:</u> client receives FIN, replies with ACK.


 Enters "timed wait" - will respond with ACK to received FINs

<u>Step 4:</u> server, receives ACK. Connection closed.

Note: with small modification, can handle simultaneous FINs.



# TCP Connection Management (cont)



# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- 3.5 Connection-oriented transport: TCP
  - segment structure
  - oreliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control


# Principles of Congestion Control


#### Congestion:


- informally: "too many sources sending too much data too fast for *network* to handle"
- different from flow control!
- manifestations:
  - lost packets (buffer overflow at routers)
  - long delays (queueing in router buffers)
- a top-10 problem!

## Causes/costs of congestion: scenario 1

- two senders, two receivers
- one router, infinite buffers
- no retransmission








- large delayswhen congested
- maximum achievable throughput


## Causes/costs of congestion: scenario 2\_

- one router, *finite* buffers
- sender retransmission of lost packet



# Causes/costs of congestion: scenario 2

- $\square$  always:  $\lambda_{in} = \lambda_{out}$  (goodput)
- "perfect" retransmission only when loss:  $\lambda' > \lambda$  out out retransmission of delayed (not lost) packet makes  $\lambda'_{in}$
- (than perfect case) for same  $\lambda_{aut}$




#### "costs" of congestion:

- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt


# Causes/costs of congestion: scenario 3\_

- four senders
- multihop paths
- 🗖 timeout/retransmit

Q: what happens as  $\lambda_{\text{in}}$  and  $\lambda_{\text{in}}'$  increase ?



## Causes/costs of congestion: scenario 3\_



#### another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

## Approaches towards congestion control

#### two broad approaches towards congestion control:

#### end-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

#### network-assisted congestion control:

- routers provide feedback to end systems
  - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
  - explicit rate sender should send at

## Case study: ATM ABR congestion control


#### ABR: available bit rate:

- "elastic service"
- if sender's path "underloaded":
  - sender should use available bandwidth
- if sender's path congested:
  - sender throttled to minimum guaranteed rate

#### RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
  - O NI bit: no increase in rate (mild congestion)
  - CI bit: congestion indication
- RM cells returned to sender by receiver, with bits intact

## Case study: ATM ABR congestion control



- two-byte ER (explicit rate) field in RM cell
  - ocongested switch may lower ER value in cell
  - sender' send rate thus maximum supportable rate on path
- □ EFCI bit in data cells: set to 1 in congested switch
  - if data cell preceding RM cell has EFCI set, sender sets CI bit in returned RM cell

# Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer


- 3.5 Connection-oriented transport: TCP
  - segment structure
  - oreliable data transfer
  - flow control
  - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

# TCP congestion control:

- goal: TCP sender should transmit as fast as possible, but without congesting network
  - O Q: how to find rate just below congestion level
- decentralized: each TCP sender sets its own rate, based on *implicit* feedback:
  - ACK: segment received (a good thing!), network not congested, so increase sending rate
  - lost segment: assume loss due to congested network, so decrease sending rate

## TCP congestion control: bandwidth probing

- "probing for bandwidth": increase transmission rate on receipt of ACK, until eventually loss occurs, then decrease transmission rate
  - continue to increase on ACK, decrease on loss (since available bandwidth is changing, depending on other connections in network)



- Q: how fast to increase/decrease?
  - details to follow


# TCP Congestion Control: details

sender limits rate by limiting number of unACKed bytes "in pipeline":

```
LastByteSent-LastByteAcked < cwnd cwnd: differs from rwnd (how, why?)
```

- sender limited by min(cwnd,rwnd)
- roughly,

rate = \frac{CWMa}{RTT} bytes/sec \frac{CWMa}{CWNA} is dynamic, function of perceived network congestion



## TCP Congestion Control: more details

#### segment loss event: reducing cwnd


- □ timeout: no response from receiver
  - cut cwnd to 1
- □ 3 duplicate ACKs: at least some segments getting through (recall fast retransmit)
  - cut cwnd in half, less aggressively than on timeout

#### ACK received: increase cwnd

- slowstart phase:
  - increase exponentially fast (despite name) at connection start, or following timeout
- congestion avoidance:
  - increase linearly

# TCP Slow Start


- when connection begins, cwnd = 1 MSS
  - example: MSS = 500 bytes & RTT = 200 msec
  - o initial rate = 20 kbps
- available bandwidth may be >> MSS/RTT
  - desirable to quickly ramp up to respectable rate
- increase rate exponentially until first loss event or when threshold reached
  - double cwnd every RTT
  - done by incrementing cwnd by 1 for every ACK received



# Transitioning into/out of slowstart

ssthresh: cwnd threshold maintained by TCP

- on loss event: set ssthresh to cwnd/2
  - remember (half of) TCP rate when congestion last occurred
- when cwnd >= ssthresh: transition from slowstart to congestion avoidance phase



# TCP: congestion avoidance


- when cwnd > ssthresh grow cwnd linearly
  - increase cwnd by 1 MSS per RTT
  - approach possible congestion slower than in slowstart
  - implementation: cwnd = cwnd + MSS/cwnd for each ACK received

#### AIMD


- ACKs: increase cwnd by 1 MSS per RTT: additive increase
- loss: cut cwnd in half (non-timeout-detected loss): multiplicative decrease

AIMD: Additive Increase <u>Multiplicative</u> <u>Decrease</u>

#### TCP congestion control FSM: overview



### TCP congestion control FSM: details




# Fast Retransmits

- Resend a segment after 3 duplicate ACKs
  - Duplicate ACK means that an out-of sequence segment was received

#### 🗖 Notes:


- ACKs are for next expected packet
- Packet reordering can cause duplicate ACKs
- Window may be too small to get enough duplicate ACKs



# Fast Recovery: After a Fast Retransmit

- $\square$  ssthresh = cwnd / 2
- cwnd = ssthresh
  - Instead of setting cwnd to 1, cut cwnd in half (multiplicative decrease)
- For each dup ack arrival
  - o dupack++
  - Indicates packet left network, so we may be able to send more
  - MaxWindow = min(cwnd + dupack, AdvWin)
- Receive ack for new data (beyond initial dup ack)
  - dupack = 0
  - Exit fast recovery
- $\square$  But when RTO expires still do *cwnd* = 1

# Fast Retransmit and Fast Recovery



- Retransmit after 3 duplicated acks
  - Prevent expensive timeouts
- □ Reduce slow starts
- At steady state, cwnd oscillates around the optimal window size


# TCP Congestion Control Summary

- Measure available bandwidth
  - Slow start: fast, hard on network
  - AIMD: slow, gentle on network
- Detecting congestion
  - Timeout based on RTT
    - Robust, causes low throughput
  - Fast Retransmit: avoids timeouts when few packets lost
    - Can be fooled, maintains high throughput
- Recovering from loss
  - Fast recovery: don't set cwnd=1 with fast retransmits

# TCP Flavors

- □ TCP-Tahoe
  - cwnd =1 whenever drop is detected
- □ TCP-Reno
  - cwnd =1 on timeout
  - cwnd = cwnd/2 on dupack
- □ TCP-newReno
  - TCP-Reno + improved fast recovery
- □ TCP-SACK

# Popular "flavors" of TCP




# TCP-SACK

- □ SACK = Selective Acknowledgements
- ACK packets identify exactly which packets have arrived
- Makes recovery from multiple losses much easier

# TCP behavior

- congestion control:
  - decrease sending rate when loss detected, increase when no loss
- routers
  - discard, mark packets when congestion occurs
- interaction between end systems (TCP) and routers?
  - want to understand (quantify) this interaction




congested router drops packets

# Generic TCP behavior

- $\square$  window algorithm (window W)
  - oup to Wpackets in network
  - return of ACK allows sender to send another packet
  - cumulative ACKS
- increase window by one per RTT


  W<- W+1/W per ACK

  ⇒ W<- W+1 per RTT</pre>
- seeks available network bandwidth




# Generic TCP behavior

- □ window algorithm (window W)
- □ increase window by one per RTT  $W \leftarrow W + 1/W per ACK$
- loss indication of congestion
- decrease window by half on detection of loss, (triple duplicate ACKs), W <- W/2




# Generic TCP Behavior

- □ window algorithm (window W)
- increase window by one per RTT  $W \leftarrow W + 1/W$  per ACK
- $\square$  halve window on detection of loss,  $W \leftarrow W/2$
- $\Box$  timeouts due to lack of ACKs -> window reduced to one, W < -1



# Generic TCP Behavior


- □ window algorithm (window W)
- □ increase window by one per RTT (or one over window per ACK,  $W \leftarrow W + 1/W$ )
- $\square$  halve window on detection of loss,  $W \leftarrow W/2$
- $\Box$  timeouts due to lack of ACKs, W <- 1
- successive timeout intervals grow exponentially long up to six times




#### Idealized model:

- W is maximum supportable window size (then loss occurs)
- □ TCP window starts at W/2 grows to W, then halves, then grows to W, then halves...
- one window worth of packets each RTT
- to find: throughput as function of loss, RTT

# packets sent per "period" =





# packets sent per "period" =


$$\frac{W}{2} + \left(\frac{W}{2} + 1\right) + \dots + W = \sum_{n=0}^{W/2} \left(\frac{W}{2} + n\right)$$

$$= \left(\frac{W}{2} + 1\right) \frac{W}{2} + \sum_{n=0}^{W/2} n$$

$$= \left(\frac{W}{2} + 1\right) \frac{W}{2} + \frac{W/2(W/2 + 1)}{2}$$

$$= \frac{3}{8}W^2 + \frac{3}{4}W$$

$$\approx \frac{3}{8}W^2$$



# packets sent per "period" 
$$\approx \frac{3}{8}W^2$$

1 packet lost per "period" implies:

$$p_{loss} \approx \frac{8}{3W^2}$$
 or:  $W = \sqrt{\frac{8}{3p_{loss}}}$ 

$$B = \text{avg.\_thruput} = \frac{3}{4}W \frac{\text{packets}}{\text{rtt}}$$

$$B = \text{avg.\_thruput} = \frac{1.22}{\sqrt{p_{loss}}} \frac{\text{packets}}{\text{rtt}}$$

B throughput formula can be extended to model timeouts and slow start (PFTK)

# TCP Futures: TCP over "long, fat pipes"

- example: 1500 byte segments, 100ms RTT, want 10
   Gbps throughput
- requires window size W = 83,333 in-flight segments
- throughput in terms of loss rate:

$$\frac{1.22 \cdot MSS}{RTT\sqrt{L}}$$


- $\Box$   $\rightarrow$  L = 2.10-10 Wow
- new versions of TCP for high-speed

# Summary: TCP Congestion Control

- when cwnd < ssthresh, sender in slow-start phase, window grows exponentially.
- when cwnd >= ssthresh, sender is in congestion-avoidance phase, window grows linearly.
- when triple duplicate ACK occurs, ssthresh set to cwnd/2, cwnd set to ~ ssthresh
- when timeout occurs, ssthresh set to cwnd/2, cwnd set to 1 MSS.

# TCP Fairness


fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



# Why is TCP fair?

#### Two competing sessions:

- Additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



# Fairness (more)


#### Fairness and UDP

- multimedia apps often do not use TCP
  - do not want rate throttled by congestion control
- □ instead use UDP:
  - pump audio/video at constant rate, tolerate packet loss


# Fairness and parallel TCP connections

- nothing prevents app from opening parallel connections between 2 hosts.
- web browsers do this
- example: link of rate R supporting 9 connections;
  - o new app asks for 1 TCP, gets rate R/10
  - o new app asks for 11 TCPs, gets R/2!

- □ Two cases
  - 3 duplicate ACKs (network capable of delivering some packers)
  - -Timeout (more alarming)
- Two phases
  - Slow start (SS) MI
     2\*cwnd per RTT till congestion
    - 2. Congestion avoidance(CA) AIMD cwnd increase by 1 per RTT
      - 3 duplicate ACKs → cwnd = cwnd/2
      - Timeout → cwnd =1
      - In timeout → timeout = 2\*timeout




SS - Slow Start
CA - Congestion Avoidance
TD - Three Duplicate ACKs
TO - Timeout



When cwnd is cut to half, why does sending rate not get cut?

Ν

There is a filling and draining of buffers for each TCP flow.



# TCP/ Reno Analysis

## TCP/ Reno Throughput Analysis

- Understand throughput in terms of
  - RTT
  - Packet loss rate (p)
  - Packet size (S)

#### Throughput calculations


- Assume congestion avoidance and no timeouts occur
- Mean window size  $W_m$  segments, round trip time RTT & pack size S

### Deterministic Analysis

#### Consider congestion avoidance


- Assume one packet is lost per cycle
- Total packets sent per cycle =  $\frac{1}{2}$ \*(W + W/2) \* W/2 = 3W<sup>2</sup>/8
- Packet loss (p) =  $1/(3W^2/8) = 8/(3W^2) + \frac{\sqrt{8/3}}{\sqrt{p}} = \frac{1.6}{\sqrt{p}}$

Throughput = 
$$\frac{S*W_m}{RTT} = \frac{S}{RTT} \left( \frac{3}{4} \frac{1.6}{\sqrt{p}} \right) = \frac{1.2S}{RTT \sqrt{p}}$$



### TCP/ Reno Drawbacks

Multiple packets lost simultaneously cannot be accounted for



### TCP/ Reno Drawbacks

- RTT unfairness
  - Flows with different RTT's grow their congestion windows differently
  - Users with shorter RTT ramp up faster!
  - On long distance links, RTT is high and cwnd takes longer to increase leading to underutilization of link.
- Synchronized losses
  - Simultaneous packet loss events for multiple competing flows.

New Protocol Necessary!!

### Desired Characteristics in TCP


- Adaptive schemes that grow the congestion window dep network conditions
  - Scalable
  - RTT Fairness
  - Faster convergence to better utilize full bandwidth

## TCP BIC

http://www.land.ufrj.br/~classes/coppe-redes-2007/projeto/BIC-TCP-infocom-04.pdf

### Growth functions

Consider TCP/Reno growth function



Grows linearly throughout

### TCP BIC

#### Binary Increase Congestion Control (BIC) algorithm

#### PHASE 1


- cwnd < low\_wind, follows TCP</p>
  - ACK received : cwnd = cwnd + 1
    - Loss event: cwnd = cwnd/2

#### PHASE 2

cwnd > low\_wind, follows BIC

- Some preliminaries
  - ßmultiplicative decrease factor
  - $W_{\text{max}}$  = cwnd size before the reduction
  - $W_{min} = \beta^* W_{max}$  just after reduction
  - midpoint = (Wmax + Wmin)/2

BIC performs binary search between  $W_{\text{max}}$  and  $W_{\text{min}}$  looking for the midpoint.



```
while (cwnd != W_{max}){
If ((W_{min} - midpoint) > S_{max})
                                                                     Additive Increase
     cwnd = cwnd + S_{max}
  else
     If ((W_{min} - midpoint) \leq S_{min})
         cwnd = W_{max}
     else
                                                                    Binary Search
          cwnd = midpoint
  If (no packet loss)
     W_{min} = cwnd
  else
     W_{min} = \beta * cwnd
     W_{max} = cwnd
  midpoint = (W_{max} + W_{min})/2
  }
```

```
while (cwnd >= W_{max}){

If (cwnd < W_{max} + S_{max})

cwnd = cwnd + S_{min}


else
cwnd = cwnd + S_{max}

Additive Increase


If (packet loss)
W_{min} = \beta * cwnd
W_{max} = cwnd
}
```

Max Probin

# TCP BIC - Summary



### TCP BIC in Action



## TCP BIC Advantages

- Scalability: quickly scales to fair BW share
- Fairness and convergence: Achieves better fairness and faster convergence
- Slow Growth around  $W_{\text{max}}$  ensures that unnecessary timeouts do not occur.

#### TCP BIC Drawbacks

- cwnd growth is aggressive for TCP with short RTT or low speed
  - Short RTT makes cwnd ramp up soon
- Still dependent on RTT
  - Proportional to inverse square of the RTT like TCP/ Reno
- Complex window growth function
  - Difficult for analysis and actual implementation

# TCP Cubic

http://www4.ncsu.edu/~rhee/export/bitcp/cubic-paper.pdf


### TCP Cubic

- cwnd =  $C( + K)^3 + W_{max}$ 
  - $W_{max}$  = cwnd before last reduction
  - ßmultiplicative decrease factor
  - C scaling factor

$$- K = \sqrt[3]{W\beta/C}$$

- t is the time elapsed since last window reduction

### TCP CUBIC



### TCP Cubic Advantages

- Good RTT fairness
  - Growth dominated by t, competing flows have same t after synchronized packet loss
- Real-time dependent
  - Similar to BIC but linear increases are time dependent
  - Does not depend on ACK's like TCP/ Reno
- Scalability
  - Cubic increases window to  $W_{\text{max}}$  (or its vicinity) quickly and keeps it there longer

### TCP Cubic Drawbacks

- Slow Convergence
  - Flows with higher cwnd are more aggressive initially
  - Prolonged unfairness between flows
- Bandwidth Delay Products
  - Linear increase artefacts

# Chapter 3: Summary

- principles behind transport layer services:
  - multiplexing, demultiplexing
  - oreliable data transfer
  - flow control
  - congestion control
- instantiation and implementation in the Internet
  - O UDP
  - O TCP

#### <u>Next:</u>

- leaving the network "edge" (application, transport layers)
- □ into the network "core"