

Operating Lease Support System Phase-2 Project for



Functional Specification FC.AD.1.5 Generate BAST Replaceement Unit

Revision 2.0

PT. Berlian Sistem Informasi

KTB Annex Bld. 4th Floor, Jl. Jend. A. Yani. Pulomas, Tel. +62 21 4786 7575 (Hunting) Fax. +62 21 4714964 www.bsi.co.id

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

Document Control

| Author | Windy Adam |
|-------------------|--|
| File Name | TM15404A-FSP-FC.AD.1.5 Generate BAST Replacement Unit Rev 2.0 |
| Directory Address | \OPRLEASE-P2\Deliverable Based-2\Working\04. Design\04.02. Functional Specification\TM15404A-FSP-FC.AD.1.5 Generate BAST Replacement Unit Rev 2.0.docx |
| Number of Page | 87 |

Revision History

| Date | Revision | Description | Author |
|-----------|----------|---|-----------------|
| 9/11/2015 | 0.0 | Initialization | Windy Adam |
| 11/1/2016 | 0.1 | Revise DSF Project Director (page 2 and 3) | Windy Adam |
| 11/1/2016 | 1.0 | 1 st Baseline | Windy Adam |
| 19/2/2016 | 1.1 | NBD Review: Revise Output Code from RPT into PF (page 6) Revise identifier number RPC into RPU, BRC into BRU, BOP into BOU, and MMO into MRU (page 7) Add description OPL unit at Screen of Configuration Access, and Screen Functionality (page 8) Add screen 5. Replacement Unit Police Number (page 12) Revise screen 7. OPL Unit Police Number (page 13) | Windy Adam |
| 10/6/2016 | 2.0 | 2 nd Baseline | Grand Zah Putra |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

Distribution List

| Name | Organization | Roles |
|------------------------|------------------------------|---------------------------|
| Mr. Yutaro Sanada | Dipo Star Finance, PT | DSF Project Director |
| Mr. Manabu Kishimoto | Dipo Star Finance, PT | DSF Project Director |
| Mr. Shinya Tsukamoto | Dipo Star Finance, PT | DSF IT Advisor |
| Mr. Ahmad Fikri | Dipo Star Finance, PT | DSF IT Advisor |
| Mr. Abdul Somad | Dipo Star Finance, PT | DSF Biz. Operation Leader |
| Mr. Roby Wijaya | Dipo Star Finance, PT | DSF PMO |
| Mr. Mukhlis Ibrahim | Dipo Star Finance, PT | DSF IT Operation Leader |
| Mr. Delta Riangga | Dipo Star Finance, PT | DSF Key User |
| Mr. Mochamad Idris | Dipo Star Finance, PT | DSF Key User |
| Mr. Jufi Iqbal | Dipo Star Finance, PT | DSF Key User |
| Mr. Reza Renika | Dipo Star Finance, PT | DSF Key User |
| Mrs. Herni Hembang | Dipo Star Finance, PT | DSF Key User |
| Mrs. Olivia Setiawan | Dipo Star Finance, PT | DSF Key User |
| Mr. Junaidi Didy | Dipo Star Finance, PT | DSF Key User |
| Mr. Dedi Supriyadi | Dipo Star Finance,PT | DSF Key User |
| Mrs. Elke Hilviana | Dipo Star Finance,PT | DSF Key User |
| Mr. Daiki Kamada | Berlian Sistem Informasi, PT | BSI Project Director |
| Mr. Yoshinori Kawahara | Berlian Sistem Informasi, PT | BSI IT Advisor |
| Mr. Satoshi Koibuchi | Berlian Sistem Informasi, PT | BSI IT Advisor |
| Mr. Grand Zah Putra | Berlian Sistem Informasi, PT | BSI Project Manager |
| Mr. Raymond | Berlian Sistem Informasi, PT | BSI Technical Leader |
| Ms. Windy Adam | Berlian Sistem Informasi, PT | BSI Business Analyst |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

Document Approval

By signing this document I acknowledge I have read the document and give the Project Management Team approval to proceed.

| Role | Name | Signature | Date |
|----------------------|----------------------|-----------|------|
| DSF Project Director | Mr. Yutaro Sanada | | |
| DSF IT Advisor | Mr. Shinya Tsukamoto | | |
| DSF IT Advisor | Mr. Ahmad Fikri | | |
| DSF Project Manager | Mr. Abdul Somad | | |
| DSF PMO | Mr. Roby Wijaya | | |
| BSI Project Director | Mr. Daiki Kamada | | |
| BSI Project Manager | Mr. Grand Zah Putra | | |
| BSI Technical Leader | Mr. Raymond | | |
| BSI Business Analyst | Ms. Windy Adam | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

TABLE OF CONTENTS

| DOCUM | ENT CONTROL | 2 |
|---------|---|-------|
| REVISIO | N HISTORY | 2 |
| DISTRIB | UTION LIST | 3 |
| DOCUM | ENT APPROVAL | 4 |
| 1 IN | ITRODUCTION | 6 |
| 1.1 | Purpose | 6 |
| 1.2 | Scope | |
| 1.3 | DEFINITION, ACRONYMS, AND ABBREVIATIONS | 6 |
| 1.4 | References | |
| 2 CC | ONFIGURATION | 7 |
| 3 SP | PECIFICATION DETAIL: FC.AD.1.5 GENERATE BAST REPLACEMENT UN | JI T7 |
| 3.1 | Purpose | 7 |
| 3.2 | Screen of Configuration Access | 8 |
| 3.3 | SCREEN FUNCTIONALITY | 8 |
| 3.4 | OPERATION FLOW | 8 |
| 3.5 | Screen Design | |
| 3.6 | COMPONENT SCREEN FUNCTIONALITY | |
| 3.7 | OPERATION DESCRIPTION | |
| 3.8 | Data Structure | |
| 3.9 | SCREEN ITEM LIST | |
| 3.10 | ENTITY RELATIONSHIP DIAGRAM | 86 |

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |

Functional Specification

1 Introduction

1.1 Purpose

Functional Specification is a document to describe the detail of functions system which includes screen design, report, and logic formula. This document will be used for system development.

1.2 Scope

Functional Specification Document contains screen design, screen functionality, process flow, and data structure of AD.1.3 Manage Replacement Unit Preparation and AD.1.4 Manage Replacement Unit Execution

Here are the scope for AD.1.3 Manage Replacement Unit Preparation:

1. AD.1.3.4 Create Replacement

Input data for request replacement unit and Prepare for BAST document Replacement Unit including register replacement unit

2. AD.1.3.5 Edit Replacement

Edit request replacement unit Prepare for editing BAST document Replacement Unit

3. AD.1.3.6 Submit Replacement

Submit replacement data for special cases, which replacement unit request data will be submit to Directors for approval request

4. AD.1.3.7 View Replacement

View detail replacement data that already submit by Asset Management

5. AD.1.3.8 Print Replacement

Print BAST unit Replacement, BAST unit leased

Here are the scope for AD.1.4 Manage Replacement Unit Execution:

1. AD.1.4.10 Update Replacement Unit Based on BAST Out or In

View list of Replacement unit data and update BAST replacement unit result

Output from this functions is:

- 1. PF.AD.1.3 BAST OPL Unit
- 2. PF.AD.1.4 BAST Replacement Unit
- 3. Memo Replacement Unit (new requirement)

1.3 Definition, Acronyms, and Abbreviations

1. OPL = Operating Lease

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

2. BAST = Berita Acara Serah Terima / Handover Report

1.4 References

This functional specification document refers to "To Be Design" BSI Unit/Vehicle Management Process, module:

- 1. AD.1.3 Manage Replacement Unit Preparation
- 2. AD.1.4 Manage Replacement Unit Execution

2 Configuration

1. Registration Number Replacement Unit:

00001/RPU/JKT/11/2015

- Segment 1: 5 digit running number
- Segment 2: Identifier of number (RPU= Registration Replacement Car)
- Segment 3: DSF Office short name
- Segment 4: Month Registration actual date
- Segment 5: Year BAST actual date
- 2. BAST Number Replacement Unit:

00001/BRU/JKT/11/2015

- Segment 1: 5 digit running number
- Segment 2: Identifier of number (BRU = BAST Replacement Unit)
- Segment 3: DSF Office short name
- Segment 4: Month BAST Replacement actual date
- Segment 5: Year BAST Replacement actual date
- 3. BAST Number Operating Lease Unit:

00001/BOU/JKT/11/2015

- Segment 1: 5 digit running number
- Segment 2: Identifier of number (BOU = BAST Operating Lease Unit)
- Segment 3: DSF Office short name
- Segment 4: Month BAST Replacement actual date
- Segment 5: Year BAST Replacement actual date
- 4. Memo Replacement Unit:

00001/MRU/JKT/11/2015

- Segment 1: 5 digit running number
- Segment 2: Identifier of number (MRU = Memo)
- Segment 3: DSF Office short name
- Segment 4: Month BAST Replacement actual date
- Segment 5: Year BAST Replacement actual date

3 Specification Detail: FC.AD.1.5 Generate BAST Replacement Unit

3.1 Purpose

Generate BAST unit replacement is process related to input replacement unit request for preparing BAST replacement unit and submit BAST result Out and BAST In of Replacement unit and OPL unit. This process includes registering replacement unit mapping to each Agreement number and OPL unit. Outputs of the process are BAST replacement unit and BAST OPL unit Out and In.

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

This function covered by 3 screens "Create BAST Unit Replacement", "Edit BAST Unit Replacement", and "View BAST Unit Replacement" screens. There is 1 additional screen for registering replacement unit which is "Registration Replacement Unit" screen. These 4 screens accessed via the main screen which is "Monitoring Unit OPL and Replacement Unit", (refer to FC.AD.1.4 Monitoring and Print Unit OPL and Replacement Unit).

3.2 Screen of Configuration Access

Here are the access right for "Create/Edit/View BAST Unit Replacement" screens users:

| User | Create | Read | Update | Print | Authorization |
|----------------------|--------|------|--------|-------|---------------|
| DSF Authorize Person | - | V | - | - | V |
| PIC Asset | V | V | V | V | V |
| Management | | | | | |
| Admin | V | V | V | V | V |

Note:

- 1. Create: related to creation of BAST OPL Unit and Replacement Unit
- 2. Read: related to read display BAST OPL Unit and Replacement Unit
- 3. Update: related to update and submit OPL Unit and Replacement Unit
- 4. Print: related to print BAST OPL Unit and Replacement Unit
- 5. Authorization: related to access screen of Monitoring OPL Unit and Replacement Unit


3.3 Screen Functionality


- 1 Display Monitoring OPL Unit and Replacement Unit
- 2 Generate BAST OPL Unit and Replacement Unit
- 3 Edit BAST OPL Unit and Replacement Unit
- 4 Submit Memo replacement special case
- 5 View BAST OPL Unit and Replacement Unit
- 6 Print BAST OPL Unit and Replacement Unit
- 7 Update OPL Unit and Replacement Unit based on BAST Out or In

3.4 Operation Flow


Below is operation flow for Monitoring and print unit preparation process refer to **To Be Design Document Unit/ Vehicle Management**, AD.1.3 Manage Replacement Unit Preparation and AD.1.4 Manage Replacement Unit Execution:


| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |






| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |





3.5 Screen Design

Initial Screen Monitoring Unit Preparation




Screen 1. Monitoring OPL Unit and Replacement Unit - Replacement Unit

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |



Screen 2. Register Unit Replacement Pop Up Dialog

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |




Screen 3. Registration Number Pop Up Dialog




Screen 4. DSF Office List Pop Up Dialog

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |




Screen 5. Replacement Unit List Pop Up Dialog




Screen 6. Model Name List Pop Up Dialog

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |




Screen 7. Agreement Number List Pop Up Dialog




Screen 8. OPL Unit Police Number List Pop Up Dialog


| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |




Screen 9. Create BAST OPL Unit and Replacement Unit Pop Up Dialog



Screen 10. Edit BAST OPL Unit and Replacement Unit Pop Up Dialog




Screen 11. View BAST OPL Unit and Replacement Unit Pop Up Dialog




Screen 12. Print BAST OPL Unit and Replacement Unit Pop Up Dialog

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |




Screen 13. Create BAST Replacement – Replacement Unit

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |




Screen 14. Create BAST Replacement – OPL Unit

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |




Screen 15. Edit BAST Replacement – Replacement Unit

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |




Screen 16. Edit BAST Replacement – OPL Unit

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |




Screen 17. View BAST Replacement - Replacement Unit

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |




Screen 18. View BAST Replacement – OPL Unit

| Project Code : | TM15404A | |
|----------------|--|--|
| Project Name : | Operating Lease Support System Phase-2 | |




Screen 19. BAST List Pop Up Dialog

• Confirmation Pop Up



Screen 20. Confirmation Pop Up When Register Replacement Unit




Screen 21. Confirmation Pop Up When Save as Draft BAST Replacement


| Project Code : | TM15404A | |
|----------------|--|--|
| Project Name : | Operating Lease Support System Phase-2 | |



Screen 22. Confirmation Pop Up When Submit BAST Replacement



Screen 23. Confirmation Pop Up When Save as Change BAST Replacement




Screen 24. Confirmation Pop Up When Save as Final BAST Replacement

Note: BAST Replacement consist of BAST replacement Out and BAST In. NotificationPop Up for both are same, the difference only on description "Are you sure want to Save As Final/Submit/Save Change BAST Replacement In/ BAST Replacement Out?"


| Project Code : | TM15404A | |
|----------------|--|--|
| Project Name : | Operating Lease Support System Phase-2 | |

• Notification Pop Up When Register Replacement Unit



Screen 25. Notification Pop Up When Register Replacement Unit


• Notification Pop Up When Save as Draft BAST Replacement



Screen 26. Confirmation Pop Up When Save as Draft BAST Replacement


| Project Code : | TM15404A | |
|----------------|--|--|
| Project Name : | Operating Lease Support System Phase-2 | |

• Notification Pop Up When Save Change BAST Replacement



Screen 27. Notification Pop Up When Save Change BAST Replacement


Notification Pop Up When Submit BAST Replacement



Screen 28. Notification Pop Up When Submit BAST Replacement

| Project Code : | TM15404A | |
|----------------|--|--|
| Project Name : | Operating Lease Support System Phase-2 | |

• Notification Pop Up When Save as Final BAST Replacement



Screen 29. Notification Pop Up When Save as Final BAST Replacement

3.6 Component Screen Functionality

a. Monitoring OPL Unit and Replacement Unit – Replacement Unit

Here are the screen functions from each component in Screen 1. Monitoring

OPL Unit and Replacement Unit – Replacement Unit tab:

| No | Component | Name | Function | |
|-------|---------------|---|--|--|
| Heade | Header | | | |
| 1 | Label | Monitoring OPL Unit and Replacement unit | Monitoring OPL Unit and Replacement Unit title | |
| Searc | h Criteria | | | |
| 2 | Drop down box | Search Criteria | To select category for searching replacement unit data | |
| 3 | Text field | Parameter | To input parameter for searching replacement unit data | |
| 4 | Date Picker | Start Modified Date | To input start period based on update date when print replacement unit data report | |
| 5 | Date Picker | End Modified Date Period | To input end period based on update date when print replacement unit data report | |
| 6 | Button | Search | To search replacement unit data based on selected criteria | |

| Project Code : | TM15404A | |
|----------------|--|--|
| Project Name: | Operating Lease Support System Phase-2 | |

| List | List of Tab | | | | |
|------|-------------|---|---|--|--|
| 7 | Tab | Monitoring OPL Unit and Replacement Unit – Replacement Unit | To display information availabitily status and location of Replacement Unit | | |
| 8 | Button | Register Replacement Unit | To register replacement unit | | |
| 9 | Button | Approval Replacement | To display list of approval replacement unit due to Special Case (refer to FC.AD.1.6 Replacement Unit Approval) | | |
| 10 | Label | DSF Office | To display DSF Office/ Branch of Unit OPL | | |
| 11 | Label | Registration Number | To display registration number of Replacement unit | | |
| 12 | Label | Replacement Unit Police No | To display list Police No of Replacement Unit | | |
| 13 | Label | Model Unit | To display unit model description of Unit Replacement | | |
| 14 | Label | Agreement No | To display list agreement number of OPL unit | | |
| 15 | Label | Customer Name | To display Customer Name based on agreement | | |
| 16 | Label | OPL Unit Police No | To display list Police No of OPL Unit | | |
| 17 | Label | Active/Not Active | To display status Active/ Not Active of Replacement Unit still supports for one unit OPL in Agreement Number | | |
| 18 | Label | Status Replacement Unit | To display Status of Unit; Customer, Return, Workshop, Claim Insurance) | | |
| 19 | Label | Location Replacement Unit – Company Name | To display location of unit (Company name) | | |
| 20 | Label | Location Replacement Unit – Site | To display location of unit (location of company) | | |
| 21 | Label | Replacing | To display information of OPL unit that being replace by replacement unit | | |
| 22 | Label | Replacement Type | To display information of replacement type; General Repair, Special Case, Insurance | | |
| 23 | Label | Usage Period – Start Date | To display information of Start Date Replacement Unit Usage | | |
| 24 | Label | Usage Period – Estimation | To display information of Estimation Replacement Unit Usage | | |
| 25 | Label | Usage Period – End Date | To display information of End Date Replacement Unit Usage | | |
| 26 | Label | Create By (BAST) | To display information Create By BAST | | |
| 27 | Label | Create Date (BAST) | To display information Create Date BAST | | |

| Project Code : | TM15404A | |
|----------------|--|--|
| Project Name : | Operating Lease Support System Phase-2 | |

| 28 | Label | Last Modified By | To display information Last Modified By |
|------|--------|-----------------------|---|
| | | (BAST) | BAST |
| 29 | Label | Last Modified | To display information Last Modified |
| | | Date (BAST) | Date BAST |
| 30 | Button | Action – Create | To create BAST of Replacement Unit |
| | | BAST | |
| 31 | Button | Action – Edit | To adit DACT of Danisasment Unit |
| 31 | Button | | To edit BAST of Replacement Unit |
| | | BAST | |
| 32 | Button | Action – View | To view BAST of Replacement Unit |
| | | BAST | |
| 33 | Button | Action – Print | To print BAST of Replacement Unit |
| 00 | Button | BAST | To print Brief of Replacement Crit |
| 2.4 | D. H | | To view bistom DACT of Doubstone |
| 34 | Button | Action – View | To view history BAST of Replacement |
| | | History BAST | Unit |
| 35 | Labal | Showing 1 to <i>n</i> | Display the entries generated by search |
| | Label | of <i>n</i> entries | engine |
| 36 | | _, | |
| | Link | First Page | To show the first page entry |
| 37 | | | |
| 07 | Link | Previous Page | To show the previous page entry |
| 38 | | | To show the page screen according the |
| 30 | Link | Page Number | . 6 |
| | | | number |
| 39 | Link | Next Page | To show the next page entry |
| | | | l |
| 40 | Link | Last Page | To show the last page entry |
| | LIIIX | Last rage | 10 show the last page chitry |
| Foot | er | | |
| 41 | Button | Print Report | To print report replacement unit report |
| | Datton | Time Report | as shown on the list |
| | | | as shown on the list |

b. Register Unit Replacement Pop Up Dialog

Here are the screen functions from each component in **Screen 2**. **Register Unit Replacement Pop Up Dialog**:

| No | Component | Name | Function | | |
|--------|--------------|------------------------------|---|--|--|
| Head | Header | | | | |
| 1 | Label | Register Unit Replacement | Register Unit Replacement title | | |
| List o | f Tab | | | | |
| 2 | Dropdown | Action | To select action; 1. Add → Register new data 2. Update → Update existing Data | | |
| 3 | Text field | Registration Number | To display registration Number automatically | | |
| 4 | Radio Button | Status - Active | To select status of replacement unit; Active | | |
| 5 | Radio Button | Status – Not Active | To select status of replacement unit; Active | | |
| 6 | Text field | DSF Office | To select DSF Office short name | | |
| 7 | Text field | Source Location (City) | To input source location of replacement unit | | |
| 8 | Search Box | Police Number | To select and input Police Number of replacement unit | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| 9 | Search Box | Model Replacement Unit | To select and display selected Model of Replacement Unit |
|-------|-----------------|------------------------------|---|
| 10 | Text field | Machine Number | To input and display machine number of Replacement Unit |
| 11 | Text field | Chassis Number | To input and display chassis Number of Replacement Unit |
| 12 | Text field | Colour | To input and display colour of unit |
| 13 | Calendar Picker | STNK Start Date | To select and display STNK Start Date |
| 14 | Calendar Picker | STNK End Date | To select and display STNK End Date |
| 15 | Calendar Picker | KEUR Start Date | To select and display KEUR Start Date |
| 16 | Calendar Picker | KEUR End Date | To select and display KEUR End Date |
| 17 | Text field | Insurance Company | To input and display Insurance Company |
| 18 | Text field | Insurance Policy Number | To input and display Insurance Policy Number |
| 19 | Calendar Picker | Insurance Start Date | To select and display Insurance Company |
| 20 | Calendar Picker | Insurance End Date | To input and display Insurance Company |
| 21 | Search Box | Agreement Number | To select and display selected agreement number of OPL Unit |
| 22 | Text field | Customer Name | To display customer name automatically based on selected Agreement Number |
| 23 | Text field | Police Number OPL Unit | To select Police Number of OPL unit |
| 24 | Search Box | Model OPL Unit | To display Model of OPL Unit based on selected agreement number |
| Foote | Footer | | <u> </u> |
| 25 | Button | Save | To save new or update registration unit replacement data |
| 26 | Button | Cancel | To cancel process update or create new registration unit replacement data |

 Registration Number List Pop Up Dialog
 Here are the screen functions from each component in Screen 3. Registration Number List Pop Up Dialog:

| No | Component | Name | Function | | |
|------|------------|------------------------|--|--|--|
| Head | Header | | | | |
| 1 | Label | Registration Number | Registration Number title | | |
| 2 | Dropdown | Show Entries | To select number of row data that will be displayed in one screen (paging) | | |
| 3 | Text field | Search | To search registration number based on input character searching | | |
| List | | | | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |

| 4 | Label | Registration No | To display registration Number automatically |
|-------|--------|---|--|
| 5 | Label | Replacement Unit Police No | To display list Police No of Replacement Unit |
| 6 | Label | Model Unit | To display unit model description of Unit Replacement |
| 7 | Label | OPL Unit Police No | To display list Police No of OPL Unit based on selected Agreement No |
| 8 | Label | Agreement No | To display list agreement number of OPL unit |
| 9 | Label | Showing 1 to <i>n</i> of <i>n</i> entries | Display the entries generated by search engine |
| 10 | Link | First Page | To show the first page entry |
| 11 | Link | Previous Page | To show the previous page entry |
| 12 | Link | Page Number | To show the page screen according the number |
| 13 | Link | Next Page | To show the next page entry |
| 14 | Link | Last Page | To show the last page entry |
| Foote | er | | |
| 15 | Button | Close | To close pop up windows |

d. DSF Office List Pop Up Dialog

Here are the screen functions from each component in **Screen 4. DSF Office List**:

| No | Component | Name | Function | | |
|-------|------------|---|--|--|--|
| Heade | Header | | | | |
| 1 | Label | DSF Office List | DSF Office title | | |
| 2 | Dropdown | Show Entries | To select number of row data that will be displayed in one screen (paging) | | |
| 3 | Text field | Search | To search DSF Office based on input character searching | | |
| List | | | | | |
| 4 | Label | Office Short Name | To display DSF Office short name | | |
| 5 | Label | Office Name | To display Office Name | | |
| 6 | Label | Showing 1 to <i>n</i> of <i>n</i> entries | Display the entries generated by search engine | | |
| 7 | Link | First Page | To show the first page entry | | |
| 8 | Link | Previous Page | To show the previous page entry | | |
| 9 | Link | Page Number | To show the page screen according the number | | |
| 10 | Link | Next Page | To show the next page entry | | |
| 11 | Link | Last Page | To show the last page entry | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| Footer | | | |
|--------|--------|-------|-------------------------|
| 12 | Button | Close | To close pop up windows |

e. Replacement Unit Police Number

Here are the screen functions from each component in **Screen 5**. **Replacement Unit List pop Up Dialog**:

| No | Component | Name | Function |
|-------|------------|---|--|
| Heade | er | | |
| 1 | Label | Replacement Unit Police Number List | Replacement Unit Police Number List title |
| 2 | Dropdown | Show Entries | To select number of row data that will be displayed in one screen (paging) |
| 3 | Text field | Search | To search police number of replacement unit |
| List | | | |
| 4 | Label | Police Number | To display list of Brand Name Replacement Unit |
| 5 | Label | Created Date | To display list of Created Date |
| 6 | Label | Showing 1 to <i>n</i> of <i>n</i> entries | Display the entries generated by search engine |
| 7 | Link | First Page | To show the first page entry |
| 8 | Link | Previous Page | To show the previous page entry |
| 9 | Link | Page Number | To show the page screen according the number |
| 10 | Link | Next Page | To show the next page entry |
| 11 | Link | Last Page | To show the last page entry |
| Foote | r | | |
| 12 | Button | Close | To close pop up windows |

f. Model Name List Pop Up Dialog

Here are the screen functions from each component in **Screen 6. Model Name List Pop Up Dialog**:

| No | Component | Name | Function | | |
|-------|------------|-----------------|--|--|--|
| Heade | Header | | | | |
| 1 | Label | Model Name List | Model Name List title | | |
| 2 | Dropdown | Show Entries | To select number of row data that will be displayed in one screen (paging) | | |
| 3 | Text field | Search | To search Brand Name and Model Name of Replacement Unit based on input character searching | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| List | | | |
|--------|--------|---|---|
| 4 | Label | Brand Name | To display list of Brand Name Replacement Unit |
| 5 | Label | Model Name | To display list of Model name Replacement Unit |
| 6 | Label | Showing 1 to <i>n</i> of <i>n</i> entries | Display the entries generated by search engine |
| 7 | Link | First Page | To show the first page entry |
| 8 | Link | Previous Page | To show the previous page entry |
| 9 | Link | Page Number | To show the page screen according the number |
| 10 | Link | Next Page | To show the next page entry |
| 11 | Link | Last Page | To show the last page entry |
| Footer | | | |
| 12 | Button | Close | To close pop up windows |

g. Agreement Number List
Here are the screen functions from each component in Screen 7. Agreement Number List:

| No | Component | Name | Function | |
|-------|------------|---|--|--|
| Heade | Header | | | |
| 1 | Label | Agreement Number List | Agreement Number List title | |
| 2 | Dropdown | Show Entries | To select number of row data that will be displayed in one screen (paging) | |
| 3 | Text field | Search | To search Agreement number based on input character searching | |
| List | | | | |
| 4 | Label | Agreement Number | To display list of Agreement Number | |
| 5 | Label | Customer Name | To display list of customer name of Agreement Number | |
| 6 | Label | Showing 1 to <i>n</i> of <i>n</i> entries | Display the entries generated by search engine | |
| 7 | Link | First Page | To show the first page entry | |
| 8 | Link | Previous Page | To show the previous page entry | |
| 9 | Link | Page Number | To show the page screen according the number | |
| 10 | Link | Next Page | To show the next page entry | |
| 11 | Link | Last Page | To show the last page entry | |
| Foote | Footer | | | |
| 12 | Button | Close | To close pop up windows | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

h. OPL Police Number List

Here are the screen functions from each component in **Screen 8. OPL Police Number List**:

| No | Component | Name | Function | |
|-------|--------------|---|--|--|
| Heade | er | | | |
| 1 | Label | OPL Police Number List | OPL Police Number title | |
| 2 | Dropdown | Show Entries | To select number of row data that will be displayed in one screen (paging) | |
| 3 | Text field | Search | To search Police Number of OPL Unit based on input character searching | |
| List | | | | |
| 4 | Radio Button | Select Police No | To select Police number of OPL Unit | |
| 5 | Label | Police Number | To display list of Police number OPL Unit | |
| 6 | Label | Status | To display list of status unit OPL whether already mapped to Replacement Unit or still not | |
| 7 | Label | Showing 1 to <i>n</i> of <i>n</i> entries | Display the entries generated by search engine | |
| 8 | Link | First Page | To show the first page entry | |
| 9 | Link | Previous Page | To show the previous page entry | |
| 10 | Link | Page Number | To show the page screen according the number | |
| 11 | Link | Next Page | To show the next page entry | |
| 12 | Link | Last Page | To show the last page entry | |
| Foote | Footer | | | |
| 13 | Button | Close | To close pop up windows | |

i. Create BAST Replacement Pop Up Dialog

Here are the screen functions from each component in **Screen 9. Create BAST Replacement Pop Up Dialog**:

| No | Component | Name | Function | | |
|--------|--------------|-----------------------------|---|--|--|
| Head | Header | | | | |
| 1 | Label | Create BAST Replacement | Pop Up Dialog title | | |
| Optio | n | | | | |
| 2 | Radio Button | BAST Replacement Unit | To select if user want create BAST Replacement Unit | | |
| 3 | Radio Button | BAST OPL Unit | To select if user want create BAST OPL Unit | | |
| Footer | | | | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| 4 | Button | Next | To continue process and go to Screen Screen 13. Create BAST Replacement – Replacement Unit or Screen 14. Create BAST Replacement – OPL Unit |
|---|--------|-------|--|
| 5 | Button | Close | To Cancel process and back to <i>Screen</i> 1. Monitoring OPL Unit and Replacement Unit – Replacement Unit |

j. Edit BAST Replacement Pop Up Dialog

Here are the screen functions from each component in **Screen 10. Edit BAST Replacement Pop Up Dialog**:

| No | Component | Name | Function | |
|--------|--------------|-----------------------------|--|--|
| Heade | Header | | | |
| 1 | Label | Edit BAST Replacement | Pop Up Dialog title | |
| Option | n | | | |
| 2 | Radio Button | BAST Replacement Unit | To select if user want edit or submit final BAST Replacement Unit | |
| 3 | Radio Button | BAST OPL Unit | To select if user want edit or submit final BAST OPL Unit | |
| Foote | r | | | |
| 4 | Button | Next | To continue process and go to Screen Screen 15. Edit BAST Replacement – Replacement Unit or Screen 16. Edit BAST Replacement – OPL Unit | |
| 5 | Button | Close | To Cancel process and back to <i>Screen</i> 1. Monitoring OPL Unit and Replacement Unit – Replacement Unit | |

k. View BAST Replacement Pop Up Dialog

Here are the screen functions from each component in **Screen 11**. **View BAST Replacement Pop Up Dialog**:

| No | Component | Name | Function | | |
|-------|--------------|-----------------------------|---|--|--|
| Heade | Header | | | | |
| 1 | Label | View BAST Replacement | Pop Up Dialog title | | |
| Optio | Option | | | | |
| 2 | Radio Button | BAST Replacement Unit | To select if user want view BAST Replacement Unit | | |
| 3 | Radio Button | BAST OPL Unit | To select if user want view BAST OPL Unit | | |
| 4 | Search Box | BAST Number | To continue process and go to Screen Screen 17. View BAST Replacement – Replacement Unit or Screen 18. View | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | | | BAST Replacement – OPL Unit | |
|-------|--------|-------|--|--|
| Foote | Footer | | | |
| 5 | Button | Next | To continue process and display preview of print out BAST Replacement form | |
| 6 | Button | Close | To Cancel process and back to Screen 1. Monitoring OPL Unit and Replacement Unit – Replacement Unit | |

I. Print BAST Replacement Pop Up Dialog

Here are the screen functions from each component in **Screen 12. Print BAST Replacement Pop Up Dialog**:

| No | Component | Name | Function | | |
|-------|--------------|-----------------------------|--|--|--|
| Head | Header | | | | |
| 1 | Label | Print BAST Replacement | Pop Up Dialog title | | |
| Optio | n | | | | |
| 2 | Radio Button | BAST Replacement Unit | To select if user want print BAST Replacement Unit | | |
| 3 | Radio Button | BAST OPL Unit | To select if user want print BAST OPL Unit | | |
| 4 | Search Box | BAST Number | To select BAST Replacement Number to be viewed and go to <i>Screen 19. BAST List Pop Up Dialog</i> | | |
| Foote | r | | | | |
| 5 | Button | Next | To continue process and display preview of print out BAST Replacement form | | |
| 6 | Button | Close | To Cancel process and back to <i>Screen</i> 1. Monitoring OPL Unit and Replacement Unit – Replacement Unit | | |

m. Create BAST Replacement - Replacement Unit

Here are the screen functions from each component in **Screen 13. Create BAST Replacement – Replacement Unit**:

| No | Component | Name | Function | | | |
|------------------|------------|----------------------------|---|--|--|--|
| Header | | | | | | |
| 1 | Label | Create BAST Replacement | Create BAST Replacement title | | | |
| 2 | Button | Back | To cancel process create BAST replacement | | | |
| BAST Information | | | | | | |
| 3 | Text field | BAST No | To display BAST No | | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| 4 | Dropdown | Replacement | To select Replacement Type. Value | | | | | |
|------|-------------------|---------------|---|--|--|--|--|--|
| 7 | Бгораошт | Type | dropdown: | | | | | |
| | | . , , , , | - General Repairment | | | | | |
| | | | - Special Case | | | | | |
| | | | - Insurance | | | | | |
| Base | Base Information | | | | | | | |
| 5 | Text field | Agreement No | To display agreement number | | | | | |
| | | | automatically based on selected | | | | | |
| | | | replacement unit | | | | | |
| 6 | Text field | Company Name | To display customer company name | | | | | |
| | | | number automatically based on selected Agreement Unit | | | | | |
| 7 | Text field | Address | To display Address of customer | | | | | |
| ' | Text field | Addiess | company name automatically based on | | | | | |
| | | | selected Agreement Unit | | | | | |
| 8 | Text field | Telp Number | To input Telp Number of customer | | | | | |
| | | | company name manually based on | | | | | |
| | | | selected Agreement Unit | | | | | |
| 9 | Text field | PIC Customer | To input PIC Customer of customer | | | | | |
| | | | company name manually based on | | | | | |
| | | | selected Agreement Unit | | | | | |
| Repl | Replacement Unit | | | | | | | |
| 10 | Text field | Police Number | To display Police Number of | | | | | |
| | | Replacement | Replacement Unit | | | | | |
| | | Unit | | | | | | |
| 11 | Text field | Merk/ Vehicle | To display Merk/ Vehicle Type of | | | | | |
| 12 | Toyt field | Type | Replacement Unit | | | | | |
| 12 | Text field | Years | To display Years of Replacement Unit | | | | | |
| 13 | Text field | Colour | To display Colour of Replacement Unit | | | | | |
| 14 | Text field | Chassis No | To display Chassis Number of | | | | | |
| 4.5 | T . C . I . | | Replacement Unit | | | | | |
| 15 | Text field | Machine No | To display Machine Number of | | | | | |
| 16 | Text field | STNK Date | Replacement Unit To display STNK Date of Replacement | | | | | |
| 10 | Text field | STINK Date | Unit | | | | | |
| 17 | Text field | KEUR Date | To display KEUR Date of Replacement | | | | | |
| | | | Unit | | | | | |
| 18 | Calendar Picker | Start Date | To select Start Date of usage | | | | | |
| | | | Replacement Unit | | | | | |
| 19 | Calendar Picker | End Date | To select End Date of usage | | | | | |
| | | Estimation | Replacement Unit | | | | | |
| BAST | Γ Out and BAST In | | | | | | | |
| 20 | Tab | BAST Out | To input or display unit component of | | | | | |
| | | | BAST replacement Out (deliver | | | | | |
| | | | replacement unit to customer) | | | | | |
| 21 | Tab | BAST In | To input or display unit component of | | | | | |
| | | | BAST replacement In (receive | | | | | |
| | 0 1 1 5:: | D 1 11 11 2 1 | replacement unit from customer) | | | | | |
| 22 | Calendar Picker | Date Unit Out | To select date Replacement unit Out | | | | | |
| 22 | Calandar Diskar | Data Unit In | from DSF Office (Tab BAST Out) | | | | | |
| 23 | Calendar Picker | Date Unit In | To select date Replacement unit Return | | | | | |
| | | | to DSF Office (Tab BAST In) | | | | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |

| 0.4 | T . C . I . | 1/0.4 | T : |
|--------|--------------|-----------------|--|
| 24 | Text field | KM | To input latest KM of Replacement unit |
| 25 | Dropdown | Fuel | To select fuel. Value of dropdown; E, 1/8, ¼, ½, ¾, F |
| 26 | Text field | Driver Name | To input Driver name |
| 27 | Text field | Observer Name | To input Observer name |
| 28 | Text field | Branch/ Poll | To input Branch/ Poll |
| 29 | Text field | Remark | To input Remark |
| 30 | Text field | Usage Location | To input usage location of Replacement Unit (Tab BAST Out) |
| 31 | Text field | Return Location | To input return location of Replacement Unit (Tab BAST In) |
| Unit C | omponent | | |
| 32 | Label | No | Increment number of row |
| 33 | Label | Component | To input component of unit, such as: Starter/Ignition System, Air Condition, STNK, Radio Tape, Catridge/ Remote R, Antena, Lighter/ Pemantik, Asbak, Seat Cover/ Sarung Jok, etc |
| 34 | Radio Button | Good | To select Condition of Unit |
| 35 | Radio Button | Damage | |
| 36 | Radio Button | Missing | |
| 37 | Radio Button | Not Exist | |
| 38 | Button | Add Item | To add Unit Component |
| 39 | Button | Delete | To delete Unit Component |
| 40 | Text field | Remark | To input Remark for notes body of paint of car |
| 41 | Button | Delete | To delete row unit component |
| Footer | r | | |
| 42 | Button | Save as Draft | To save BAST Replacement as draft |
| 43 | Button | Submit | To Submit replacement unit data due to |
| | Batton | | special case |

n. Create BAST Replacement - OPL Unit

Here are the screen functions from each component in **Screen 14. Create BAST Replacement – OPL Unit**:

See components screen of Screen 13. Create BAST Replacement – Replacement Unit, with modification component as below:

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| No | Component | Name | Function |
|-------|-----------------|---------------------------|---|
| OPL U | Jnit | | |
| 1 | Text field | Police Number OPL Unit | To display Police Number of OPL Unit |
| 2 | Text field | Merk/ Vehicle Type | To display Merk/ Vehicle Type of Replacement Unit |
| 3 | Text field | Years | To display Years of Replacement Unit |
| 4 | Text field | Colour | To display Colour of Replacement Unit |
| 5 | Text field | Chassis No | To display Chassis Number of Replacement Unit |
| 6 | Text field | Machine No | To display Machine Number of Replacement Unit |
| 7 | Text field | STNK Date | To display STNK Date of OPL Unit |
| 8 | Text field | KEUR Date | To display KEUR Date of OPL Unit |
| 9 | Calendar Picker | Start Date | To select Start Date of repairment OPL Unit |
| 10 | Calendar Picker | End Date Estimation | To select End Date of OPL Unit repairment |
| BAST | Out and BAST In | | |
| 11 | Tab | BAST Out | To input or display unit component of BAST replacement Out (deliver OPL unit to workshop) |
| 12 | Tab | BAST In | To input or display unit component of BAST replacement In (return OPL unit to customer) |
| 13 | Calendar Picker | Date Unit Out | To select date OPL unit Out from Customer Office (Tab BAST Out) |
| 14 | Calendar Picker | Date Unit In | To select date OPL unit return to Customer Office (Tab BAST In) |
| 15 | Text field | Damage Location | To input Damage location of OPL Unit (Tab BAST Out) |
| 16 | Text field | Return Location | To input return location of OPL Unit (Tab BAST In) |
| 17 | Text field | KM | To input latest KM of OPL unit |
| 18 | Dropdown | Fuel | To select fuel. Value of dropdown; E, 1/8, ¼, ½, ¾, F |
| 19 | Text field | Driver Name | To input Driver name |
| 20 | Text field | Observer Name | To input Observer name |
| 21 | Text field | Branch/ Poll | To input Branch/ Poll |
| 22 | Text field | Remark | To input Remark |

Then there are several component that will not available:

| Foote | r | | |
|-------|--------|--------|--|
| 1 | Button | Submit | To re-submit replacement unit data due |
| | | | to special case |

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |

| 2 | Button | Print Memo | To re-print Memo due to special case |
|---|--------|------------|--------------------------------------|
| | | | |

o. Edit BAST Replacement - Replacement Unit

Here are the screen functions from each component in **Screen 15**. **Edit BAST Replacement – Replacement Unit**:

See components screen of Screen 13. Create BAST Replacement – Replacement Unit, with additional and modification component as below:

| No | Component | Name | Function | | |
|-------|-------------|--------------------------|--|--|--|
| Heade | Header | | | | |
| 1 | Label | Edit BAST Replacement | Edit BAST Replacement title | | |
| BAST | Information | | | | |
| 2 | Search Box | BAST No | To select BAST Number that will be edited | | |
| 3 | Text field | Replacement Type | To display selected Replacement Type. Value: - General Repairment - Special Case - Insurance | | |
| Foote | r | | | | |
| 4 | Button | Save as Change | To save changes or update BAST Replacement | | |
| 5 | Button | Submit | To re-submit replacement unit data due to special case | | |
| 6 | Button | Print Memo | To print Memo due to special case | | |
| 7 | Button | Save as Final | To firm BAST Replacement | | |

p. Edit BAST Replacement - OPL Unit

Here are the screen functions from each component in **Screen 16. Edit BAST Replacement – OPL Unit**:

See components screen of Screen 13. *Create BAST Replacement – OPL Unit*, with additional and modification component as below:

| No | Component | Name | Function | | | |
|------|------------------|--------------------------|--|--|--|--|
| Head | Header | | | | | |
| 1 | Label | Edit BAST Replacement | Edit BAST Replacement title | | | |
| BAST | BAST Information | | | | | |
| 2 | Search Box | BAST No | To select BAST Number that will be edited | | | |
| 3 | Text field | Replacement Type | To display selected Replacement Type. Value: General Repairment Special Case Insurance | | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |

| Footer | | | |
|--------|--------|----------------|---|
| 4 | Button | Save as Change | To save changes or update BAST Replacement |
| 5 | Button | Save as Final | To firm BAST Replacement |

Then there are several component that will not available:

| Footer | | | |
|--------|--------|------------|--|
| 1 | Button | Submit | To re-submit replacement unit data due to special case |
| 2 | Button | Print Memo | To re-print Memo due to special case |

q. View BAST Replacement - Replacement Unit

Here are the screen functions from each component in **Screen 17**. **View BAST Replacement – Replacement Unit**:

See components screen of Screen 13. *Create BAST Replacement – Replacement Unit*, all component will be Not Active and there are some modification as below:

| No | Component | Name | Function | |
|-------|-----------|--------------------------|-----------------------------|--|
| Heade | er | | | |
| 1 | Label | View BAST Replacement | View BAST Replacement title | |

Then there are several component that will not available:

| Foote | r | | |
|-------|--------|---------------|--|
| 1 | Button | Save as Draft | To save draft of BAST Replacement |
| 2 | Button | Submit | To re-submit replacement unit data due to special case |
| 3 | Button | Print Memo | To re-print Memo due to special case |

r. View BAST Replacement - OPL Unit

Here are the screen functions from each component in **Screen 18. View BAST Replacement – OPL Unit**:

See components screen of Screen 13. *Create BAST Replacement – OPL Unit*, all component will be Not Active and there are some modification as below:

| No | Component | Name | Function | |
|-------|-----------|--------------------------|-----------------------------|--|
| Heade | er | | | |
| 1 | Label | View BAST Replacement | View BAST Replacement title | |

Then there are several component that will not available:

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |

| Foote | r | | |
|-------|--------|---------------|--|
| 1 | Button | Save as Draft | To save draft of BAST Replacement |
| 2 | Button | Submit | To re-submit replacement unit data due to special case |
| 3 | Button | Print Memo | To print Memo due to special case |

s. BAST List Pop Up Dialog

Here are the screen functions from each component in **Screen 19. BAST List Pop Up Dialog**:

| No | Component | Name | Function | | | |
|--------|------------|--------------|--|--|--|--|
| Header | | | | | | |
| 1 | Label | BAST List | BAST List title | | | |
| 2 | Dropdown | Show Entries | To select number of row data that will be displayed in one screen (paging) | | | |
| 3 | Text field | Search | To search BAST Number based on input criteria | | | |
| List | | | | | | |
| 4 | Label | BAST No | To display list of BAST Number | | | |
| 5 | Label | Created Date | To display list of created date BAST Replacement Unit | | | |
| Foote | r | | | | | |
| 6 | Button | Close | To close pop up windows | | | |

3.7 Operation Description

| No. | Operation Name | Des | Description | | | | | |
|-----|----------------------|-----|---|---------------------------|--------|--|--|--|
| 1 | Initial view of List | The | The screen for list of Monitoring OPL Unit and Replacement Unit – | | | | | |
| | Monitoring OPL Unit | Rep | Replacement Unit tab: | | | | | |
| | and Replacement | | | | | | | |
| | Unit – Replacement | 1. | Component St | tatus; | | | | |
| | Unit tab | | Component | Name/Caption | Status | | | |
| | | | Label | Monitoring OPL Unit and | Active | | | |
| | | | | Replacement unit | | | | |
| | | | Drop down | Search Criteria | Active | | | |
| | | | box | | | | | |
| | | | Text field | Parameter | Active | | | |
| | | | Date Picker | Start Modified Date | Active | | | |
| | | | Date Picker | End Modified Date Period | Active | | | |
| | | | Button | Search | Active | | | |
| | | | Tab | Monitoring OPL Unit and | Active | | | |
| | | | | Replacement Unit – | | | | |
| | | | | Replacement Unit | | | | |
| | | | Button | Register Replacement Unit | Active | | | |
| | | | Button | Approval Replacement | Active | | | |
| | | | Label | DSF Office | Active | | | |
| | | | Label | Registration Number | Active | | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | | | Label | Replacement Unit | Police No | Active | |
|---|-----------------|----|---------------------------|------------------------------|-----------------|--|--|
| | | | Label | Model Unit | | Active | |
| | | | Label | Agreement No | | Active | |
| | | | Label | OPL Unit Police No | | Active | |
| | | | Label | Customer Name | | | |
| | | | | | | Active | |
| | | | Label | Active/ Not Active | - 4 - 1 1 - 1 4 | Active | |
| | | | Label | Status Replacemer | | Active | |
| | | | Label | Location of Replace | ing Unit | Active | |
| | | | Label | Replacing | | Active | |
| | | | Label | Replacement Type | | Active | |
| | | | Label | Usage Period – Sta | | Active | |
| | | | Label | Usage Period – Est | imation | Active | |
| | | | Label | Usage Period – End | d Date | Active | |
| | | | Label | Create By (BAST) | | Active | |
| | | | Label | Create Date (BAST | _) | Active | |
| | | | Label | Last Modified By (E | BAST) | Active | |
| | | | Label | Last Modified Date | (BAST) | Active | |
| | | | Button | Action – Create BA | | Active | |
| | | | Button | Action – Edit BAST | | Active | |
| | | | Button | Action – View BAS | | Active | |
| | | | Button | Action – Print BAS | | Active | |
| | | | Button | Action – View Histo | | Active | |
| | | | Link | Showing 1 to <i>n</i> of | | Active | |
| | | | Link | First Page | II entries | Active | |
| | | | Link | | | Active | |
| | | | | Previous Page | | | |
| | | | Link | Page Number | | Active | |
| | | | Link | Next Page | | Active | |
| | | | Link | Last Page | | Active | |
| | | | Button | Print Report | | Active | |
| 2 | Initial view of | | | gister Unit Replacem | <u>nent</u> : | | |
| | Register Unit | 1. | Component St | | T | 1 | |
| | Replacement | | Component | Name/Caption | Status | Remark | |
| | | | Label | Register Unit Replacement | Active | | |
| | | | Dropdown | Action | Active | Value dropdown; 1. Add 2. Update Default value is Add | |
| | | | Text field/ Search Box | Registration Number | Active | 1. If user click Action 'Add' then Registration Number will be Text field 2. If user click Action 'Update' then Registration Number will be Search Box | |
| | | | Radio Button | Status - Active | Active | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | | | Radio | Status – Not | Active | | |
|---|---------------------|-----|--------------------|-----------------------------------|---------------|---------------|---|
| | | | Button | Active | 1.5.1.0 | | |
| | | | Text field | DSF Office | Active | | 1 |
| | | | Text field | Source Location | Active | | |
| | | | | (City) | | | |
| | | | Search box | Police Number | Active | | |
| | | | Search Box | Model | Active | | |
| | | | | Replacement Unit | | | |
| | | | Text field | Machine Number | Active | | |
| | | | Text field | Chassis Number | Active | | |
| | | | Calendar Picker | STNK Start Date | Active | | |
| | | | Calendar Picker | STNK End Date | Active | | |
| | | | Calendar Picker | KEUR Start Date | Active | | - |
| | | | Calendar Picker | KEUR End Date | Active | | - |
| | | | Text field | Insurance Company | Active | | |
| | | | Text field | Insurance Policy Number | Active | | - |
| | | | Calendar | Insurance Start | Active | | 1 |
| | | | Picker | Date | | | |
| | | | Calendar | Insurance End | Active | | 1 |
| | | | Picker | Date | | | |
| | | | Search Box | Agreement Number | Active | | |
| | | | Text field | Customer Name | Active | Automatically | 1 |
| | | | Search Box | Model OPL Unit | Active | Automatically | |
| | | | Text field | Police Number OPL Unit | Active | | |
| | | | Button | Save | Active | | 1 |
| | | | Button | Cancel | Active | | 1 |
| 3 | Initial view of | The | -1 | gistration Number Lis | | • | |
| | Registration Number | | Component S | ~ | : | | |
| | List | | Component | Name/Caption | | Status | 1 |
| | | | Label | Registration Number | er | Active | 1 |
| | | | Dropdown | Show Entries | | Active |] |
| | | | Text field | Search | | Active |] |
| | | | Label | Registration No | | Active |] |
| | | | Label | Replacement Unit F | Police No | Active |] |
| | | | Label | Model Unit | | Active |] |
| | | | Label | OPL Unit Police No | | Active | |
| | | | Label | Agreement No | | Active | |
| | | | Label | Showing 1 to <i>n</i> of <i>i</i> | n entries | Active |] |
| | | | Link | First Page | | Active | 1 |
| | | | Link | Previous Page | | Active | 1 |
| | | | Link | Page Number | | Active | 1 |
| | i | | Link | Next Page | | Active | 1 |
| | | | | | | 7.01.70 | 1 |
| | | | | | | Active | |
| | | | Link Button | Last Page Close | | Active Active | - |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | Initial view of DSF | The | screen for DS | F Office List: | |
|---|-----------------------|----------------------|---------------|---|------------|
| | Office List | 1. Component Status; | | | |
| | 000 2.01 | | Component | | Status |
| | | | Label | DSF Office List | Active |
| | | | Dropdown | Show Entries | Active |
| | | | Text field | Search | Active |
| | | | Label | Office Short Name | Active |
| | | | Label | Office Name | Active |
| | | | Label | Showing 1 to <i>n</i> of <i>n</i> entries | Active |
| | | | Link | First Page | Active |
| | | | Link | Previous Page | Active |
| | | | Link | Page Number | Active |
| | | | Link | Next Page | Active |
| | | | Link | Last Page | Active |
| | | | Button | Close | Active |
| | | | | • | |
| 4 | Initial view of | | | <u>placement Unit Police Number Li</u> | <u>st:</u> |
| | Replacement Unit | 1. | Component St | | |
| | Police Number List | | Component | • | Status |
| | | | Label | Replacement Unit Police | Active |
| | | | | Number List | |
| | | | Dropdown | Show Entries | Active |
| | | | Text field | Search | Active |
| | | | Label | Police Number | Active |
| | | | Label | Created Date | Active |
| | | | Label | Showing 1 to <i>n</i> of <i>n</i> entries | Active |
| | | | Link | First Page | Active |
| | | | Link | Previous Page | Active |
| | | | Link | Page Number | Active |
| | | | Link | Next Page | Active |
| | | | Link | Last Page | Active |
| 5 | Initial view of Model | | | odel Name List List: | |
| | Name List | 1. | Component St | | |
| | | | Component | • | Status |
| | | | Label | Model Name List | Active |
| | | | Dropdown | Show Entries | Active |
| | | | Text field | Search | Active |
| | | | Label | Brand Name | Active |
| | | | Label | Model Name | Active |
| | | | Label | Showing 1 to <i>n</i> of <i>n</i> entries | Active |
| | | | Link | First Page | Active |
| | | | Link | Previous Page | Active |
| | | | Link | Page Number | Active |
| | | | Link | Next Page | Active |
| | | | Link | Last Page | Active |
| | | | Button | Close | Active |
| 6 | Initial view of | | _ | reement Number List: | |
| | Agreement Number | 2. | Component S | | |
| | List | | Component | Name/Caption | Status |
| | | | Label | Agreement Number List | Active |
| | | | Dropdown | Show Entries | Active |
| | | | Text field | Search | Active |
| | | | Label | Agreement Number | Active |
| | | | Label | Customer Name | Active |
| | | | Label | Showing 1 to <i>n</i> of <i>n</i> entries | Active |
| | | <u> </u> | | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | | | Link | First Page | | Active | |
|---|------------------------|-----|-----------------|--|------------|------------------|--|
| | | | Link | Previous Page | | Active | |
| | | | Link | | | | |
| | | | | Page Number | | Active | |
| | | | Link | Next Page | | Active | |
| | | | Link | Last Page | | Active | |
| | | | Button | Close | | Active | |
| 7 | Initial view of Police | The | screen for OP | L Police Number List: | | | |
| , | Number List | 1. | Component S | · | | | |
| | | | Component | | | Status | |
| | | | Label | OPL Police Number L | ist | Active | |
| | | | Dropdown | Show Entries | -131 | Active | |
| | | | Text field | Search | | Active | |
| | | | Radio | Select Police No | | | |
| | | | | Select Police No | | Active | |
| | | | Button | Dollar No. | | A ative | |
| | | | Label | Police No | | Active | |
| | | | Label | Status | | Active; 2 values | |
| | | | | | | that will be | |
| | | | | | | display are | |
| | | | | | | Registered, | |
| | | | | | | Available | |
| | | | Label | Showing 1 to <i>n</i> of <i>n</i> | entries | Active | |
| | | | Link | First Page | | Active | |
| | | | Link | Previous Page | | Active | |
| | | | Link | Page Number | | Active | |
| | | | Link | Next Page | | Active | |
| | | | Link | Last Page | | Active | |
| | | | Button | Close | | Active | |
| 8 | Initial view of Create | 1 | The core of for | n Create DACT Denless | amount Dan | locomount Unit. | |
| 0 | BAST Replacement | 1. | | r <u>Create BAST Replace</u> tatus Replacement Un | • | iacement onit. | |
| | | | Component | Name/Caption | Status | Remark | |
| | | | Label | Create BAST Replacement | Active | | |
| | | | Button | Back | Active | | |
| | | | Text field | BAST No | Active | Automatically | |
| | | | Dropdown | Replacement Type | Active | | |
| | | | Text field | Agreement No | Active | Automatically | |
| | | | Text field | Company Name | Active | Automatically | |
| | | | Text field | Address | Active | Automatically | |
| | | | Text field | Telp Number | Active | . istomationity | |
| | | | Text field | PIC Customer | Active | | |
| | | | Text field | Police Number | Active | Automatically | |
| | | | TOAT HEID | Replacement Unit | ACTIVE | Automatically | |
| | | | Text field | Merk/ Vehicle Type | Active | Automatically | |
| | | | Text field | Years | Active | Automatically | |
| | | | Text field | Colour | Active | Automatically | |
| | | | Text field | Chassis No | Active | Automatically | |
| | | | Text field | Machine No | Active | Automatically | |
| | | | Text field | STNK Date | Active | Automatically | |
| | | | TENTHEIR | DINK Date | ACTIVE | Automatically | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | | 1 | 1 |
|--------------------|-----------------|------------|--|
| Text field | KEUR Date | Active | Automatically |
| Calendar | Start Date | Active | |
| Picker | | | |
| Calendar | End Date | Active | |
| Picker | Estimation | | |
| Tab | BAST Out | Active | 1. By default system will display input data for BAST Out |
| | | | 2. BAST Out fields will be Not Active if BASTOutStatus = 30 (Firmed) |
| Tab | BAST In | Not Active | Will be active after BASTOutStatus = 30 (Firmed) |
| Calendar Picker | Date Unit Out | Active | , , , , , , , , |
| Text field | Usage Location | Active | |
| Text field | Return Location | Active | |
| Text field | KM | Active | |
| Dropdown | Fuel | Active | |
| Text field | Driver Name | Active | |
| Text field | Observer Name | Active | |
| Text field | Branch/ Poll | Active | |
| Text field | Remark | Active | |
| Label | No | Active | |
| Label | Component | Active | |
| Radio Button | Good | Active | |
| Radio Button | Damage | Active | |
| Radio Button | Missing | Active | |
| Radio Button | Not Exist | Active | |
| Button | Add Item | Active | |
| Button | Delete | Active | |
| Text field | Remark | Active | |
| Button | Save as Draft | Active | Will not active if user select Replacement type: Special Case |
| Button | Print Memo | Not Active | Will be active only if user select Replacement type: Special Case |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| Button | Submit | Not Active | Will be active |
|--------|--------|------------|----------------|
| | | | only if user |
| | | | select |
| | | | Replacement |
| | | | type: Special |
| | | | Case |

2. The screen for <u>Create BAST Replacement – OPL Unit</u>: Component Status Replacement Unit;

| Component | Namo/Cantion | Status | Domark |
|----------------------|--------------------------------|------------------|--|
| Component Text field | Name/Caption Police Number OPL | Status Active | Remark |
| Text field | Unit Unit | Active | Automatically |
| Text field | Merk/ Vehicle Type | Active | Automatically |
| Text field | Years | Active | Automatically |
| Text field | Colour | Active | Automatically |
| Text field | Chassis No | Active | Automatically |
| Text field | Machine No | Active | Automatically |
| Text field | STNK Date | Active | Automatically |
| Text field | KEUR Date | Active | Automatically |
| Calendar | Start Date | Active | |
| Picker | | | |
| Calendar | End Date | Active | |
| Picker | Estimation | | |
| Tab | BAST Out | Active | 1. By default system will display input data for BAST Out 2. BAST Out fields will be Not Active if BASTOutStatus = 30 (Firmed) |
| Tab | BAST In | Not Active | Will be active after BASTOutStatus = 30 (Firmed) |
| Calendar Picker | Date Unit Out | Active | , , |
| Calendar Picker | Date Unit In | Active | |
| Text field | Damage Location | Active | |
| Text field | Return Location | Active | |
| Text field | KM | Active | |
| Dropdown | Fuel | Active | |
| Text field | Driver Name | Active | |
| Text field | Observer Name | Active | |
| Text field | Branch/ Poll | Active | |
| Text field | Remark | Active | |
| Label | No | Active | |
| Label | Component | Active | |
| Radio Button | Good | Active | |
| Radio | Damage | Active | |
| Naulu | Damage | ACTIVE | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | | | Rutton | | | |
|---|----------------------|----|--------------------|---------------------|-----------|--|
| | | | Button Radio | Missing | Active | |
| | | | Button | wiissiriy | ACTIVE | |
| | | | Radio | Not Exist | Active | |
| | | | Button | NOT EXIST | Active | |
| | | | Button | Add Item | Active | |
| | | | Button | Delete | Active | |
| | | | Text field | Remark | Active | |
| | | | Button | Save as Draft | Active | |
| 9 | Initial view of Edit | 1. | | Edit BAST Replaceme | | rement Unit: |
| , | BAST Replacement | | Component St | | эн төргас | |
| | | | Component | Name/Caption | Status | Remark |
| | | | Label | Edit BAST | Active | |
| | | | Label | Replacement | | |
| | | | Button | Back | Active | |
| | | | Text field | BAST No | Active | |
| | | | Dropdown | Replacement Type | Active | Automatically |
| | | | Text field | Agreement No | Active | Automatically |
| | | | Text field | Company Name | Active | Automatically |
| | | | Text field | Address | Active | Automatically |
| | | | Text field | Telp Number | Active | |
| | | | Text field | PIC Customer | Active | |
| | | | Text field | Police Number | Active | Automatically |
| | | | Text field | Merk/ Vehicle Type | Active | Automatically |
| | | | Text field | Years | Active | Automatically |
| | | | Text field | Colour | Active | Automatically |
| | | | Text field | Chassis No | Active | Automatically |
| | | | Text field | Machine No | Active | Automatically |
| | | | Text field | STNK Date | Active | Automatically |
| | | | Text field | KEUR Date | Active | Automatically |
| | | | Calendar Picker | Start Date | Active | |
| | | | Calendar | End Date | Active | |
| | | | Picker | Estimation | | <u> </u> |
| | | | Tab | BAST Out | Active | 1. BAST Out fields will be Not Active if BASTOutStatus = 30 (Firmed) |
| | | | Tab | BAST In | Active | Will be active after BASTOutStatus = 30 (Firmed) |
| | | | Calendar Picker | Date Unit Out | Active | |
| | | | Calendar Picker | Date Unit In | Active | |
| | | | Text field | Usage Location | Active | |
| | | | Text field | Return Location | Active | |
| | | | Text field | KM | Active | |
| | | | Dropdown | Fuel | Active | |
| | | | Text field | Driver Name | Active | |
| | | | Text field | Observer Name | Active | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| Text field | Branch/ Poll | Active | |
|------------|---------------|------------|--------------------|
| Text field | Remark | Active | |
| Label | No | Active | |
| Label | Component | Active | |
| Radio | Good | Active | |
| Button | | | |
| Radio | Damage | Active | |
| Button | | | |
| Radio | Missing | Active | |
| Button | | | |
| Radio | Not Exist | Active | |
| Button | | | |
| Button | Add Item | Active | |
| Button | Delete | Active | |
| Text field | Remark | Active | |
| Button | Save Change | Active | |
| Button | Submit | Not Active | Will not active if |
| | | | user select |
| | | | Replacement |
| | | | type: Special |
| | | | Case |
| | | | |
| Button | Print Memo | Not Active | Will not active if |
| | | | user select |
| | | | Replacement |
| | | | type: Special |
| | | | Case |
| Dutton | Cove on Final | Antivo | |
| Button | Save as Final | Active | |

2. The screen for <u>Edit BAST Replacement – OPL Unit</u>: Component Status;

| Component | Name/Caption | Status | Remark |
|------------|--------------------|--------|---------------|
| Labal | Edit BAST | Active | |
| Label | Replacement | | |
| Button | Back | Active | |
| Text field | BAST No | Active | |
| Dropdown | Replacement Type | Active | Automatically |
| Text field | Agreement No | Active | Automatically |
| Text field | Company Name | Active | Automatically |
| Text field | Address | Active | Automatically |
| Text field | Telp Number | Active | |
| Text field | PIC Customer | Active | |
| Text field | Police Number | Active | Automatically |
| Text field | Merk/ Vehicle Type | Active | Automatically |
| Text field | Years | Active | Automatically |
| Text field | Colour | Active | Automatically |
| Text field | Chassis No | Active | Automatically |
| Text field | Machine No | Active | Automatically |
| Text field | STNK Date | Active | Automatically |
| Text field | KEUR Date | Active | Automatically |
| Calendar | Start Date | Active | |
| Picker | | | |
| Calendar | End Date | Active | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | | Picker | Estimation | | |
|----|--|--------------------------------------|-----------------------------------|-----------------------|--|
| | | Tab | BAST Out | Active | 1. BAST Out fields will be Not Active if BASTOutStatus = 30 (Firmed) |
| | | Tab | BAST In | Active | Will be active after BASTOutStatus = 30 (Firmed) |
| | | Calendar Picker | Date Unit Out | Active | |
| | | Calendar Picker | Date Unit In | Active | |
| | | Text field | Damage Location | Active | |
| | | Text field | Return Location | Active | |
| | | Text field | KM | Active | |
| | | Dropdown | Fuel | Active | |
| | | Text field | Driver Name | Active | |
| | | Text field | Observer Name | Active | |
| | | Text field | Branch/ Poll | Active | |
| | | Text field | Remark | Active | |
| | | Label | No | Active | |
| | | Label | Component | Active | |
| | | Radio Button | Good | Active | |
| | | Radio Button | Damage | Active | |
| | | Radio Button | Missing | Active | |
| | | Radio Button | Not Exist | Active | |
| | | Button | Add Item | Active | |
| | | Button | Delete | Active | |
| | | Text field | Remark | Active | |
| | | Button | Save Change | Active | |
| | | Button | Save as Final | Active | |
| | | Datton | 1 34 10 43 1 11141 | 1,101100 | |
| 10 | Initial view of View BAST Replacement | The screen for Vie 1. Component S | ew BAST Replacement status; | – Replaceme | ent Unit and OPL Unit: |
| | | Component | Name/Caption | Status | Remark |
| | | Label | View BAST | Active | Remark |
| | | Button | Replacement | Active | |
| | | Text field | Back BAST No | Active | |
| | | | | | automatically |
| | | Dropdown Toxt field | Replacement Type | Not Active | automatically |
| | | Text field | Agreement No | Not Active | Automatically |
| | | Text field | Company Name | Not Active | Automatically |
| | | Text field | Address | Not Active | Automatically |
| | | Text field | Telp Number | Not Active | Automatically |
| | | Text field | PIC Customer | Not Active | Automatically |
| | | Text field Text field | Police Number Merk/ Vehicle Type | Not Active Not Active | Automatically Automatically |
| | | I LEXI HEID | I MEIK VEDICIE IVDE | I MOLACIIVA | LAUDOHAUCAUV |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | | | Text field | Years | Not Active | Automatically | | |
|----|------------------|--|--|-------------------------|----------------|--------------------|-------|--|
| | | | Text field | Colour | Not Active | Automatically | | |
| | | | Text field | Chassis No | Not Active | Automatically | | |
| | | | Text field | Machine No | Not Active | Automatically | | |
| | | | Text field | STNK Date | Not Active | Automatically | | |
| | | | Text field | KEUR Date | Not Active | Automatically | | |
| | | | Calendar | Start Date | Not Active | Automatically | | |
| | | | Picker | | | | | |
| | | | Calendar | End Date | Not Active | Automatically | | |
| | | | Picker | Estimation | | J | | |
| | | | Tab | BAST Out | Active | Automatically | | |
| | | | Tab | BAST In | Active | Automatically | | |
| | | | Calendar | Date Unit Out | Not Active | Automatically | | |
| | | | Picker | | | | | |
| | | | Text field | Usage Location/ | Active | Automatically | | |
| | | | | Damage Location | | | | |
| | | | Text field | Return Location | Active | Automatically | | |
| | | | Text field | KM | Not Active | Automatically | | |
| | | | Dropdown | Fuel | Not Active | Automatically | | |
| | | | Text field | Driver Name | Not Active | Automatically | | |
| | | | Text field | Observer Name | Not Active | Automatically | | |
| | | | Text field | Branch/ Poll | Not Active | Automatically | | |
| | | | Text field | Remark | Not Active | Automatically | | |
| | | | Label | No | Not Active | Automatically | | |
| | | | Label | Component | Not Active | Automatically | | |
| | | | Radio | Good | Not Active | Automatically | | |
| | | | Button | | | | | |
| | | | Radio | Damage | Not Active | | | |
| | | | Button | | | | | |
| | | | Radio | Missing | Not Active | | | |
| | | | Button | | | | | |
| | | | Radio | Not Exist | Not Active | | | |
| | | | Button | | | | | |
| | | | Text field | Remark | Not Active | Automatically | | |
| | | | | | | | | |
| | | | | | | | | |
| 11 | Register | Inpu | | | | | | |
| | Replacement Unit | | Access OLSS | \ | | | | |
| | | | Select menu I | · · | DI and linit D | onlocoment | | |
| | | | | enu Monitoring Unit O | | | Unit | |
| | | | | Register Replacement | | en 1. Wormonng OPL | Ullit | |
| | | | • | nent Unit – Replaceme | ent Onit | | | |
| | | 5. Click Dropdown Action; Add | | | | | | |
| | | 6. Select Status; Active or Not Active7. Select DSF Office of Replacement Car | | | | | | |
| | | | | Location (City) of Rep | | t | | |
| | | | | | | | | |
| | | | Select or Input Police Number of Replacement Unit Select Model Unit of Replacement Unit | | | | | |
| | | | Double cli | ck on selected Agreer | nent No list | | | |
| | | | | riteria searching on se | | | | |
| | | | | Number of Replacen | | | | |
| | | | 12. Input Chassis Number of Replacement Unit 13. Input Colour of Replacement Unit 14. Soloct STNK Start Date and STNK End Date | | | | | |
| | | | | | | | | |
| | | | 14. Select STNK Start Date and STNK End Date15. Select KEUR Start Date and KEUR End Date (Optional/Not Mandatory) | | | | | |
| | | | 16. Input Insurance Company | | | | | |
| | | | 17. Input Insurance Policy Number | | | | | |
| | - | • | • | • | | | | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

- 18. Select Insurance Start Date and End Date
- 19. Select Agreement Number
 - Double click on selected Agreement No list
 - Or input criteria searching on search box
- 20. Select Police Number of OPL Unit
- 21. Click button save
- 22. Click button Close (X)

Constraint:

- For all input data cannot more than length on data structure
- For input date, End Date cannot less than Start Date

Process:

- When user click button Register Replacement Unit, system will display Screen 2. Register Unit Replacement Pop Up Dialog
- If user click dropdown Add, then: Registration Number will be Text Field and by default is blank (will be set when button save clicked)



- When user select DSF Office of Replacement Car, then system will display Screen 4. DSF Office List.
 - 3.1 By default system will display DSF Office list based on data stored on Tb_OPL_Branch. Data that will be displayed are; Branch Short Name (Tb_OPL_Branch.BranchCode) and Branch Name (Tb_OPL_Branch.BranchName)
 - 3.2 If user input criteria searching on search box, then system will filter DSF Office based on input criteria searching
 - 3.3 When user double click on selected row, then display screen will back to Screen 2. Register Unit Replacement Pop Up Dialog
- 4. Agreement Number search box disable until user Input information related to RPC Unit (Starts from Model Name upto information Insurance)
- 5. When user select Police number of Replacement Unit, then system will display information of Police number Replacement Unit that already registered at Tb_OPL_Unit.PoliceNo where Tb_OPL_Unit.IsOPL = 0, If Replacement Unit not registered yet, then user can input Police number of Replacement Unit. But if Replacement Unit already registered then user can select Replacement Unit and on Screen 2. Register Unit Replacement, field Model Unit, Machine Number, Chassis Number, Colour, STNK Start and End Date, KEUR Start and End Date will be input automatically.
- When user select Model of Replacement Unit using search box, then system will display Screen 5. Model Name list Pop Up Dialog.
 - 6.1 By default system will display all Brand Name (Product.BrandName) and Model Name (Product.ModelName) that already register to system with number of row list based on selected show entries number
 - 6.2 If user input criteria searching on search box, then system will filter Brand Name based on input criteria searching
 - 6.3 When user double click on selected row, then display screen will back to Screen 2. Register Unit Replacement Pop Up Dialog
- 7. When user select Model of OPL Unit using search box, then system will

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| display Screen | 5 | Model | Namo | lict | Don | Hn | Dialog | |
|-----------------------|---|-------|------|------|-----|----|--------|--|
| | | | | | | | | |

- 7.1 By default system will display all Brand Name (Product.BrandName) and Model Name (Product.ModelName) that already register to system with number of row list based on selected show entries number
- 7.2 If user input criteria searching on search box, then system will filter Brand Name based on input criteria searching
- 7.3 When user double click on selected row, then display screen will back to **Screen 2. Register Unit Replacement Pop Up Dialog**
- 8. When user select Start Date and End Date of STNK and KEUR of Replacement Unit, system will display format date in: MM/dd/yyyy (MM: month, dd: day, yyyy: year)
- When user select Agreement Number using search box, then system will display Screen 6. Agreement Number List Pop Up Dialog.
 - 9.1 By default system will display all Agreement No (OPLAgreement.AgreementNumber) and Customer Name (Customer.CustomerName, Where OPLAgreement.CustomerCode = Customer.CustomerCode) that already register to system with number of row list based on selected show entries number
 - 9.2 System will only display Agreement Number where its status = 18 (Note: Open) Tb_OPL_OPLAgreement.Status = 18
 - 9.3 If user input criteria searching on search box, then system will filter agreement number based on input criteria searching
 - 9.4 When user double click on selected row, then display screen will back to Screen 2. Register Unit Replacement Pop Up Dialog
 - 9.5 System will display Customer Name (Customer.CustomerName, Where *OPLAgreement.CustomerCode* = Customer.CustomerCode) based on selected Agreement Number automatically
- 10. When user select Police Number using search box, then system will display Screen 7. OPL Police Number List.
 - 10.1 By default system will display all Police Number OPL Unit that already register to system (Unit.PoliceNumber, where Unit.IdAgreement = OPLAgreement.IdOPLAgreement) with number of row list based on selected show entries number. System will only display Unit.PoliceNumber based on selected Agreement Number on previous point.
 - 10.2 System will display Status availability of Police number OPL unit with formula as below:
 - Check whether Police number OPL Unit (Tb_OPL_Unit.PoliceNo)
 already mapped with inputed Police number Replacement Unit on
 Text field Screen 2 Register Unit Replacement Pop Up Dialog on
 Table Tb_MGT_RegRPC (IdRPCUnit, IdOPL Unit, where
 Tb_OPL_Unit.IdProduct = IdRPCUnit AND Tb_OPL_Unit.IdProduct
 = IdOPLUnit)
 - If already registered then Status availability of Police Number OPL unit will be "Registered"
 - If not registered yet then Status availability of Police Number OPL unit will be "Available"
 - 10.3 If user input criteria searching on search box, then system will filter Police number based on input criteria searching
 - 10.4 When user double click on selected row, then display screen will back to Screen 2. Register Unit Replacement Pop Up Dialog
- 11. When user click button Save, system will display window confirmation: Screen 19. Confirmation Pop Up When Register Replacement Unit
- 12. If user click button Yes on window confirmation, then system will:
 - 12.1 Generate Registration Number of Replacement Unit, with below format: 00001/RPU/JKT/11/2015
 - Segment 1: 5 digit running number (get from table configuration field identifier 1, where document = Registration Replacement Car)
 - Segment 2: Identifier of document (RPU= Registration Replacement Car)

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| Segment 3: Branch Short Name Segment 15: Month Registration actual date (get from TB_MGT_RegRPC.RegDate (YYYY-MM-DD), MM digit) Segment 5: Year Registration actual date get from TB_MGT_RegRPC.RegDate (YYYY-MM-DD), YYYY digit) 12.2 Check whether Police Number of Replacement Unit that already input by user already exist at Tb_OPL_Unit.PoliceNo. if No then Replacement Unit tibe registered to Tb_OPL_Unit with stored data are: • DSF-Office 3* Tb_OPL_Unit. IdBranch, | |
|---|--|
| input by user already exist at Tb_OPL_Unit. PoliceNo. if No then Replacement Unit will be registered to Tb_OPL_Unit. Stored data into table Tb_OPL_Unit, with stored data are: • DSF Office → Tb_OPL_Unit. Idians, with stored data are: • DSF Office → Tb_OPL_Unit. Idians, with stored data are: • Model Replacement Unit → Tb_OPL_Unit. Idiproduct, Check Product. IdiProduct of Selected Model Replacement Unit • Police Number of Replacement Unit → Tb_OPL_Unit. PoliceNo = Input Police Number • Machine No → Tb_OPL_Unit. ChassisNo = Input Colour = Input Exact Date STNK • End Date STNK → Tb_OPL_Unit. StartSTNK = Input End Date STNK • End Date STNK → Tb_OPL_Unit. StartKEUR = Input Start Date KEUR → Tb_OPL_Unit. StartKEUR = Input End Date KEUR • End Date KEUR → Tb_OPL_Unit. StartIns = input Start Date KEUR • Start Date Insurance → Tb_OPL_Unit. StartIns = input Start Date Insurance Policy • End Date Insurance → Tb_OPL_Unit. CompanyInsurance = Input Company Insurance → Tb_OPL_Unit. InsuranceNumber = Insurance Number → Tb_OPL_Unit. Server (IdRPCUnit. Check Product. IdProduct of selected Model Replacement Unit → D. MGT. RegRPC. IdRPCUnit. Check Product. IdProduct of selected Model Replacement Unit → D. MGT. RegRPC. IdRPCUnit. Check Product. IdProduct of selected Model Replacement Unit → D. MGT. RegRPC. IdRPCUnit. Check Product. IdProduct of selected Of Note Replacement Insurance Number → RegRPC. IdAgreement AND Tb_MGT_RegRPC. IdAgreement AND Tb_ | Segment 4: Month Registration actual date (get from TB_MGT_RegRPC.RegDate (YYYY-MM-DD), MM digit) Segment 5: Year Registration actual date get from TB_MGT_RegRPC.RegDate (YYYY-MM-DD), YYYY |
| Agreement Number → RegRPC.IdAgreement AND Tb_MGT_RegRPC.AgreementNumber, Check OPLAgreement.IdOPLAgreement of selected Agreement Number Model OPL Unit → Tb_MGT_RegRPC.IdOPLUnit, Check Product.IdProduct of selected OPL Unit Status → Tb_MGT_RegRPC.IsActive = 1 (Note: 1 = Active; 0 = Not Active) | Check whether Police Number of Replacement Unit that already input by user already exist at Tb_OPL_Unit.PoliceNo. if No then Replacement Unit will be registered to Tb_OPL_Unit - Stored data into table Tb_OPL_Unit, with stored data are: • DSF Office → Tb_OPL_Unit.IdBranch, where Tb_OPL_Branch.BranchShortName = selected DSF Office • Model Replacement Unit → Tb_OPL_Unit.IdProduct, Check Product.IdProduct of selected Model Replacement Unit • Police Number of Replacement Unit → Tb_OPL_Unit.PoliceNo = input Police Number • Machine No → Tb_OPL_Unit.MachineNo = input Machine No chassis No → Tb_OPL_Unit.Colour = input Colour • Start Date STNK → Tb_OPL_Unit.StartSTNK = input Start Date STNK • End Date STNK → Tb_OPL_Unit.StartSTNK = input End Date STNK • End Date STNK → Tb_OPL_Unit.StartKEUR = input End Date STNK • Start Date KEUR → Tb_OPL_Unit.StartKEUR = input Start Date KEUR • End Date KEUR → Tb_OPL_Unit.StartKEUR = input Start Date KEUR • End Date Insurance → Tb_OPL_Unit.StartIns = input End Date KEUR • Start Date Insurance → Tb_OPL_Unit.StartIns = input End Date Insurance Policy • Company Insurance → Tb_OPL_Unit.CompanyInsurance = Input Company Insurance • Insurance Number → Tb_OPL_Unit.InsuranceNumber = Insurance Number • Tb_OPL_Unit.IsOPL = 0 (Note: 0 = Replacement unit; 1 = OPL unit) • CreatedDate = Sys.CurrentDate • CreatedBy = Sys.CurrentUser Stored data into table Tb_MGT_RegRPC, with stored data are: • Registration Number → Tb_MGT_RegRPC.RegNo • Model Replacement Unit → Tb_MGT_RegRPC.IdRPCUnit, Check Product.IdProduct of selected Model Replacement Unit • DSF Office → Tb_MGT_RegRPC.IdBranch, checkTb_OPL_Unit.IdBranch of selected Branch short name • Model Replacement Unit → Tb_MGT_RegRPC.IdRPCUnit, Check Product.IdProduct of selected Model Replacement Unit • Police Number of Replacement Unit → RegRPC.RPCPoliceNo |
| O = Not Active) | Agreement Number → RegRPC.IdAgreement AND Tb_MGT_RegRPC.AgreementNumber, Check OPLAgreement.IdOPLAgreement of selected Agreement Number Model OPL Unit → Tb_MGT_RegRPC.IdOPLUnit, Check Product.IdProduct of selected OPL Unit |
| | 0 = Not Active) |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | - IsCreatable = 0 → if based on other RegNo its IdRPCUnit or IdOPLUnit IsCreatable = 0 and BASTOutStatus != Null IsCreatable = 1 → if based on other RegNo its IdRPCUnit or IdOPLUnit IsCreatable = 0 and BASTOutStatus = Null IsCreatable ! → if based on other RegNo its IdRPCUnit or IdOPLUnit IsCreatable = 1 without checking for its BASTOutStatus • Tb_MGT_RegRPC.RegDate = Sys.CurrentDate • Tb_MGT_RegRPC.RegDate = Sys.CurrentUser 12.4 Check whether Police Number of Replacement Unit that already input by user is used by another OPL unit, with formula as below: Check Tb_MGT_Current.IdReplacingUnit, where Tb_MGT_Current.IdReplacingUnit is MBT_RegRPC.IdRPCUnit. • If Tb_MGT_Current.IdReplacingUnit = null AND there is no Tb_MGT_UnitStatusLoc (first time registration) Then system will display information on Screen 1. Monitoring OPL Unit and Replacement Unit — Replacement Unit — DSF Office (source: Tb_OPL_Branch.Branch Spranch.Branch Spranch.IdBranch = Tb_OPL_Branch.IdBranch = Tb_OPL_Branch.IdBranch = Tb_OPL_Branch.IdBranch = Tb_OPL_Branch.IdBranch = Tb_OPL_Unit.IdTb_OPL_Unit = Tb_OPL_Unit.Source: Product.ModelName) Where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdTb_OPL_Unit AND Tb_OPL_Unit.IdProduct = Product.IdProduct = Product.IdProduct = Product.IdProduct = OPLAgreement No (source: OPLAgreement = OPLAgreement.IdOPLAgreement = Tb_OPL_Unit.IdTb_OPL_Unit = Tb_OPL_Unit.IdTb_OPL_Unit = Tb_OPL_Unit.IdTb_OPL_Unit = Tb_OPL_Unit.IdDPOPL_Unit = Tb_OPL_Unit.IdDPOPL_Unit = Tb_OPL_Unit.IdDPOPL_Unit = Tb_OPL_Unit.IdDPOPL_Unit = Tb_OPL_Unit.IdDPOPL_Unit = Tb_OPL_Unit.IdDPOPL_Unit = Tb_OPL_U |
|--------------|---|
| | Replacement Unit – Replacement Unit - DSF Office (source: Tb_OPL_Branch.BranchShortName) Where Tb_MGT_RegRPC.IdBranch = Tb_OPL_Branch.IdBranch - Registration Number (source: Tb_MGT_RegRPC.RegNumber) |
| | Replacement Unit Police No (source: Tb_OPL_Unit.PoliceNo) Where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdTb_OPL_Unit Model Unit (source: Product.ModelName) Where Tb_MGT_RegRPC.IdRPCUnit = |
| Confidential | ©PT Rerlian Sistem Informasi 2016 Page |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| Tb_OPL_Unit.IdTb_OPL_Unit AND Tb_OPL_Unit.IdProduct = |
|---|
| |
| Product.IdProduct |
| - Agreement No (source: OPLAgreement.AgreementNumber) |
| Where Tb_MGT_RegRPC.IdOPLAgreement = |
| OPLAgreement.IdOPLAgreement |
| Customer Name (source: OPLAgreement.CustomerName) |
| Where Tb_MGT_RegRPC.IdOPLAgreement = |
| OPLAgreement.IdOPLAgreement |
| OPL Unit Police No (source: Tb_OPL_Unit.PoliceNo) |
| Where Tb_MGT_RegRPC.IdOPLUnit = |
| Tb_OPL_Unit.IdTb_OPL_Unit |
| - Active/Not Active (source : Tb_MGT_RegRPC.IsActive) |
| - Unit Status (value: "Return") |
| - Location of Replacement Unit |
| <u>Company Name Source</u> : (value = "PT. DSF") |
| Site source : (value = input Source Location (City)) |
| - Replacing (value = "N/A") |
| - Replacement Type (value = "N/A") |
| - Period of usage – Start Date (value = "N/A") |
| - Period of usage – Estimation (value = "N/A") |
| - Period of usage – End Date (value = "N/A") |
| |
| If Tb_MGT_Current.IdReplacingUnit = null AND |
| Tb_MGT_UnitStatusLoc.Status = "Workshop", Then system will |
| display information on Screen 1. Monitoring OPL Unit and |
| Replacement Unit – Replacement Unit |
| - DSF Office (source: Tb_OPL_Branch.BranchShortName) |
| Where Tb_MGT_RegRPC.IdBranch = |
| Tb_OPL_Branch.IdBranch |
| Registration Number (source: Tb_MGT_RegRPC.RegNumber) |
| - Replacement Unit Police No (source: Tb_OPL_Unit.PoliceNo) |
| Where Tb_MGT_RegRPC.IdRPCUnit = |
| Tb_OPL_Unit.IdTb_OPL_Unit |
| - Model Unit (source: Product.ModelName) |
| Where Tb_MGT_RegRPC.IdRPCUnit = |
| Tb_OPL_Unit.IdTb_OPL_Unit AND Tb_OPL_Unit.IdProduct = |
| Product.IdProduct |
| - Agreement No (source: OPLAgreement.AgreementNumber) |
| |
| Where Tb_MGT_RegRPC.IdOPLAgreement = |
| OPLAgreement.IdOPLAgreement |
| - Customer Name (source: OPLAgreement.CustomerName) |
| Where Tb_MGT_RegRPC.IdOPLAgreement = |
| OPLAgreement.IdOPLAgreement |
| OPL Unit Police No (source: Tb_OPL_Unit.PoliceNo) |
| Where Tb_MGT_RegRPC.IdOPLUnit = |
| Tb_OPL_Unit.IdTb_OPL_Unit |
| Active/Not Active (source : Tb_MGT_RegRPC.IsActive) |
| - Unit Status (value: "Workshop") |
| - Location of Replacement Unit |
| <u>Column 1 source</u> : (source: Tb_MTN_UnderMT.Workshop) |
| Where |
| Tb_MGT_UnitStatusLoc.LineTrans = |
| Tb_MTN_UnderMT.IdTb_MTN_UnderMT |
| Column 2 source: Tb_MGT_UnitStatusLoc.Location) |
| Where Tb_MGT_Current.IdTb_MGT_UnitStatusLoc = |
| Tb_MGT_UnitStatusLoc.IdTb_MGT_UnitStatusLoc |
| - Replacing (value = "N/A") |
| - Replacement Type (value = "N/A") |
| - Period of usage – Start Date (source: |
| . o. loa o. doago otal i buto (boaroc. |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| Tb_MGT_UnitStatusLoc.StartDate) |
|--|
| Period of usage – Estimation (value = "N/A") |
| Period of usage – End Date (value = "N/A") |
| |
| If Tb_MGT_Current.IdReplacingUnit = null AND |
| Tb_MGT_UnitStatusLoc.Status = "Insurance Claim", Then |
| system will display information on Screen 1. Monitoring OPL |
| Unit and Replacement Unit – Replacement Unit |
| DSF Office (source: Tb_OPL_Branch.BranchShortName) |
| Where Tb_MGT_RegRPC.IdBranch = |
| Tb_OPL_Branch.IdBranch |
| Registration Number (source: Tb_MGT_RegRPC.RegNumber) |
| Replacement Unit Police No (source: Tb_OPL_Unit.PoliceNo) |
| Where Tb_MGT_RegRPC.IdRPCUnit = |
| Tb_OPL_Unit.IdTb_OPL_Unit |
| Model Unit (source: Product.ModelName) |
| Where Tb_MGT_RegRPC.IdRPCUnit = |
| Tb_OPL_Unit.IdTb_OPL_Unit AND Tb_OPL_Unit.IdProduct = |
| Product.IdProduct |
| - Agreement No (source: OPLAgreement.AgreementNumber) |
| |
| Where Tb_MGT_RegRPC.IdOPLAgreement = |
| OPLAgreement.IdOPLAgreement |
| - Customer Name (source: OPLAgreement.CustomerName) |
| Where Tb_MGT_RegRPC.IdOPLAgreement = |
| OPLAgreement.IdOPLAgreement |
| OPL Unit Police No (source: Tb_OPL_Unit.PoliceNo) |
| Where Tb_MGT_RegRPC.IdOPLUnit = |
| Tb_OPL_Unit.IdTb_OPL_Unit |
| - Active/Not Active (source : Tb_MGT_RegRPC.IsActive) |
| - Unit Status (value: "Insurance Claim") |
| - Location of Replacement Unit |
| Company Name source: (source: |
| Tb_MTN_UnderMT.Workshop) |
| Where |
| Tb_MGT_UnitStatusLoc.LineTrans = |
| Tb_MTN_UnderMT.IdTb_MTN_UnderMT |
| Site source: (source: Tb_MGT_UnitStatusLoc.Location) |
| Where Tb_MGT_Current.IdTb_MGT_UnitStatusLoc = |
| Tb_MGT_UnitStatusLoc.IdTb_MGT_UnitStatusLoc |
| - Replacing (value = "N/A") |
| - Replacing (value = N/A) - Replacement Type (value = "N/A") |
| - Replacement Type (value = N/A) - Period of usage – Start Date (source: |
| Tb_MGT_UnitStatusLoc.StartDate) |
| - Period of usage – Estimation (value = "N/A") |
| - Period of usage – Estimation (value = "N/A") - Period of usage – End Date (value = "N/A") |
| . Silve Si douge Ella Date (value - 19/1) |
| If Tb_MGT_Current.IdReplacingUnit != null, then on Screen 1. |
| Monitoring OPL Unit and Replacement Unit – Replacement Unit |
| will be displayed information as below: |
| - DSF Office (source: Tb_OPL_Branch.BranchShortName) |
| Where Tb_MGT_RegRPC.IdBranch = |
| Tb_OPL_Branch.IdBranch |
| - Registration Number (source: Tb_MGT_RegRPC.RegNumber) |
| - Replacement Unit Police No (source: Tb_OPL_Unit.PoliceNo) |
| Where Tb_MGT_RegRPC.IdRPCUnit = |
| Tb_OPL_Unit.IdTb_OPL_Unit |
| - Model Unit (source: Product.ModelName) |
| Where Tb_MGT_RegRPC.IdRPCUnit = |
| · · · · · · · · · · · · · · · · · · · |
| Tb_OPL_Unit.IdTb_OPL_Unit AND Tb_OPL_Unit.IdProduct = |
| Product.IdProduct |


| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| Project Name : | Operating Lease Support System Phase-2 | | |
|----------------|--|--|--|
| | - Agreement No (source: OPLAgreement.AgreementNumber) Where Tb_MGT_RegRPC.IdOPLAgreement = OPLAgreement.IdOPLAgreement - Customer Name (source: OPLAgreement.CustomerName) Where Tb_MGT_RegRPC.IdOPLAgreement = OPLAgreement.IdOPLAgreement - OPL Unit Police No (source: Tb_OPL_Unit.PoliceNo) Where Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdTb_OPL_Unit - Active/Not Active (source: Tb_MGT_RegRPC.IsActive) - Unit Status (source: Tb_MGT_UnitStatusLoc.Status) Where Tb_MGT_Current.IdTb_MGT_UnitStatusLoc = Tb_MGT_UnitStatusLoc.IdTb_MGT_UnitStatusLoc - Location of Replacement Unit Company Name source: (source: OPLAgreement.CustomerName) Where Tb_MGT_Current.IdAgreement = OPLAgreement.IdOPLAgreement Site source: (source: Tb_MGT_UnitStatusLoc.Location) Where Tb_MGT_Current.IdTb_MGT_UnitStatusLoc - Replacement Type (source: Tb_MGT_UnitStatusLoc - Replacement Type (source: Tb_MGT_UnitStatusLoc) - Period of usage - Start Date (source: Tb_MGT_UnitStatusLoc.StartDate) - Period of usage - Estimation (source: Tb_MGT_UnitStatusLoc.EstDate) - Period of usage - End Date (source: Tb_MGT_UnitStatusLoc.EstDate) - Period of usage - End Date (source: Tb_MGT_UnitStatusLoc.EndDate) | | |
| | 10. When user click button Cancel or Close (X) after saved data, screen will back to Screen 1. Monitoring OPL Unit and Replacement Unit – Replacement Unit | | |
| | Output: System will display confirmation message Screen 24. Notification Pop Up When Register Replacement Unit Data Replacement Unit will be display to Screen 1. Monitoring OPL Unit and Replacement Unit – Replacement Unit | | |
| | If status of replacement unit is Active (Tb_MGT_RegRPC.isActive = 1) then all button on field Action Screen 1. Monitoring OPL Unit and Replacement Unit – Replacement Unit will be active. | | |
| | | | |
| | 4. But if status of replacement unit is Not Active (Tb_MGT_RegRPC.isActive = 0), then button Create and Edit Replacement Unit on field Action Screen 1. Monitoring OPL Unit and Replacement Unit – Replacement Unit will be Not Active | | |



5. If unit replacement is being used by other OPL unit (Tb_MGT_Current.IdReplacingUnit != null), then button Create and Edit Replacement Unit on field Action **Screen 1. Monitoring OPL Unit and** Replacement Unit - Replacement Unit will be Not Active

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |



| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

- 12.7 Input Branch/ Poll
- 12.8 Input Remark
- 12.9 Input Unit Component
- 12.10 Select Condition of Unit Component
- 12.11 Add Item (optional)
- 12.12 Input Remark (Note: Body/ Paint of Car)
- 13. Click button Save as Draft

Constraint:

- For all input data cannot more than length on data structure
- For all input calendar, End Date cannot more than Start Date

Process:

- 1. When user click button generate Replacement Unit (), System will display Screen 9. Create BAST Replacement Pop Up Dialog
- If user select BAST Replacement Unit, then after click button Next, system will display Screen 13. Create BAST Replacement – Replacement Unit
- 3. Text field BAST No will be blank
- 4. If user select BAST OPL Unit, then after click button Next, system will display Screen 14. Create BAST Replacement OPL Unit
- On Screen 13. Create BAST Replacement Replacement Unit and On Screen 14. Create BAST Replacement – OPL Unit:
 - 5.1 If user select Replacement Type: General Repairment and Insurance, there is no additional component screen that will be display
 - 5.2 If user select Replacement Type: Special Case, then system will display additional component screen as below:



- 5.3 On Section Base Information, system will display below data automatically:
 - Agreement No (Tb_MGT_RegRPC.AgreementNumber)
 - Company Name (OPLAgreement.CustomerName, where Tb_MGT_RegRPC.IdOPLAgreement = OPLAgreement.IdOPLAgreement)
 - Address (OPLAgreement.Address, where Tb_MGT_RegRPC.IdOPLAgreement = OPLAgreement.IdOPLAgreement)
- 5.4 If user select BAST replacement unit, then on Section Replacement Unit, system will display below data automatically:
 - Police Number (Tb_OPL_Unit.PoliceNo, where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct)
 - Merk/Vehicle Type (Product.ModelName, where Tb_MGT_RegRPC.IdRPCUnit = Product.IdProduct)
 - Colour (Tb_OPL_Unit.Colour, where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct)
 - Chassis No (Tb_OPL_Unit.ChassisNo, where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct)
 - Machine No (Tb_OPL_Unit.MachineNo, where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct)
 - STNK Date (Tb_OPL_Unit.EndSTNK, where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct)

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | KEUR Date (Tb_OPL_Unit.EndKEUR, where |
|---|--|
| | Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct) |
| | 5.5 If user select BAST OPL unit, then on Section Operating Lease Unit, |
| | system will display below data automatically: |
| | - Police Number (Tb_OPL_Unit.PoliceNo, where |
| | Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct) |
| | Merk/Vehicle Type (Product.ModelName, where |
| | Tb_MGT_RegRPC.IdOPLUnit = Product.IdProduct) |
| | - Colour (Tb_OPL_Unit.Colour, where Tb_MGT_RegRPC.IdOPLUnit = |
| | Tb_OPL_Unit.IdProduct) |
| | Chassis No (Tb_OPL_Unit.ChassisNo, where |
| | Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct) |
| | - Machine No (Tb_OPL_Unit.MachineNo, where |
| | Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct) |
| | - STNK Date (Tb_OPL_Unit.StartSTNK, where |
| | Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct) |
| | - KEUR Date (Tb_OPL_Unit.StartKEUR, where |
| | Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct) |
| | 5.6 On Section Unit Component Information, system will display below |
| | input data automatically: |
| | - Starter/Ignition System |
| | - Air Conditioner Merk |
| | - STNK |
| | - Radio Tape/ Merk |
| | - CD Player/ Merk |
| | - Catridge/ Remote R/ Tape |
| | - Antena |
| | - Lighter/ Pematik |
| | - Asbak |
| | - Seat Cover/ Sarung Jok |
| | - Safety Belt |
| | - Head Rest |
| | - Lampu Plafon |
| | Karpet LembaranKotak P3K |
| | - Kotak P3K - Segitiga Pengaman |
| | - Segringa Pengaman - Perkakas Standar |
| | - Perkakas Standar - Dongkrak/ Tuas |
| | - Dongkrak/ Tuas - Dop Roda 4 Buah |
| | - Kaca Spion Dalam |
| | - Kaca Spion Dalam - Kaca Spion Luar |
| | - Raca Spion Luai - Ban 4 Buah |
| | - Ban Cadangan 1 Buah |
| | - Kipas/ Wiper |
| | - Buku Manual |
| | - Buku Service |
| | - Tutup Bensin |
| | - Lampu-lampu sein |
| | - Lampu Besar |
| | - Lampu Kecil |
| | - Lampu Rem |
| | - Lampu Mundur |
| | - Kaca Film |
| | 5.7 If user click button Add Item, then it will add row on selected tab; |
| | BAST Out and BAST In includes several components on each row: |
| | - Running Number |
| | - Component |
| • | · |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

- Condition; Good, Damage, Missing, Not Exist 5.8 Tab BAST In will be Not Active and cannot be clicked

6. Several component screen will be as below: If user select create BAST Replacement unit

| Donloomont | Component | | |
|---------------------|-------------------------|---------------|----------------------|
| Replacement Type | Button Save as Draft | Button Submit | Button Print Memo |
| General repairment | Active | Not Active | Not Active |
| Insurance | Active | Not Active | Not Active |
| Special Case | Active | Active | Active |

If user select create BAST OPL unit

| Davida a succept | Component | | | |
|---------------------|----------------|---------------|--------------|--|
| Replacement Type | Button Save as | Button Submit | Button Print | |
| туре | Draft | | Memo | |
| General | Active | Not Active | Not Active | |
| repairment | | | | |
| Insurance | Active | Not Active | Not Active | |
| Special Case | Active | Not Active | Not Active | |

- 7. When user click button Save as Draft, system will:
 - 7.1 System will display Screen 21. Confirmation Pop Up When Save as Draft BAST Replacement
 - If user click button Ok, then system will continue to process create BAST Replacement and generate BAST number
 - 7.2 System will generate BAST Replacement number with below format automatically:

BAST Replacement Unit

00001/BRU/JKT/11/2015

Segment 1: 5 digit running number (get from table configuration field identifier 1, where document = BAST Replacement Unit)

Segment 2: Identifier of document (BRU = BAST Replacement Unit)

Segment 3: DSF Office Short Name

(Tb_OPL_Branch.BranchShortName, where Tb_OPL_Unit.IdBranch = Tb_OPL_Branch.IdBranch)

Segment 4: Month BAST actual date (get from current month)

Segment 5: Year BAST actual date (get from current year)

BAST OPL Unit

00001/BOU/JKT/11/2015

Segment 1: 5 digit running number (get from table configuration field identifier 1, where document = BAST OPL Unit)

Segment 2: Identifier of document (BOU = BAST OPL Unit)

Segment 2. Identifier of document (BOO = BAST OFE C

Segment 3: DSF Office Short Name

(Tb_OPL_Branch.BranchShortName, where Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct AND Tb_OPL_Unit.IdBranch = Tb_OPL_Branch.IdBranch)

Segment 4: Month BAST actual date (get from current month)

Segment 5: Year BAST actual date (get from current year)

- 7.3 System will change Tb_MGT_RegRPC.IsCreatable into 0, if there is any IdRPCUnit or IdOPLUnit on other IdRegRPC
- 7.4 System will save data BAST Replacement to table Tb_MGT_BASTRPC

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| П | |
|-----|--|
| | with data as below: |
| | - BAST Number → Tb_MGT_BASTRPC.BASTNumber |
| | - Tb_MGT_BASTRPC.BASTType = 1 or 2 (Note: 1= BAST |
| | replacement Unit; 2= BAST OPL Unit) |
| | Tb_MGT_BASTRPC.IdTb_MGT_RegRPC = Tb_MGT_RegRPC. |
| | IdTb_MGT_RegRPC → check Tb_MGT_RegRPC. |
| | IdTb_MGT_RegRPC of selected Registration RPC |
| | Replacement Type → Tb_MGT_BASTRPC.RPCType |
| | Telp Number → Tb_MGT_BASTRPC.TelpNumber |
| | PIC Number → Tb_MGT_BASTRPC.PIC |
| | Start Date Usage Replacement Unit → Tb_MGT_ |
| | BASTRPC.StartDate (If BAST Replacement Unit) |
| | End Date Usage Replacement Unit → Tb_MGT_ BASTRPC.EstDate |
| | (If BAST Replacement Unit) |
| | Start Date Repairment OPL Unit → Tb_MGT_ BASTRPC.StartDate |
| | (If BAST OPL Unit) |
| | End Date Repairment OPL Unit → Tb_MGT_ BASTRPC.EstDate (If |
| | BAST OPL Unit) |
| | Date BAST Out → Tb_MGT_BASTRPC.DateOut |
| | - KM Out → Tb_MGT_ BASTRPC.KMOut |
| | - Fuel Out → Tb_MGT_ BASTRPC.FuelOut |
| | Driver Name Out → Tb_MGT_ BASTRPC.DriverOut |
| | - Branch/Poll Out → Tb_MGT_ BASTRPC.BranchOut |
| | - Status BAST Out → Tb_MGT_BASTRPC.BASTOutStatus = 1 (note: |
| | 1= draft; 2= Submitted; 30= Firmed) |
| | - Usage Location → Tb_MGT_ BASTRPC.UsageLoc |
| | - Damage Location → Tb_MGT_ BASTRPC.DamageLoc |
| | - Remark Out → Tb_MGT_ BASTRPC.RemarkOut |
| | Remark out 7 15_Me1_ Broth enternanced |
| | 7.5 System will save data BAST Replacement to table |
| | Tb_MGT_BASTRPCDtl with data as below: |
| | - Tb_MGT_BASTRPCDtl.IdTb_MGT_BASTRPC = |
| | Tb_MGT_BASTRPC.IdTb_MGT_BASTRPC |
| | - Unit Component → Tb_MGT_ BASTRPCDtl.Description |
| | - Condition → Tb_MGT_ BASTRPCDtl.BASTOutValue (value: 1: |
| | Good, 2: Damage, 3: Missing, 4: Not Exist) |
| | - Remark → Tb_MGT_ BASTRPCDtl.Remark |
| | - Remark / Tb_WGT_ BASTRFCDtt.Remark |
| | 7.4 For angular ages type, system will save data DAST Depleasment to |
| | 7.6 For special case type, system will save data BAST Replacement to |
| | table Tb_MGT_MemoRPC with data as below: |
| | Tb_MGT_MemoRPC.IdTb_MGT_BASTRPC = Tb_MGT_BASTRPC_IdTb_MGT_BASTRPC |
| | Tb_MGT_BASTRPC.IdTb_MGT_BASTRPC |
| | Memo Number → Tb_MGT_MemoRPC.MemoNo |
| | Format: 00001/MRU/JKT/11/2015 |
| | Segment 1: 5 digit running number (get from table |
| | configuration field identifier 1, where document = |
| | Memo) |
| | Segment 2: Identifier of document (MRU = Memo) |
| | Segment 3: DSF Office Short Name |
| | (Tb_OPL_Branch.BranchShortName, where |
| | Tb_MGT_RegRPC.IdOPLUnit = |
| | Tb_OPL_Unit.IdProduct AND Tb_OPL_Unit.IdBranch |
| | = Tb_OPL_Branch.IdBranch) |
| | Segment 4: Month BAST actual date (get from current month) |
| | Segment 5: Year BAST actual date (get from current year) |
| | Memo date → Tb_MGT_MemoRPC.MemoDate |
| i I | Mome Note -> Th. MCT. MemoRRC Descriptor |
| | Memo Note → Tb_MGT_MemoRPC.Descripton |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| • | IsMemo → Tb | _MGT_ | _BASTRPC.IsMemo = | 1 | (note: 1= dra | ıft) |
|---|-------------|-------|-------------------|---|---------------|------|
|---|-------------|-------|-------------------|---|---------------|------|

7.7 When Save as Draft button is clicked, System will add a new Log of Create BAST action to Tb_MGT_BASTRPC_History. Data which should be inserted are:

| Field Name | Value |
|-------------|----------------------|
| ProcessId | NewGUID |
| OriginalId | Tb_MGT_BASTRPC.IdTb_ |
| | MGT_BASTRPC |
| CreatedDate | Sys.CurrentDate |
| CreatedBy | Sys.CurrentUser |
| Action | Save as Draft |

7.8 History Data will be stored in the table Tb_MGT_BASTRPC_History and Tb_ MGT_ BASTRPC_History_Dtl where Tb_MGT_ BASTRPC_History_Dtl is Tb_MGT_ BASTRPC added Tb_MGT_ BASTRPC_History.IdTb_MGT_ BASTRPC_History as a foreign key

Output:

1. System will display pop up message:

Screen 26. Notification Pop Up When Save as Draft BAST Replacement

13 Edit BAST Replacement

Input:

- 1. Access OLSS
- 2. Select menu Management
- 3. Select sub menu Monitoring Unit OPL and Unit Replacement
- 4. Click button Edit Replacement Unit on Screen 1. Monitoring OPL Unit and Replacement Unit Replacement Unit ()
- Click button Next on Screen 10. Edit BAST Replacement Pop Up Dialog
- 6. Edit Replacement Type; General Repairment, Special Case, Insurance Claim
 - If user select Special Case, user must input Note for request approval replacement unit to authorize person
- 7. Edit Telp Number
- 8. Edit PIC Customer
- 9. Edit Start Date Usage Replacement Unit or Start Date Repairment OPL Unit
- Edit End Date Estimation Usage Replacement Unit or End Date Repairment OPL Unit
- 11. Select tab BAST Out and edit several data as below:
 - 11.1 Edit Date Unit Out
 - 11.2 Edit Usage Location or Input Damage Location
 - 11.3 Edit KM
 - 11.4 Edit Fuel
 - 11.5 Edit Driver Name
 - 11.6 Edit Observer Name
 - 11.7 Edit Branch/ Poll
 - 11.8 Edit Remark
 - 11.9 Edit Unit Component
 - 11.10 Select Condition of Unit Component
 - 11.11 Add Item (optional)
 - 11.12 Edit Remark (Note: Body/ Paint of Car)

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

- 12. Or Select tab BAST In and input/edit several data as below:
 - 12.1 Input/edit Date Unit In
 - 12.2 Input/edit Return Location
 - 12.3 Input/edit KM
 - 12.4 Input/edit Fuel
 - 12.5 Input/edit Driver Name
 - 12.6 Input/edit Observer Name
 - 12.7 Input/edit Branch/ Poll
 - 12.8 Input/edit Remark
 - 12.9 Input/edit Unit Component
 - 12.10 Select Condition of Unit Component
 - 12.11 Add Item (optional)
 - 12.12 Edit Remark (Note: Body/ Paint of Car)
- 13. Click button Save Change

Constraint:

- For all input data cannot more than length on data structure
- For all input calendar, End Date cannot more than Start Date

Process:

- 1. When user click button Edit Replacement Unit (), System will display Screen 9. Edit BAST Replacement Pop Up Dialog
- If user select BAST Replacement Unit, then after click button Next, system will display Screen 15. Edit BAST Replacement – Replacement Unit
- 3. If user select BAST OPL Unit, then after click button Next, system will display **Screen 16. Edit BAST Replacement OPL Unit**
- On Screen 15. Create BAST Replacement Replacement Unit and On Screen 16. Create BAST Replacement – OPL Unit:
 - 4.1 If user select Replacement Type: General Repairment and Insurance, there is no additional component screen that will be display
 - 4.2 If user select Replacement Type: Special Case, then system will display additional component screen as below:



- 4.3 On Section Base Information, system will display below data automatically:
 - Agreement No (Tb_MGT_RegRPC.AgreementNumber)
 - Company Name (OPLAgreement.CustomerName, where Tb_MGT_RegRPC.IdOPLAgreement = OPLAgreement.IdOPLAgreement)
 - Address (OPLAgreement.Address, where Tb_MGT_RegRPC.IdOPLAgreement = OPLAgreement.IdOPLAgreement)

Note: All information above canot be edit

- 4.4 If user select BAST replacement unit, then on Section Replacement Unit, system will display below data automatically:
 - Police Number (Tb_OPL_Unit.PoliceNo, where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct)
 - Merk/Vehicle Type (Product.ModelName, where

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| Г | |
|---|---|
| | Tb_MGT_RegRPC.IdRPCUnit = Product.IdProduct) |
| | Year (Product.ModelYear, where Tb_MGT_RegRPC.IdRPCUnit = |
| | Product.IdProduct) |
| | - Colour (Tb_OPL_Unit.Colour, where Tb_MGT_RegRPC.IdRPCUnit = |
| | Tb_OPL_Unit.IdProduct) |
| | - Chassis No (Tb_OPL_Unit.ChassisNo, where |
| | Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct) |
| | - Machine No (Tb_OPL_Unit.MachineNo, where |
| | Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct) |
| | - STNK Date (Tb_OPL_Unit.StartSTNK, where |
| | Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct) |
| | - KEUR Date (Tb_OPL_Unit.StartKEUR, where |
| | Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct) |
| | Note: All information above canot be edit |
| | 4.5 If user select BAST OPL unit, then on Section Operating Lease Unit, |
| | system will display below data automatically: |
| | - Police Number (Tb_OPL_Unit.PoliceNo, where |
| | Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct) |
| | - Merk/Vehicle Type (Product.ModelName, where |
| | Tb_MGT_RegRPC.IdOPLUnit = Product.IdProduct) |
| | |
| | · |
| | Product.IdProduct) Colour (Th. ODL. Unit Colour, whore Th. MCT. BogDDC IdODLUnit |
| | - Colour (Tb_OPL_Unit.Colour, where Tb_MGT_RegRPC.IdOPLUnit = |
| | Tb_OPL_Unit.IdProduct) |
| | - Chassis No (Tb_OPL_Unit.ChassisNo, where |
| | Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct) |
| | - Machine No (Tb_OPL_Unit.MachineNo, where |
| | Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct) |
| | - STNK Date (Tb_OPL_Unit.StartSTNK, where |
| | Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct) |
| | - KEUR Date (Tb_OPL_Unit.StartKEUR, where |
| | Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct) |
| | Note: All information above canot be edit |
| | 4.6 Tab BAST In will be enable when Tb_MGT_BASTRPC.BASTOutStatus = |
| | 30 |
| | 4.7 System will display Telp Number, PIC customer, and information in |
| | both tab BAST out and BAST in based on selected BAST Number with |
| | below formula: |
| | Tab BAST Out: |
| | - Date BAST Out → Tb_MGT_BASTRPC.DateOut |
| | - KM Out → Tb_MGT_ BASTRPC.KMOut |
| | - Fuel Out → Tb_MGT_ BASTRPC.FuelOut |
| | - Driver Name Out → Tb_MGT_ BASTRPC.DriverOut |
| | - Observer Name Out → Tb_MGT_ BASTRPC.ObserverOut |
| | - Branch/Poll Out → Tb_MGT_ BASTRPC.BranchOut |
| | - Usage Location → Tb_MGT_ BASTRPC.UsageLoc |
| | - Damage Location → Tb_MGT_ BASTRPC.DamageLoc |
| | - Remark Out → Tb_MGT_ BASTRPC.RemarkOut |
| | - Remark Out → Tb_MGT_ BASTRPC.RemarkOut2 |
| | Tab BAST In: |
| | - Date BAST In → Tb_MGT_BASTRPC.DateIn |
| | |
| | - KM In → Tb_MGT_ BASTRPC.KMIn |
| | - Fuel In → Tb_MGT_ BASTRPC.FuelIn |
| | - Driver Name In → Tb_MGT_ BASTRPC.DriverIn |
| | - Observer Name Out → Tb_MGT_ BASTRPC.ObserverIn |
| | - Branch/Poll In → Tb_MGT_ BASTRPC.BranchIn |
| | - Return Location → Tb_MGT_ BASTRPC.ReturnLoc |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

- Remark In → Tb_MGT_ BASTRPC.RemarkIn
- Remark In2 → Tb_MGT_ BASTRPC.RemarkIn2
- 4.8 On Section Unit Component Information, system will display below input data automatically based on selected BAST number which Tb_MGT_BASTRPCDtl.IdTb_MGT_BASTRPC = Tb_MGT_BASTRPC. IdTb_MGT_BASTRPC AND Tb_MGT_BASTRPCDtl.BASTOutValue = 1 or 2 (Note: 1 = BAST Detail Out; 2 = BAST Detail In)
- 4.9 If user click button Add Item, then it will add row on selected tab; BAST Out and BAST In includes several components on each row:
 - Running Number
 - Component
 - Condition; Good, Damage, Missing, Not Exist
- 5. Several component screen will be as below:

If user select create BAST Replacement unit

| | Component | | | |
|--------------|-----------|------------|------------|---------|
| Replacement | Button | Button | Button | Button |
| Type | Save | Print | Submit | Save as |
| | Change | Memo | | final |
| General | Active | Not Active | Not Active | Active |
| repairment | | | | |
| Insurance | Active | Not Active | Not Active | Active |
| Special Case | Active | Active | Active | Active |

If user select create BAST OPL unit

| | Component | | | |
|--------------|-----------|------------|--------------|---------|
| Replacement | Button | Button | Button Print | Button |
| Type | Save as | Submit | Memo | Save as |
| | Draft | | | final |
| General | Active | Not Active | Not Active | Active |
| repairment | | | | |
| Insurance | Active | Not Active | Not Active | Active |
| Special Case | Active | Not Active | Not Active | Active |

- 6. When user click button Save Change, system will:
 - 6.1 System will display **Screen 23. Confirmation Pop Up When Save Change BAST Replacement**
 - If user click button Yes, then system will continue to process edit BAST Replacement for selected BAST number
 - 6.2 System will save updated data BAST Replacement to table Tb_MGT_BASTRPC with data as below:
 - BAST Number → Tb_MGT_BASTRPC.BASTNumber
 - Tb_MGT_BASTRPC.BASTType = 1 or 2 (Note: 1= BAST replacement Unit; 2= BAST OPL Unit)
 - Tb_MGT_BASTRPC.IdTb_MGT_RegRPC = Tb_MGT_RegRPC.
 IdTb_MGT_RegRPC → check Tb_MGT_RegRPC.
 IdTb_MGT_RegRPC of selected Registration RPC
 - Replacement Type → Tb_MGT_BASTRPC.RPCType
 - Telp Number → Tb_MGT_BASTRPC.TelpNumber
 - PIC Number → Tb_MGT_BASTRPC.PIC
 - Start Date Usage Replacement Unit → Tb_MGT_ BASTRPC.StartDate (If BAST Replacement Unit)
 - End Date Usage Replacement Unit → Tb_MGT_ BASTRPC.EstDate (If BAST Replacement Unit)
 - Start Date Repairment OPL Unit → Tb_MGT_ BASTRPC.StartDate

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

(If BAST OPL Unit)

- End Date Repairment OPL Unit → Tb_MGT_ BASTRPC.EstDate (If BAST OPL Unit)
- Date BAST Out → Tb_MGT_BASTRPC.DateOut
- Date BAST In → Tb_MGT_BASTRPC.DateIn
- KM Out → Tb_MGT_ BASTRPC.KMOut
- KM In → Tb MGT BASTRPC.KMIn
- Fuel Out → Tb_MGT_ BASTRPC.FuelOut
- Fuel In → Tb_MGT_ BASTRPC.FuelIn
- Driver Name Out → Tb MGT BASTRPC.DriverOut
- Driver Name In → Tb_MGT_ BASTRPC.DriverIn
- Branch/Poll Out → Tb_MGT_ BASTRPC.BranchOut
- Branch/Poll In → Tb_MGT_ BASTRPC.BranchOut
- Status BAST Out → Tb_MGT_BASTRPC.BASTOutStatus = 1 (note:
 1= draft; 2= Submitted; 3= Firmed)
- Or Status BAST In → Tb_MGT_BASTRPC.BASTInStatus = 1 (note:
 1= draft; 2= Submit)
- Usage Location → Tb_MGT_ BASTRPC.UsageLoc
- Damage Location → Tb_MGT_ BASTRPC.DamageLoc
- Damage Location → Tb_MGT_ BASTRPC.ReturnLoc
- 6.3 System will save data BAST Replacement to table

Tb_MGT_BASTRPCDtl with data as below:

- Tb_MGT_BASTRPCDtl.IdTb_MGT_BASTRPC =
 Tb_MGT_BASTRPC.IdTb_MGT_BASTRPC
- Unit Component → Tb_MGT_ BASTRPCDtl.Description
- Condition → Tb_MGT_ BASTRPCDtl.BASTOutValue or Tb_MGT_ BASTRPCDtl.BASTInValue (value: 1: Good, 2: Damage, 3: Missing, 4: Not Exist)
- Remark → Tb_MGT_ BASTRPCDtl.Remark
- 6.4 For special case:
- In tab BAST Out
 - >> Button Save as Final can not be clicked until

Tb_MGT_BASTOutStatus = 3 (Approved)

- >> Button Print Memo will always enable
- >> Button Submit will enable when:
 - >>> Tb_MGT_BASTOutStatus = 1 (Draft)
 - >>> Tb_MGT_BASTOutStatus = 4 (Revised)
- In tab BAST In
 - >> Button Save as Final will always enable
 - >> Button Save Change, Print Memo, and Submit disable
- 6.5 When Save Change button is clicked, System will add a new Log of Create BAST action to Tb_MGT_BASTRPC_History. Data which should be inserted are:

| Field Name | Value |
|-------------|----------------------|
| ProcessId | NewGUID |
| OriginalId | Tb_MGT_BASTRPC.IdTb_ |
| | MGT_BASTRPC |
| CreatedDate | Sys.CurrentDate |
| CreatedBy | Sys.CurrentUser |
| Action | Save Change |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | | 6.6 History Data will be stored in the table Tb_MGT_BASTRPC_History and Tb_ MGT_ BASTRPC_History_Dtl where Tb_MGT_ BASTRPC_History_Dtl is Tb_MGT_ BASTRPC added Tb_MGT_ BASTRPC_History.IdTb_MGT_ BASTRPC_History as a foreign key Output: 1. System will display pop up message: Screen 27. Notification Pop Up When Save Change BAST Replacement |
|----|---|---|
| 14 | Print Memo Replacement Unit | Input: Operation Name No. 10 Generate BAST Replacement no 1 – 12 or Operation Name No. 11 Edit BAST Replacement no 1 – 12 Click button Print Memo Print Memo At print form preview, click print button to print document BAST as a hardcopy System will display print preview of Memo Replacement unit If Tb_MGT_BASTRPC.BASTOutStatus = 2 (Submited) then field sign must display authorize name based on approval path System will convert Memo into selected file type Ms. Excel or pdf and file will be stored in selected path with file name as below format: |
| 15 | Submit Replacement Unit Request (Special Case) to get approval | Input: 1. Operation Name No. 10 Generate BAST Replacement no 1 – 12 or Operation Name No. 11 Edit BAST Replacement no 1 – 12 2. Click button Process: 1. Form BAST Replacement Unit will be display at Replacement Unit Approval (refer to FC.AD.1.6 Replacement Unit Approval) 2. System will update Tb_MGT_BASTRPC.BASTOutStatus = 1 into Tb_MGT_BASTRPC.BASTOutStatus = 2 (Note 1= Draft; 2= Submitted) Output: 1. Form BAST Replacement unit will goes to approval flow (refer to FC.AD.1.6 Replacement Unit Approval) |
| 16 | Print Replacement Unit | Input: 1. Access OLSS 2. Select menu Management 3. Select sub menu Monitoring Unit OPL and Unit Replacement 4. Click button Print Replacement Unit on Screen 1. Monitoring OPL Unit and Replacement Unit – Replacement Unit () 5. Select BAST Replacement Unit that will be printed using radio button (BAST Replacement Unit or BAST OPL Unit) |

| | | Operating Lease Support System Filase-2 |
|----|-------------|---|
| | | Select BAST Replacement unit number using search box Click button Next At print form preview, click print button to print document BAST as a hardcopy. Process: When user click button →, system will display Screen 12. Print BAST Replacement Pop Up Dialog When user select click serach box then system will display Screen 19. BAST List Pop Up Dialog: By default system will display all BAST No (Tb_MGT_BASTRPC.BASTNUmber) and Created Date (Tb_MGT_BASTRPC.BASTNUMBER) Tb_MGT_BASTRPC.BASTOUTSTATUS = 1 AND Tb_MGT_BASTRPC.RPCType = General Repair, Tb_MGT_BASTRPC.BASTOUTSTATUS = 1 AND Tb_MGT_BASTRPC.BASTOUTSTATUS = 3 AND Tb_MGT_BASTRPC.RPCType = Insurance Tb_MGT_BASTRPC.RPCType = Special Case that already register to system with number of row list based on selected show entries number. Note: Status 1 = Draft Status 2 = Submitted Status 2 = Submitted Status 3 = Approve If user input criteria searching on search box, then system will filter BAST number number based on input criteria searching When user double click on selected row, then display screen will back to Screen 12. Print BAST Replacement Pop Up Dialog When click button Next, system will display preview of form BAST Replacement unit By default system will display BAST that already created based on Tb_MGT_BASTRPC.IdTb_MGT_BASTRPC System will convert document BAST into selected file type Ms. Excel or pdf and file will be stored in selected path with file name as below format: BAST Replacement Unit_MMddyyyy_hhmm Note: MMddyyyy → month,day,year when report printed hhmm → hours, minute when report printed System will print document BAST as a hardcopy when user click print button at Print form preview. Output: Print out form BAST R |
| 17 | View BAST | 1. Print out form BAST Replacement PF.AD.1.3 BAST OPL Unit and BAST |
| | Replacement | Access OLSS Select menu Management Select sub menu Monitoring Unit OPL and Unit Replacement Click button Edit Replacement Unit on Screen 1. Monitoring OPL Unit and Replacement Unit - Replacement Unit () Select BAST that will be displayed using radio button: BAST Replacement |

Operating Lease Support System Phase-2

Project Code :

Project Name :

TM15404A

| | Project Code : | TWT54U4A |
|----|--|--|
| | Project Name : | Operating Lease Support System Phase-2 |
| | | |
| | | Unit or BAST OPL Unit using search box 6. Select BAST Replacement unit number using search box 7. Click button Next on Screen 10. View BAST Replacement Pop Up Dialog Process: 1. When user click button , system will display Screen 11. View BAST Replacement Pop Up Dialog 2. When user select click search box then system will display Screen 19. BAST List Pop Up Dialog: - By default system will display all BAST No (Tb_MGT_BASTRPC.BASTNumber) and Created Date (Tb_MGT_BASTRPC.BASTNumber) and Created Date (Tb_MGT_BASTRPC.BASTOUTStatus = 1 AND Tb_MGT_BASTRPC.BASTOUTStatus = 1 AND Tb_MGT_BASTRPC.BASTOUTSTATUS = 1 AND Tb_MGT_BASTRPC.BASTOUTSTATUS = 2 AND Tb_MGT_BASTRPC.BASTOUTSTATUS = 2 AND Tb_MGT_BASTRPC.BASTOUTSTATUS = 3 AND Tb_MGT_BASTRPC.BASTOUTSTATUS = 3 AND Tb_MGT_BASTRPC.BASTOUTSTATUS = 3 AND Tb_MGT_BASTRPC.RPCType = Insurance Tb_MGT_BASTRPC.BASTOUTSTATUS = 3 AND Tb_MGT_BASTRPC.BASTOUTSTATUS = 3 AND Tb_MGT_BASTRPC.RPCType = Special Case that already register to system with number of row list based on selected show entries number. Note: Status 1 = Draft Status 2 = Submitted Status 3 = Approve - If user input criteria searching on search box, then system will filter BAST number number based on input criteria searching - When user double click on selected row, then display screen will back to Screen 11. View BAST Replacement Pop Up Dialog 3. When click button Next, system will display Screen 17. View BAST Replacement — Replacement Unit and Screen 18. View BAST Replacement — OPL Unit 4. System will display BAST that already created based on |
| | | Tb_MGT_BASTRPC.IdTb_MGT_BASTRPC Output: |
| 18 | Unit based on BAST Out or In (BAST Replacement Unit) | Display BAST Replacement Unit or BAST OPL Unit Update Final BAST Out Input: Operation Name No. 11 Edit BAST Replacement no 1 – 12 Select tab BAST Out Click button Save As Final Process: When user click button Save as Final, system will: |
| | | 1.1 System will display Screen 24. Confirmation Pop Up When Save as Final BAST Replacement If user click button Yes, then system will continue to process submit final BAST Replacement for selected BAST number 1.2 System will save final data BAST Replacement to table Tb_MGT_BASTRPC based on selected BAST number: Status BAST Out → Tb_MGT_BASTRPC.BASTOutStatus = 30 (note: 1 = draft; 2 = Submitted; 30 = Firmed) 1.3 For special case type, system will save data BAST Replacement to table Tb_MGT_MemoRPC with data as below: IsMemo → Tb_MGT_BASTRPC.IsMemo = 30 (note: 1 = draft; 2 = |

Project Code :

TM15404A

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

Submitted; 30= Firmed)

- 1.4 System will update table Tb_MGT_UnitStatusLoc with below data:
 - Tb_MGT_UnitStatusLoc.IdTb_MGT_UnitStatusLoc → automatically
 - Tb_MGT_UnitStatusLoc.IdTb_OPL_Unit =
 Tb_MGT_RegRPC.IdRPCUnit → Where Tb_MGT_BASTRPC.

 IdTb_MGT_RegRPC = IdTb_MGT_RegRPC
 - Tb_MGT_UnitStatusLoc.Status → "Customer"
 - Tb_MGT_UnitStatusLoc.Location = Tb_MGT_BASTRPC.UsageLoc
 - Tb MGT UnitStatusLoc.StartDate = Tb MGT BASTRPC.StartDate
 - Tb_MGT_UnitStatusLoc.EstDate = Tb_MGT_BASTRPC.EstDate
 - Tb_MGT_UnitStatusLoc.EndDate = N/A
 - Tb_MGT_UnitStatusLoc.Transcode = 5
 - 1. BAST Receiving Delivery = 1
 - 2. BAST Return = 2
 - 3. Regular Maintenance = 3
 - 4. Irregular Maintenance = 4
 - 5. BAST Replacement = 5
 - 6. Insurance Claim = 6
 - Tb_MGT_UnitStatusLoc.LineTrans = Tb_MGT_BASTRPC.
 IdTb_MGT_BASTRPC
 - Tb_MGT_UnitStatusLoc.LastModifiedDate = Sys.CurrentDate
 - Tb_MGT_UnitStatusLoc.UpdateBy = Sys.CurrentUser
- 1.5 System will update table Tb_MGT_Current with below data:

Search where Tb MGT Current.IdTb OPL Unit =

Tb MGT UnitStatusLoc.IdTb OPL Unit

- Tb_MGT_Current.IdAgreement = Tb_MGT_RegRPC.IdOPLAgreement → Where Tb_MGT_BASTRPC. IdTb_MGT_RegRPC = IdTb_MGT_RegRPC
- Tb_MGT_Current.IdReplacingUnit = Tb_MGT_RegRPC.IdOPLUnit
 → Where Tb_MGT_BASTRPC. IdTb_MGT_RegRPC = IdTb_MGT_RegRPC
- Tb_MGT_Current.ReplacingPLNo = Tb_MGT_RegRPC.OPLPoliceNo
 → Where Tb_MGT_BASTRPC. IdTb_MGT_RegRPC = IdTb_MGT_RegRPC
- Tb_MGT_ Current.RPCType = Tb_MGT_BASTRPC.RPCType
- Tb_MGT_ Current.IdTb_MGT_UnitStatusLoc =
 Tb_MGT_UnitStatusLoc.IdTb_MGT_UnitStatusLoc
- 1.6 When Save as Final button is clicked, System will add a new Log of Create BAST action to Tb_MGT_BASTRPC_History. Data which should be inserted are:

| Field Name | Value |
|-------------|----------------------|
| ProcessId | NewGUID |
| OriginalId | Tb_MGT_BASTRPC.IdTb_ |
| _ | MGT_BASTRPC |
| CreatedDate | Sys.CurrentDate |
| CreatedBy | Sys.CurrentUser |
| Action | Save as Final |

1.7 History Data will be stored in the table Tb_MGT_BASTRPC_History and Tb_ MGT_ BASTRPC_History_Dtl where Tb_MGT_ BASTRPC_History_Dtl is Tb_MGT_ BASTRPC added Tb_MGT_ BASTRPC_History.IdTb_MGT_ BASTRPC_History as a foreign key

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

B. Update Final BAST In

Input:

- 1. Operation Name No. 11 Edit BAST Replacement no 1 13
- 2. Select tab BAST In
- 3. Click button Save As Final

Process:

- 1. When user click button Save as Final, system will:
 - 1.1 System will display Screen 24. Confirmation Pop Up When Save as Final BAST Replacement
 - If user click button Yes, then system will continue to process submit final BAST Replacement for selected BAST number
 - 1.2 System will save final data BAST Replacement to table

Tb_MGT_BASTRPC based on selected BAST number:

- Status BAST In → Tb_MGT_BASTRPC.BASTInStatus = 30 (note:
 1= draft; 2= Submit; 30=Firmed)
- 1.3 System will update table Tb_MGT_UnitStatusLoc with below data:
 - Tb_MGT_UnitStatusLoc.IdTb_MGT_UnitStatusLoc → automatically
 - Tb_MGT_UnitStatusLoc.IdTb_OPL_Unit =
 Tb_MGT_RegRPC.IdRPCUnit → Where Tb_MGT_BASTRPC.
 IdTb_MGT_RegRPC = IdTb_MGT_RegRPC
 - Tb_MGT_UnitStatusLoc.Status → "Return"
 - Tb_MGT_UnitStatusLoc.Location = Tb_MGT_BASTRPC.UsageLoc
 - Tb_MGT_UnitStatusLoc.StartDate = Tb_MGT_BASTRPC.StartDate
 - Tb_MGT_UnitStatusLoc.EstDate = Tb_MGT_BASTRPC.EstDate
 - Tb_MGT_UnitStatusLoc.EndDate = Tb_MGT_BASTRPC.EndDate
 - Tb_MGT_UnitStatusLoc.Transcode = 5Note:
 - 1. BAST Receiving Delivery = 1
 - 2. BAST Return = 2
 - 3. Regular Maintenance = 3
 - 4. Irregular Maintenance = 4
 - 5. BAST Replacement = 5
 - 6. Insurance Claim = 6
 - Tb_MGT_UnitStatusLoc.LineTrans = Tb_MGT_BASTRPC.
 IdTb_MGT_BASTRPC
 - Tb_MGT_UnitStatusLoc.LastModifiedDate = Sys.CurrentDate
 - Tb_MGT_UnitStatusLoc.UpdateBy = Sys.CurrentUser
- 1.4 System will update table Tb_MGT_Current with below data:

Search where Tb_MGT_Current.IdTb_OPL_Unit =

Tb_MGT_UnitStatusLoc.IdTb_OPL_Unit

- Tb_MGT_Current.IdAgreement =
 Tb_MGT_RegRPC.IdOPLAgreement → Where Tb_MGT_BASTRPC.

 IdTb_MGT_RegRPC = IdTb_MGT_RegRPC
- Tb_MGT_Current.IdReplacingUnit = N/A
- Tb_MGT_Current.ReplacingPLNo = N/A
- Tb_MGT_ Current.RPCType = N/A
- Tb_MGT_UnitStatusLoc.IdTb_MGT_UnitStatusLoc
- 1.5 When Save as Final button is clicked, System will add a new Log of Create BAST action to Tb_MGT_BASTRPC_History. Data which should be inserted are:

| Project Code : | TM15404A |
|----------------|--|
| Project Name: | Operating Lease Support System Phase-2 |

| | | | Field Name | Value | | |
|----|--------------|---|-----------------------------------|-------------------------------|--------------|--|
| | | | ProcessId | NewGUID | | |
| | | | OriginalId | Tb_MGT_BASTRPC.IdTb_ | | |
| | | | _ | MGT_BASTRPC | | |
| | | | CreatedDate | Sys.CurrentDate | | |
| | | | CreatedBy | Sys.CurrentUser | | |
| | | | Action | Save as Final | | |
| | | | | | | |
| | | 1.6 History Data will be stored in the table Tb_MGT_BASTRPC_History and | | | | |
| | | Tb_ MGT_ BASTRPC_History_Dtl where Tb_MGT_ | | | | |
| | | BASTRPC_History_Dtl is Tb_MGT_ BASTRPC added Tb_MGT_ | | | | |
| | | | BASTRPC _History.IdTb_MG | I_ BASTRPC_History as a for | eign key | |
| | | Output: | | | | |
| | | 1. System will display pop up message: | | | | |
| | | _ | reen 27. Notification Pop (| • | placement | |
| 19 | System error | Process: | | - 1 | | |
| | message | 1. Any | - kind of errors outside of ap | oplication validation or that | which cannot | |
| | 3 | be handled by application such as errors when communication with | | | | |
| | | Database, bugs, overloop, etc will generate error message: | | | | |
| | | "System error. Please contact your administrator" | | | | |
| | | Output: | | | | |
| | | | age with system error messa | age will appear | | |

3.8 Data Structure

Tb_OPL_Unit

| Field Name | Data Type | Length | Source | Remarks | Nullable | Mandatory |
|-------------------|--------------|--------|-------------------------------|--|----------|-----------|
| IdTb_OPL_U nit | integer | n/a | Tb_OPL_Unit.IdTb_ OPL_Unit | Primary Key | No | Yes |
| IdProduct | integer | n/a | Tb_OPL_Unit.IdProduct | Foreign Key | No | Yes |
| PoliceNumbe r | varchar | 10 | Tb_OPL_Unit.Police Number | - If OPL Unit, source : Tb_MGT_BASTSupC ust.PoliceNumber | No | Yes |
| EngineNumb er | varchar | 20 | Tb_OPL_Unit.Engine Number | If OPL Unit, source : Tb_MGT_BASTSupC ust.MachineNumber | No | Yes |
| ChassisNum ber | varchar | 20 | Tb_OPL_Unit.Chassi sNumber | - If OPL Unit, source : Tb_MGT_BASTSupC ust.ChassisNumber | No | Yes |
| Colour | varchar | 20 | Tb_OPL_Unit.Colour | - If OPL Unit, source : Tb_MGT_BASTSupC ust.Colour | No | Yes |
| IsOPL | Boolean | n/a | Tb_OPL_Unit.IsOPL | 1 = OPL Unit 0 = Replacement Unit | No | Yes |
| StartSTNK | Date | n/a | Tb_OPL_Unit.StartS TNK | | No | Yes |
| EndSTNK | Date | n/a | Tb_OPL_Unit.EndST NK | | No | Yes |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| StartKEUR | Date | n/a | Tb_OPL_Unit.StartK EUR | | No | Yes |
|---------------------|--------------|-----|------------------------------------|---|----|-----|
| EndKEUR | Date | n/a | Tb_OPL_Unit.EndKE UR | | No | Yes |
| StartInsuran ce | Date | n/a | Tb_OPL_Unit.StartI nsurance | | No | Yes |
| EndInsuranc e | Date | n/a | Tb_OPL_Unit.EndIn surance | | No | Yes |
| CompanyIns urance | varchar | 50 | Tb_OPL_Unit. CompanyInsurance | | No | Yes |
| InsuranceNu mber | varchar | 50 | Tb_OPL_Unit. InsuranceNumber | | No | Yes |
| CreatedDate | DateTim e | n/a | Tb_OPL_Unit.Create dDate | If OPL Unit, source: Tb_MGT_BASTSupC ust.LastModifiedDat e If Replacement Unit, Source: Tb_MGT_RegRPC.Re gDate | No | Yes |
| CreatedBy | Varchar | 50 | Tb_MGT_UnitStatus Loc.CreatedBy | If OPL Unit, source: Tb_MGT_BASTSupC ust.LastModifiedBy If Replacement Unit, Source: Tb_MGT_RegRPC.Cr eatedBy | No | Yes |

Tb_MGT_RegRPC

| Field Name | Data Type | Length | Source | Remarks | Nullable | Mandatory |
|---------------------|--------------|--------|-----------------------------------|-------------|----------|-----------|
| IdTb_MGT_R egRPC | integer | n/a | Tb_MGT_RegRPC. IdTb_MGT_RegRPC | Primary key | No | Yes |
| RegNo | varchar | 20 | Tb_MGT_RegRPC.R egNo | Unique key | No | Yes |
| IdBranch | varchar | 20 | Tb_MGT_RegRPC.Id Branch | Foreign key | No | Yes |
| IdOPLAgree ment | integer | n/a | OPLAgreement.IdOP LAgreement | Foreign key | No | Yes |
| IdRPCUnit | integer | n/a | Tb_OPL_Unit. IdTb_OPL_Unit | Foreign key | No | Yes |
| RPCPoliceNo | varchar | 20 | Tb_MGT_RegRPC.R PCPoliceNo | | No | Yes |
| AgreementN umber | varchar | 50 | Tb_MGT_RegRPC.A greementNumber | | No | Yes |
| IdOPLUnit | integer | n/a | Tb_OPL_Unit. IdTb_OPL_Unit | Foreign key | No | Yes |
| OPLPoliceNo | varchar | 20 | Tb_MGT_RegRPC.O PLPoliceNo | | No | Yes |
| IsActive | Boolean | n/a | Tb_MGT_RegRPC.Is Active | | No | Yes |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| IsCreatabe | Boolean | n/a | Tb_MGT_RegRPC.Is Creatable | | |
|----------------------|--------------|-----|---------------------------------|----|-----|
| RegDate | DateTim e | n/a | Tb_MGT_RegRPC.R egDate | No | Yes |
| CreatedBy | Varchar | 50 | Tb_MGT_RegRPC.Cr eatedBy | No | Yes |
| LastModified Date | DateTim e | n/a | Tb_MGT_RegRPC.La stModifiedDate | No | Yes |
| LastModified By | Varchar | 50 | Tb_MGT_RegRPC.Cr eatedBy | No | Yes |
| IsDelete | Boolean | n/a | Tb_MGT_RegRPC.Is Delete | No | Yes |
| RemarkSys | varchar | 100 | Tb_MGT_RegRPC.R emarkSys | No | Yes |

Tb_MGT_BASTRPC

| I D_IVIG I _BA | | | | | | |
|----------------------|--------------|--------|-----------------------------------|---|----------|-----------|
| Field Name | Data Type | Length | Source | Remarks | Nullable | Mandatory |
| IdTb_MGT_B ASTRPC | integer | n/a | Tb_MGT_BASTRPC. IdTb_MGT_BASTRP C | Primary key | No | Yes |
| BAST Number | varchar | 50 | Tb_MGT_BASTRPC. BASTNumber | Unique key | No | Yes |
| BASTType | integer | n/a | Tb_MGT_BASTRPC. BASTType | 1 = BAST Replacement Unit 2 = BAST OPL Unit | No | Yes |
| IdTb_MGT_R egRPC | integer | n/a | Tb_MGT_RegRPC. IdTb_MGT_RegRPC | Foreign key | No | Yes |
| RPCType | varchar | 15 | Tb_MGT_BASTRPC. RPCType | Insurance, Special Case, General Repair | No | Yes |
| BASTOutDat e | Date | n/a | Tb_MGT_BASTRPC. BASTOutDate | Format display on screen: MM/dd/yyyy | No | Yes |
| BASTInDate | Date | n/a | Tb_MGT_BASTRPC. BASTInDate | Format display on screen: MM/dd/yyyy | No | Yes |
| StartDate | Date | n/a | Tb_MGT_BASTRPC. StartDate | Format display on screen: MM/dd/yyyy | No | Yes |
| EstDate | Date | n/a | Tb_MGT_BASTRPC. EstDate | Format display on screen: MM/dd/yyyy | No | Yes |
| EndDate | Date | n/a | Tb_MGT_BASTRPC. EndDate | Format display on screen: MM/dd/yyyy | No | Yes |
| BASTOutSta tus | integer | n/a | Tb_MGT_BASTRPC. BASTOutStatus | 1 = Draft (BAST already created but has not been submited) 2 = Submit (BAST already submitted) | No | Yes |
| BASTInStatu s | integer | n/a | Tb_MGT_BASTRPC. BASTInStatus | 1 = Draft (BAST already created but has not been submited) 2 = Submit (BAST already submitted) | No | Yes |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| KMOut | decimal | 5,0 | Tb_MGT_BASTRPC. KMOut | Yes | No |
|----------------------|--------------|-----|----------------------------------|-----|-----|
| KMIn | decimal | 5,0 | Tb_MGT_BASTRPC. KMIn | Yes | No |
| FuelOut | varchar | 5 | Tb_MGT_BASTRPC. FuelOut | Yes | No |
| FuelIn | varchar | 5 | Tb_MGT_BASTRPC. FuelIn | Yes | No |
| DriverOut | varchar | 15 | Tb_MGT_BASTRPC. DriverOut | Yes | No |
| DriverIn | varchar | 15 | Tb_MGT_BASTRPC. DriverIn | Yes | No |
| ObseverOut | varchar | 15 | Tb_MGT_BASTRPC. ObserverOut | Yes | No |
| ObseverIn | varchar | 15 | Tb_MGT_BASTRPC. ObserverIn | Yes | No |
| BranchOut | varchar | 10 | Tb_MGT_BASTRPC. BranchOut | Yes | No |
| BranchIn | varchar | 10 | Tb_MGT_BASTRPC. BranchIn | Yes | No |
| UsageLoc | varchar | 30 | Tb_MGT_BASTRPC. UsageLoc | No | Yes |
| DamageLoc | varchar | 30 | Tb_MGT_BASTRPC. DamageLoc | No | Yes |
| ReturnLoc | varchar | 30 | Tb_MGT_BASTRPC. ReturnLoc | No | Yes |
| CreatedBy | varchar | 50 | Tb_MGT_BASTRPC. CreatedBy | No | Yes |
| CreatedDate | DateTim e | n/a | Tb_MGT_BASTRPC. CreatedDate | No | Yes |
| LastModified Date | DateTim e | 50 | Tb_MGT_BASTRPC. LastModifiedDate | No | Yes |
| LastModified By | varchar | n/a | Tb_MGT_BASTRPC. LastModifiedBy | No | Yes |
| IsDelete | Boolean | n/a | Tb_MGT_BASTRPC.I sDelete | No | Yes |
| RemarkSys | varchar | 100 | Tb_MGT_BASTRPC. RemarkSys | No | Yes |

Tb_MGT_BASTRPCDtI

| Field Name | Data Type | Length | Source Remarks | | Nullable | Mandatory |
|-------------------------|--------------|--------|---------------------------------------|----------|----------|-----------|
| IdTb_MGT_B ASTRPCDtI | integer | n/a | Tb_MGT_BASTRPCD | | No | Yes |
| IdTb_MGT_B ASTRPC | integer | n/a | Tb_MGT_BASTRPCD tl. IdTb_MGT_BASTRP C | | No | Yes |
| Description | varchar | 50 | Tb_MGT_BASTRPCD tl.Description | | Yes | No |
| BASTOutVal | integer | n/a | Tb_MGT_BASTRPCD | 1 = Good | Yes | No |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| ue | | | tl. BASTOutValue | 2 = Damage 3 = Missing 4 = Not Exist | | |
|----------------------|--------------|-----|--|--|----|-----|
| BASTInValu e | integer | n/a | Tb_MGT_BASTRPCD | | | |
| CreatedBy | varchar | 50 | Tb_MGT_BASTRPCD tl.CreatedBy | | No | Yes |
| CreatedDate | DateTim e | n/a | Tb_MGT_BASTRPCD tl.CreatedDate | | No | Yes |
| LastModified Date | DateTim e | 50 | Tb_MGT_BASTRPCD tl.LastModifiedDate | | No | Yes |
| LastModified By | varchar | n/a | Tb_MGT_BASTRPCD tl.LastModifiedBy | | No | Yes |
| IsDelete | Boolean | n/a | Tb_MGT_BASTRPCD tl.lsDelete | | No | Yes |
| RemarkSys | varchar | 100 | Tb_MGT_BASTRPCD tl.RemarkSys | | No | Yes |

Tb_MGT_UnitStatusLoc

| Field Name | Data Type | Length | Source | rce Remarks | | Mandatory |
|--------------------------------|--------------|--------|--|--|-----|-----------|
| IdTb_MGT_ UnitStatusLo c | Integer | n/a | Tb_MGT_UnitStatus Loc.Id_Tb_UnitStat usLoc | c.Id_Tb_UnitStat | | Yes |
| IdTb_OPL_U nit | Integer | n/a | Tb_OPL_Unit.IdTb_ OPL_Unit | Foreign key | No | Yes |
| Status | Varchar | 20 | Tb_MGT_UnitStatus Loc.Status | | No | Yes |
| Location | Varchar | 30 | Tb_MGT_UnitStatus Loc.Location | | No | Yes |
| StartDate | Date | n/a | Tb_MGT_UnitStatus Loc.StartDate | Format display on screen: MM/dd/yyyy | No | Yes |
| EstDate | Date | n/a | Tb_MGT_UnitStatus Loc.EstDate | Format display on screen: MM/dd/yyyy | Yes | No |
| EndDate | Date | n/a | Tb_MGT_UnitStatus Loc.EndDate | Format display on screen: MM/dd/yyyy | Yes | No |
| TransCode | Integer | n/a | Tb_MGT_UnitStatus Loc.TransCode | Transaction Code: 1. BAST Receiving Delivery = 1 2. BAST Return = 2 3. Regular Maintenance = 3 4. Irregular Maintenance = 4 5. BAST Replacement = 5 6. Insurance Claim = 6 | No | Yes |
| LineTrans | Integer | n/a | Tb_MGT_UnitStatus Loc.LineTrans | | No | Yes |
| LastModified Date | DateTim e | n/a | Tb_MGT_UnitStatus Loc.LastModifiedDat e | | No | Yes |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| LastModified | Varchar | 50 | Tb_MGT_UnitStatus | | No | Yes |
|--------------|---------|-----|--------------------|--|----|-----|
| Ву | | | Loc.LastModifiedBy | | | |
| IsDelete | Boolean | n/a | Tb_MGT_UnitStatus | | No | Yes |
| | | | Loc.IsDelete | | | |
| RemarkSys | varchar | 100 | Tb_MGT_UnitStatus | | No | Yes |
| | | | Loc.RemarkSys | | | |

Tb_MGT_Current

| Ib_MGI_current | | | | | | |
|--------------------------------|--------------|--------|--|---|----------|-----------|
| Field Name | Data Type | Length | Source Remarks | | Nullable | Mandatory |
| IdTb_MGT_C urrent | Integer | n/a | Tb_MGT_Current. IdTb_MGT_Current Primary key | | No | Yes |
| IdTb_OPL_U nit | integer | n/a | Tb_OPL_Unit. IdTb_OPL_Unit | Foreign Key | No | Yes |
| IdAgreemen t | integer | n/a | OPLAgreement. IdOPLAgreement | Foreign Key | No | Yes |
| IdReplacing Unit | integer | n/a | Tb_MGT_RegRPC.Id UnitOPL Foreign Key | | No | Yes |
| ReplacingPL No | varchar | 10 | Tb_MGT_Current.Re placingPLNo | | No | Yes |
| RPCType | varchar | 15 | Tb_MGT_ Current.RPCType | | No | Yes |
| IdTb_MGT_ UnitStatusLo c | integer | n/a | Tb_MGT_UnitStatus Loc.Id_Tb_UnitStat usLoc | Tb_MGT_UnitStatus Loc.Id_Tb_UnitStat Foreign Key | | Yes |
| LastModified Date | DateTim e | n/a | Tb_MGT_UnitStatus Loc.LastModifiedDat e | | No | Yes |
| LastModified By | Varchar | 50 | Tb_MGT_UnitStatus Loc.LastModifiedBy | | No | Yes |
| IsDelete | Boolean | n/a | Tb_MGT_Current.Is Delete No | | No | Yes |
| RemarkSys | varchar | 100 | Tb_MGT_Current.Re markSys | Tb_MGT_Current.Re | | Yes |


Tb_MGT_Memo

| Field Name | Data Type | Length | Source Remarks | | Nullable | Mandatory |
|----------------------|--------------|--------|----------------------------|--|----------|-----------|
| IdTb_MGT_ Memo | Integer | n/a | Tb_MGT_Memo. | | No | Yes |
| IdTb_MGT_B ASTRPC | integer | n/a | | | No | Yes |
| MemoNo | varchar | 50 | Tb_MGT_MemoRPC. | | No | Yes |
| MemoDate | Date | n/a | Tb_MGT_MemoRPC. MemoDate | | No | Yes |
| Descripton | varchar | 50 | Tb_MGT_MemoRPC. Descripton | | No | Yes |
| IsMemo | bit | n/a | Tb_MGT_memoRPC. IsMemo | | No | Yes |
| CreatedBy | varchar | 50 | Tb_MGT_memoRPC. CreatedBy | | No | Yes |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| CreatedDate | DateTim e | n/a | Tb_MGT_memoRPC. No Yes CreatedDate | | Yes | |
|----------------------|--------------|-----|-------------------------------------|--|-----|-----|
| LastModified Date | DateTim e | 50 | Tb_MGT_memoRPC. No LastModifiedDate | | Yes | |
| UpdateBy | varchar | n/a | Tb_MGT_memoRPC. No UpdateBy | | Yes | |
| IsDelete | Boolean | n/a | Tb_MGT_memoRPC. No IsDelete | | No | Yes |
| RemarkSys | varchar | 100 | Tb_MGT_memoRPC. No RemarkSys | | Yes | |

3.9 Screen Item List



| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

RPT.AD.1.3 BAST OPL Unit and RPT.AD.1.4 BAST Replacement Unit

| No. | Content | Description | Source | Remarks |
|-----|---|--|---|---|
| 1 | Logo | Logo PT. DSF and default address | Static | |
| 2 | Berita Acara Serah terima Kendaraan | Label Default | Static | |
| 3 | No Form | BAST Replacement Unit Number BAST OPL Unit | Tb_MGT_RegRPC.B ASTNumber Tb_MGT_RegRPC.B | |
| | | Number | ASTNumber | |
| 4 | Status Unit | Status of unit, whether Replacement Unit or OPL unit | Tb_MGT_BASTRPC. BASTType | If Tb_MGT_BASTRPC.BASTType = 1 then value = "Replacement Unit" |
| | | | | If Tb_MGT_BASTRPC.BASTType = 1 then value = "Leased Unit" |
| 5 | Nama Pemakai Kendaraan | PIC Customer | Tb_MGT_BASTRPC. PIC | |
| 6 | Nama Perusahaan | Customer Company Name | OPLAgreement.Cust omerName | where Tb_MGT_RegRPC.IdOPLAgreement = OPLAgreement.IdOPLAgreement |
| 7 | Alamat | Customer Company Address | OPLAgreement.Addr ess | where Tb_MGT_RegRPC.IdOPLAgreement = OPLAgreement.IdOPLAgreement |
| 8 | No Telepon | Telp Number Customer Company | Tb_MGT_BASTRPC. Telp | |
| 9 | Agreement Number | Agreement Number Customer | Tb_MGT_RegRPC.A greementNumber | |
| 10 | No. Polisi | Police Number Replacement Unit | Tb_OPL_Unit.Police No | where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct |
| | | Police Number OPL Unit | Tb_OPL_Unit.Police No | where Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct |
| 11 | Merk/Tipe Kendaraan | Merk/Vehicle Type of Replacement Unit | Product.ModelName | where Tb_MGT_RegRPC.IdRPCUnit = Product.IdProduct |
| | | Merk/Vehicle Type of OPL Unit | Product.ModelName | where Tb_MGT_RegRPC.IdOPLUnit = Product.IdProduct |
| 12 | Tahun | Model Year of Replacement Unit | Product.ModelYear | where Tb_MGT_RegRPC.IdRPCUnit = Product.IdProduct |
| | | Model Year of OPL unit | Product.ModelYear | where Tb_MGT_RegRPC.IdOPLUnit = Product.IdProduct |
| 13 | Warna | Colour of Replacement Unit | Tb_OPL_Unit.Colour | where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct |
| | | Colour of OPL Unit | Tb_OPL_Unit.Colour | where Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct |
| 14 | No. Rangka | Colour of Replacement Unit | Tb_OPL_Unit.Chassi sNo | where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct |
| | | Colour of OPL Unit | Tb_OPL_Unit.Chassi sNo | where Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| 15 | No. Mesin | Machine No of Replacement Unit | Tb_OPL_Unit.Machi neNo | where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct |
|-------|---------------------------|---------------------------------------|---|--|
| | | Machine No of OPL Unit | Tb_OPL_Unit.Machi | where Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct |
| 16 | Tanggal STNK/KEUR | STNK and KEUR Start Date | Tb_OPL_Unit.EndST NK/ Tb_OPL_Unit.EndKE UR | where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct / where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct Format display on report: MM/dd/yyyy |
| | | STNK and KEUR Start | Th ODL Unit StartS | 3333 |
| | | Date | Tb_OPL_Unit.StartS TNK/ Tb_OPL_Unit.StartK EUR | where Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct / where Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct |
| | | | | Format display on report: MM/dd/yyyy |
| 17 | Kendaraan yang diganti | OPL unit (BAST Replacement Unit) | Tb_MGT_RegRPC.Id OPLUnit | where Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct / where Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct |
| | | Replacement Unit unit (BAST OPL Unit) | Tb_MGT_RegRPC.Id RPCUnit | where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct / where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct |
| Seral | n Terima | | | |
| 18 | Tanggal | Date BAST Out | Tb_MGT_BASTRPC. DateOut | |
| 19 | Kilometer | KM Out | Tb_MGT_ BASTRPC.KMOut | |
| 20 | Fuel | Fuel Out | Tb_MGT_ BASTRPC.FuelOut | |
| 21 | Nama Pengemudi | Driver Name Out | Tb_MGT_ BASTRPC.DriverOut | |
| 22 | Nama Pemeriksa | Observer Name Out | Tb_MGT_ BASTRPC.Observer Out | |
| 23 | Cabang/Pool | Branch/Poll Out | Tb_MGT_ BASTRPC.BranchOu t | |
| 24 | Ket | Remark Out | Tb_MGT_ BASTRPC.RemarkO ut | |
| Seral | n Kembali | • | | |
| 25 | Tanggal | Date BAST In | Tb_MGT_BASTRPC. DateIn | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| 26 | Kilometer | KM In | Tb_MGT_ BASTRPC.KMIn | |
|-----|------------------------------------|------------------|---|--|
| 27 | Fuel | Fuel In | Tb_MGT_ BASTRPC.FuelIn | |
| 28 | Nama Pengemudi | Driver Name In | Tb_MGT_ BASTRPC.DriverIn | |
| 29 | Nama Pemeriksa | Observer Name In | Tb_MGT_ BASTRPC.ObserverI n | |
| 30 | Cabang/Pool | Branch/Poll In | Tb_MGT_ BASTRPC.BranchIn | |
| 31 | Ket | Remark In | Tb_MGT_ BASTRPC.RemarkIn | |
| Com | ponent Unit | | | |
| 32 | No | Running Number | Automatically generate | |
| 33 | Nama Komponen | Component Name | Tb_MGT_ BASTRPCDtl.Descrip tion | |
| 34 | Keluar | Condition Out | Tb_MGT_ BASTRPCDtI.BASTO utStatus = 1 | <pre>value: 1: Good (B), 2: Damage (R), 3: Missing (H), 4: Not Exist (T) Where Tb_MGT_BASTRPCDtl.DtlStatus = 1</pre> |
| 35 | Masuk | Condition In | Tb_MGT_ BASTRPCDtI.BASTO utStatus = 2 | value: 1: Good (B), 2: Damage (R), 3: Missing (H), 4: Not Exist (T) Where Tb_MGT_BASTRPCDtl.DtlStatus = 2 |
| 36 | Kondisi Cat/Body Saat Keluar | Remark Out | Tb_MGT_ BASTRPCDtI.Remar kOut2 | Where Tb_MGT_BASTRPCDtl.DtlStatus = 1 |
| 37 | Kondisi Cat/Body Saat Masuk | Remark In | Tb_MGT_ BASTRPCDtI.Remar kIn2 | Where Tb_MGT_BASTRPCDtl.DtlStatus = 2 |
| 38 | Label | Label Default | Static | Default Value : B = Baik, R = Rusak, H = Hilang, T = Tidak Ada 1. Lembar Putih untuk DSF 2. Lembar Merah untuk Costumer |
| 39 | Image | Image unit | Static | |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| 1 | Kepada: Mr/s |
|-----|--|
| 2 | Dari : Asset Management Operating Lease Dept. |
| 4 [| Tanggal: |
| 5 [| Perihal: Permohonan Peminjaman Replacement Car Untuk Kondisi Khusus |
| | Dengan hormat, |
| 6 | Mohon agar dapat disetujui untuk memberikan pinjaman unit replacement car berikut ini: Nomor Polisi: |
| 7 | > Nomor Polisi : Type/Jenis Kendaraan : |
| 1 | Periode Peminjaman : 8 |
| 9 | Kepada customer operating lease berikut ini: Nama Customer : Nomor Polisi : Type/Jenis Kendaraan : 11 Dengan alasan sebagai berikut: |
| | \ |
| 12 | |
| | Demikian permohonan ini disampaikan, terimakasih atas kerjasamanya |
| | Diajukan oleh, Diketahui oleh, Disetujui oleh, |
| | |

Memo Replacement Unit


| No. | Content | Description | Source | Remarks |
|-----|--------------|----------------|-------------------------------------|---|
| 1 | Kepada: Mr/s | Memo recipient | Tb_SYS_ApprovalPa thDtl.RoleName | Where Tb_SYS_ApprovalPathDtl.ApprovalL evel = Approve AND Tb_SYS_ApprovalPathDtl.RoleName Level = highest |
| 2 | Dari: | Memo sender | Static | Asset Management Operating Lease Dept |
| 3 | No: | Number Memo | Tb_MGT_MemoRPC. MemoNo | Where Tb_MGT_MemoRPC.IdTb_MGT_BAS TRPC = Tb_MGT_BASTRPC.IdTb_MGT_BAST RPC |
| 4 | Tanggal: | Memo Date | Tb_MGT_MemoRPC. MemoDate | Where Tb_MGT_MemoRPC.IdTb_MGT_BAS TRPC = |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

| | | | | Tb_MGT_BASTRPC.IdTb_MGT_BAST RPC |
|----|---------------------------------------|-----------------------------------|---|---|
| 5 | Perihal: | Regarding | Tb_MGT_MemoRPC. Descripton | Where Tb_MGT_MemoRPC.IdTb_MGT_BAS TRPC = Tb_MGT_BASTRPC.IdTb_MGT_BAST RPC |
| 6 | Nomor Polisi: | Police Number Replacement Unit | Tb_OPL_Unit.Police | where Tb_MGT_RegRPC.IdRPCUnit = Tb_OPL_Unit.IdProduct |
| 7 | Type/Jenis Kendaraan: | Model replacement unit | Product.ModelName | where Tb_MGT_RegRPC.IdRPCUnit = Product.IdProduct |
| 8 | Periode Peminjaman: | Usage Period of replacement unit | Tb_MGT_UnitStatus Loc.StartDate - Tb_MGT_UnitStatus Loc.Estimation | Format display on report: MM/dd/yyyy |
| 9 | Nama Customer: | Customer Name | OPLAgreement.Cust omerName | where Tb_MGT_RegRPC.IdOPLAgreement = OPLAgreement.IdOPLAgreement |
| 10 | Nomor Polisi | Police Number OPL Unit | Tb_OPL_Unit.Police | where Tb_MGT_RegRPC.IdOPLUnit = Tb_OPL_Unit.IdProduct |
| 11 | Type/Jenis Kendaraan | Model OPL Unit | Product.ModelName | where Tb_MGT_RegRPC.IdOPLUnit = Product.IdProduct |
| 12 | Dengan alas an sebagai berikut: | Reason of memo | Tb_MGT_MemoRPC. Descripton | Where Tb_MGT_MemoRPC.IdTb_MGT_BAS TRPC = Tb_MGT_BASTRPC.IdTb_MGT_BAST RPC |

| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

3.10 Entity Relationship Diagram



| Project Code : | TM15404A |
|----------------|--|
| Project Name : | Operating Lease Support System Phase-2 |

APPENDIX

Configuration Access for Monitoring Unit Preparation:

| User | DSF | 3 | | F | unction | s | |
|-----------------------|--------|--------------|--------|------|---------|------------|--------------|
| Osei | Office | Display List | Create | Edit | View | Print Form | Print Report |
| | One | V | | | V | | V |
| | Area | | | | | | |
| PIC OPL HO/Branch | All | | | | | | |
| | Area | | | | | | |
| | All | | | | | | |
| | One | V | | | V | | V |
| Head of Branch | Area | | | | | | |
| | All | | | | | | |
| | One | | | | | | |
| Head of Department | Area | | | | | | |
| | All | V | | | V | | V |
| | One | | | | | | |
| Regional Manager | Area | V | | | V | | V |
| | All | | | | | | |
| | One | | | | | | |
| Advisor | Area | | | | | | |
| | All | V | | | V | | V |
| | One | | | | | | |
| Director | Area | | | | | | |
| | All | V | | | V | | V |
| | One | | | | | | |
| President Director | Area | | | | | | |
| | All | V | | | V | | V |
| | One | | | | | | |
| Shareholder's Meeting | Area | | | | | | |
| _ | All | V | | | V | | V |

Legend:

V = Have the access