



AIRLOG Generator

Table of Contents

Table of Contents.....	1
Product Overview.....	1
Getting Started.....	2
Installing as A Service.....	2
Running as a Standalone Application.....	5
User Interface	6
System Settings	7
Station Configuration	9
Scheduled Tasks.....	11



AIRLOG Generator

Product Overview

AIRLOG Generator was written to allow users to generate air log files from their WideOrbit Automation for Radio Central Server. AIRLOG Generator allows users to generate air log files on demand or based on a user-defined schedule. This application was designed to be run either as a service or a standalone application. AIRLOG Generator provides a browser-based user interface with a built-in web host. As a service, this application will run scheduled tasks based on the individual station configuration json files. It is possible to manually create these files if UI access is not available or use the UI to create the schedule.

Application Disclaimer: This tool was written with the help of Artificial Intelligence.

Getting Started

AIRLOG Generator can be installed as a service or run as a standalone application. The provided software package contains AIRLOGGeneratorInstaller.exe that is used to install a service in Windows. The service will be starting with AIRLOGGenerator.exe, the same file used to operate the application in a standalone manner. The application is designed to be self-contained and will operate from any location where the software package is placed.

Installing as A Service

In the provided software package, locate the AirlogGeneratorInstaller.exe. Right click on this file and “Run as Administrator”.

- 1) By default, the installer is set to use the Local Account for the service
 - a. This is the account that will be writing the air logs to disk after generation
 - b. It is possible to set a service account if needed

Service Credentials

☐ Local System Account (default)

☒ Custom Account

Username:

Password:

Test Credentials



AIRLOG Generator

- 2) By default, the service will be installed as “Airlog Generator Service”. It is possible to set this service name to something different if desired.

Service Info

Display Name: Airlog Generator Service

Description: Generates and manages Airlog data.

- 3) Click on the Install Button

AirlogGenerator Service Setup

Service Status: Not Installed Refresh

Install Service Uninstall Service Start Service Stop Service Restart Service

Service Info

Display Name: Airlog Generator Service

Description: Generates and manages Airlog data.

Service Credentials

☒ Local System Account (default)

☐ Custom Account

Username:

Password:

Test Credentials

Crash Recovery Settings


Restart Delay (seconds):

View Service Log


- 4) When the installation is complete. The integrated log window will display a message of success.



AIRLOG Generator




5) After the service is installed, start the service.





AIRLOG Generator

6) The service can be verified in the Services window.




Running as a Standalone Application

In the provided software package locate the AirlogGenerator.exe file. Right click on the file and “Run as Administrator”.

- 1) When the application is started, a dialogue box regarding access to network connections may be displayed. This allows the application to access the local network.



AIRLOG Generator



- 2) While the application is running, a terminal window will be displayed. The terminal window must remain open for the application to run.

```
C:\UTILITIES\AirlogGenerator-1.0.5\AirlogGenerator.exe
{"maxSizeMb": 10
}
}
[CONFIG] Parsed values:
WebPort = 8030
DefaultServerIp = 127.0.0.1
SchedulerIntervalMinutes = 1
Logging.Level = INFO
Logging.RetentionDays = 14
Logging.MaxSizeMb = 10
[CONFIG] Loading system.json from: C:\UTILITIES\AirlogGenerator-1.0.5\CONFIG\system.json
[CONFIG] Raw JSON loaded:
{
  "webPort": 8030,
  "defaultServerIp": "127.0.0.1",
  "schedulerIntervalMinutes": 1,
  "logging": {
    "level": "INFO",
    "retentionDays": 14,
    "maxSizeMb": 10
  }
}
}
[CONFIG] Parsed values:
WebPort = 8030
DefaultServerIp = 127.0.0.1
SchedulerIntervalMinutes = 1
Logging.Level = INFO
Logging.RetentionDays = 14
Logging.MaxSizeMb = 10
```



AIRLOG Generator

User Interface

The user interface can be accessed using a web browser. By default, the web service starts on port 8030. The port that is used can be modified as part of the system configuration.

System Settings

- 1) Open a web browser. Enter the IP address of the workstation where the application is running followed by a colon (:) and the configured port number (8030 by default). 127.0.0.1 or localhost can be used if accessing the interface from the same server where the application is running. (EX: <http://127.0.0.1:8030>)



- 2) Across the top of the screen:
 - a. The application version number will be displayed
 - b. When connected to a server, the Central Server database version will be displayed.
 - c. The WO AFR Software version will be displayed
 - d. A Link to this manual will be available.



- 3) Enter in the IP address of the Central Server where the air logs will be generated from.



AIRLOG Generator

- a. This address will be saved to the station configuration files for the radio stations associated with the Central Server.
- b. It is possible to install AIRLOG Generator in a centralized location and connect to different Central Servers*
 - * AIRLOG Generator connects to the Central Server database on port 5432. To use AIRLOG Generator from a remote location, it may be necessary to allow access to the port through the system firewall.
- c. Clicking connect will populate the container on the right side of the screen with a list of available radio stations from that server.

Central Server Connection

Central Server IP:

- 4) Web Port: defines the port used to access the User Interface. The default port is 8030. If this port is changed, it will require a restart of the service for the change to take effect.
- 5) Scheduler Interval: Define an interval will use to check for scheduled tasks.
 - a. Setting an interval of 0 will keep the application into “Continuius Mode”. In this mode the service will check for tasks every second.
 - b. Setting an interval value between 1 –120 minutes, the service will check for tasks at that interval.

System Settings

Web Port: Scheduler Interval (minutes):

- 6) AIRLOG Generator writes comprehensive application logs. A new log will be written to the LOG folder inside the application location. A new log will start each day.
 - a. Log Level: Sets the level of logging that will be maintained. INFO is the default setting.
 - b. Retention Days: Sets the number of days of logs will be retained. The default value is 14 days
 - c. Max Log Size (MB): This sets the maximum log size. If a given day exceeds the maximum size, it will roll into a new log.
- 7) Application Log: Displays an active log window.



AIRLOG Generator

- 8) Save System Settings: Will write all setting changes to a system.json file located in a CONFIG folder within the application folder. Any changes made to the configuration will require a restart of the service after saving.
- 9) Station Configuration: When connected to a Central Server, this section will display a list of available radio stations associated with the connected Central Server.

Logging

Log Level: Retention Days: Max Log Size (MB):

Application Log

```
[2026-01-08T03:18:11.766Z] [INFO] Browser detected: Mozilla/5.0 (Windows NT 10.0; Win64; x64) AppleWebKit/537.36 (KHTML, like Gecko) Chrome/143.0.0.0 Safari/537.36 Edg/143.0.0.0
[2026-01-08T03:18:11.767Z] [INFO] Folder picker not supported in this browser. Manual path entry only.
[2026-01-08T03:18:11.791Z] [INFO] AIRLOG GENERATOR UI loaded.
Log stream connected
Log stream connected
2026-01-07 22:18:11 [INFO] [SYSTEM] Status API called.
2026-01-07 22:18:11 [INFO] [SYSTEM] Status API called.
[2026-01-08T03:18:11.915Z] [SUCCESS] Connected to backend.
2026-01-07 22:18:11 [SUCCESS] [SERVICE] Central server version: 2024.0.36
2026-01-07 22:18:11 [SUCCESS] [SERVICE] Central server version: 2024.0.36
```

Station Configuration

This section will display a list of radio stations associated with the connected Central Server. This initial display will show the radio station name as it is configured in the Central Server as well as a time zone offset that has been configured with the radio station. This section provides the ability to generate air logs on demand or configure a schedule to generate air logs.

- 1) Click on the desired Radio Station

Station Configuration

2024-S1 (Offset 0 Hours from Central Server)

2024-S2 (Offset -3 Hours from Central Server)

2024-S3 (Offset 0 Hours from Central Server)

2024-S4 (Offset 0 Hours from Central Server)

- 2) Timezone Offset: Displays the offset configured on the radio station.
 - a. The offset is NOT configurable from this application.



AIRLOG Generator

- b. Enable: when checked (default) the AIRLOG will be generated with adjusted times based on the offset*
- In earlier version of the WO AFR software times were recorded based on the Central Server local time. This necessitated the need to adjust the time based on this offset. Starting with AFR2024, airtime were recorded in the database based on the offset and further adjustment is not necessary. If running AFR2024 or later uncheck this box to disable the offset adjustments.

2024-S2

Timezone Offset: ☐ Enable Calculation

- 3) On Demand Execution: Allows the user to select one or more dates (only 30 days of logs are available). To select more than one date, hold down the Control Key and click on the desired dates.

On Demand Execution

< **January 2026** >

				1	2	3
4	5	6	7	8	9	10
11	12	13	14	15	16	17
18	19	20	21	22	23	24
25	26	27	28	29	30	31

Query Type:

Destination:

- a. Query Type provides options for the data provided in the air log
- Standard – the standard air log
 - Partner ID – if a playlist (music or traffic) is processed using Partner ID, the artist field will be replaced with the Partner ID
 - Rotator Only – Provides an air log displaying only the Rotators Media Asset ID (MAID).



AIRLOG Generator

- Rotator + MAID – Will display the Rotator ID along with the MAID of the asset that played
- Rotator + Partner ID – Displays the Rotator MAID and the Partner ID
- b. Destination: Set the destination where the AIRLOG will be written.
- c. Multifunction Execution Button: Using the drop down a user will have the ability to set how the air logs will be presented
 - Preview – Will display the selected air log(s) in a preview pane below within the UI
 - Save / Write – will write the air log to the destination entered in the destination box
 - Download – will download a copy of the file to the user's workstation.

Scheduled Tasks

While the service is running (both standalone and system service) allows a user to schedule tasks to be executed. Saving the Station Configuration will write these tasks along with the Host Central Server IP address, and Timezone offset election. While the service is running, the application will review the saved station.json files and execute the scheduled tasks against the Host Address, and Radio Station.

Schedule

Daily

▼

Every

1

days at

12:15 AM

🕒

X

Query Type: Standard

Destinations:

D:\Logs\2024-S2\AIR

X

\\MediaServer\S2\AIR

X

Add Destination

Execute Now

Minutes

▼

Every

15

minutes

X

Query Type: Standard

Destinations:

\\MediaProvider\S2\Recon

X

Add Destination

Execute Now

Add Schedule Entry

Save Station Config

- 1) Add Scheduled Entry: add a scheduled task to be executed
- 2) Mode Dropdown box:



AIRLOG Generator

- a. Daily (Default) – Will be executed based on the configured number of days at the time specified. When executed it will generate logs from “yesterday” going back to the configured number of days.
 - b. Minutes – Executes air log generation based on the configured number of minutes set. This interval can be affected if the Scheduler interval in the system setting is greater than the interval of the scheduled task.
 - c. Hourly - Executes air log generation based on the configured number of hours set. This interval can be affected if the Scheduler interval in the system setting is greater than the interval of the scheduled task.
 - d. Weekly – Scheduled tasks will be executed based on the number of weeks set on the day and time configured. It will generate a daily log for each day in the time frame set.
 - e. Monthly - Scheduled tasks will be executed based on the number of months set on the day and time configured. It will generate a daily log for each day in the time frame set. This setting should not be set higher than 1. Currently, the WO AFR system only retains 30 days of logs.
- 3) Add Destination: Allows the user to add destination(s) will be saved as part of the scheduled task.
- 4) Query type provides for setting the type of data that will be included in the scheduled task:
- i. Standard – the standard air log
 - ii. Partner ID – if a playlist (music or traffic) is processed using Partner ID, the artist field will be replaced with the Partner ID
 - iii. Rotator Only – Provides an air log displaying only the Rotators Media Asset ID (MAID).
 - iv. Rotator + MAID – Will display the Rotator ID along with the MAID of the asset that played
 - v. Rotator + Partner ID – Displays the Rotator MAID and the Partner ID
- 5) Execute Now: Will execute the selected task immediately.
- 6) Save Station Configuration: Will write the schedule tasks to a station.json file. This file will also save host server address and timezone offset election.