

Chapter 4: Processes

- Process Concept
- Process Scheduling
- Operations on Processes
- Cooperating Processes
- Interprocess Communication
- Communication in Client-Server Systems





Process Concept

- An operating system executes a variety of programs:
 - Batch system jobs
 - Time-shared systems user programs or tasks
- Textbook uses the terms job and process almost interchangeably
- Process a program in execution; process execution must progress in sequential fashion
- A process includes:
 - program counter
 - stack
 - data section






Process State

- As a process executes, it changes state
 - new: The process is being created
 - running: Instructions are being executed
 - waiting: The process is waiting for some event to occur
 - ready: The process is waiting to be assigned to a process
 - terminated: The process has finished execution





Diagram of Process State







Process Control Block (PCB)

Information associated with each process

- Process state
- Program counter
- CPU registers
- CPU scheduling information
- Memory-management information
- Accounting information
- I/O status information





Process Control Block (PCB)

process state

process number

program counter

registers

memory limits


list of open files

. . .





CPU Switch From Process to Process








Process Scheduling Queues

- Job queue set of all processes in the system
- Ready queue set of all processes residing in main memory, ready and waiting to execute
- Device queues set of processes waiting for an I/O device
- Process migration between the various queues






Ready Queue And Various I/O Device Queues







Representation of Process Scheduling








Schedulers

- Long-term scheduler (or job scheduler) selects which processes should be brought into the ready queue
- Short-term scheduler (or CPU scheduler) selects which process should be executed next and allocates CPU





Addition of Medium Term Scheduling







Schedulers (Cont.)

- Short-term scheduler is invoked very frequently (milliseconds) ⇒ (must be fast)
- Long-term scheduler is invoked very infrequently (seconds, minutes) ⇒ (may be slow)
- The long-term scheduler controls the degree of multiprogramming
- Processes can be described as either:
 - I/O-bound process spends more time doing I/O than computations, many short CPU bursts
 - CPU-bound process spends more time doing computations; few very long CPU bursts





Context Switch

- When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process
- Context-switch time is overhead; the system does no useful work while switching
- Time dependent on hardware support





Process Creation

- Parent process create children processes, which, in turn create other processes, forming a tree of processes
- Resource sharing
 - Parent and children share all resources
 - Children share subset of parent's resources
 - Parent and child share no resources
- Execution
 - Parent and children execute concurrently
 - Parent waits until children terminate





Process Creation (Cont.)

- Address space
 - Child duplicate of parent
 - Child has a program loaded into it
- UNIX examples
 - fork system call creates new process
 - exec system call used after a fork to replace the process' memory space with a new program






C Program Forking Separate Process

```
#include <stdio.h>
#include <unistd.h>
int main(int argc, char *argv[])
int pid;
    /* fork another process */
    pid = fork():
    if (pid < 0) { /* error occurred */
            fprintf(stderr, "Fork Failed");
            exit(-1);
    else if (pid == 0) { /* child process */
            execlp("/bin/ls","ls",NULL);
    else { /* parent process */
            /* parent will wait for the child to complete */
            wait(NULL);
            printf("Child Complete");
            exit(0);
```



Processes Tree on a UNIX System







Process Termination

- Process executes last statement and asks the operating system to decide it (exit)
 - Output data from child to parent (via wait)
 - Process' resources are deallocated by operating system
- Parent may terminate execution of children processes (abort)
 - Child has exceeded allocated resources
 - Task assigned to child is no longer required
 - If parent is exiting
 - Some operating system do not allow child to continue if its parent terminates
 - All children terminated cascading termination





Cooperating Processes

- Independent process cannot affect or be affected by the execution of another process
- Cooperating process can affect or be affected by the execution of another process
- Advantages of process cooperation
 - Information sharing
 - Computation speed-up
 - Modularity
 - Convenience





Producer-Consumer Problem

- Paradigm for cooperating processes, producer process produces information that is consumed by a consumer process
 - unbounded-buffer places no practical limit on the size of the buffer
 - bounded-buffer assumes that there is a fixed buffer size





Bounded-Buffer – Shared-Memory Solution

```
public interface Buffer
{
    // producers call this method
    public abstract void insert(Object item);
    // consumers call this method
    public abstract Object remove();
}
```





Bounded-Buffer – Shared Memory Solution

```
import java.util.*;
public class BoundedBuffer implements Buffer
       private static final int BUFFER SIZE = 5;
       private int count; // number of items in the buffer
       private int in; // points to the next free position
       private int out; // points to the next full position
       private Object[] buffer;
       public BoundedBuffer() {
             // buffer is initially empty
             count = 0;
             in = 0;
             out = 0:
             buffer = new Object[BUFFER SIZE];
      // producers calls this method
       public void insert(Object item) {
           // Slide 4.24
      // consumers calls this method
       public Object remove() {
           // Figure 4.25
```





Bounded-Buffer - Insert() Method

```
public void insert(Object item) {
  while (count == BUFFER SIZE)
  ; // do nothing -- no free buffers
  // add an item to the buffer
  ++count;
  buffer[in] = item;
  in = (in + 1) % BUFFER SIZE;
```





Bounded Buffer - Remove() Method

```
public Object remove() {
   Object item;
   while (count == 0)
        ; // do nothing -- nothing to consume
   // remove an item from the buffer
   --count;
   item = buffer[out];
   out = (out + 1) % BUFFER SIZE;
   return item;
```





Interprocess Communication (IPC)

- Mechanism for processes to communicate and to synchronize their actions
- Message system processes communicate with each other without resorting to shared variables
- IPC facility provides two operations:
 - **send**(*message*) message size fixed or variable
 - receive(message)
- If P and Q wish to communicate, they need to:
 - establish a communication link between them
 - exchange messages via send/receive
- Implementation of communication link
 - physical (e.g., shared memory, hardware bus)
 - logical (e.g., logical properties)





Implementation Questions

- How are links established?
- Can a link be associated with more than two processes?
- How many links can there be between every pair of communicating processes?
- What is the capacity of a link?
- Is the size of a message that the link can accommodate fixed or variable?
- Is a link unidirectional or bi-directional?





Direct Communication

- Processes must name each other explicitly:
 - send (P, message) send a message to process P
 - receive(Q, message) receive a message from process Q
- Properties of communication link
 - Links are established automatically
 - A link is associated with exactly one pair of communicating processes
 - Between each pair there exists exactly one link
 - The link may be unidirectional, but is usually bi-directional





Indirect Communication

- Messages are directed and received from mailboxes (also referred to as ports)
 - Each mailbox has a unique id
 - Processes can communicate only if they share a mailbox
- Properties of communication link
 - Link established only if processes share a common mailbox
 - A link may be associated with many processes
 - Each pair of processes may share several communication links
 - Link may be unidirectional or bi-directional





Indirect Communication

- Operations
 - create a new mailbox
 - send and receive messages through mailbox
 - destroy a mailbox
- Primitives are defined as:

send(A, message) - send a message to mailbox A
receive(A, message) - receive a message from mailbox A





Indirect Communication

- Mailbox sharing
 - P₁, P₂, and P₃ share mailbox A
 - P₁, sends; P₂ and P₃ receive
 - Who gets the message?
- Solutions
 - Allow a link to be associated with at most two processes
 - Allow only one process at a time to execute a receive operation
 - Allow the system to select arbitrarily the receiver. Sender is notified who the receiver was.





Synchronization

- Message passing may be either blocking or non-blocking
- Blocking is considered synchronous
 - Blocking send has the sender block until the message is received
 - Blocking receive has the receiver block until a message is available
- Non-blocking is considered asynchronous
 - Non-blocking send has the sender send the message and continue
 - Non-blocking receive has the receiver receive a valid message or null





Buffering

- Queue of messages attached to the link; implemented in one of three ways
 - Zero capacity 0 messages
 Sender must wait for receiver (rendezvous)
 - 2. Bounded capacity finite length of *n* messages Sender must wait if link full
 - 3. Unbounded capacity infinite length Sender never waits





Client-Server Communication

- Sockets
- Remote Procedure Calls
- Remote Method Invocation (Java)






Sockets

- A socket is defined as an endpoint for communication
- Concatenation of IP address and port
- The socket **161.25.19.8:1625** refers to port **1625** on host **161.25.19.8**
- Communication consists between a pair of sockets





Socket Communication








Remote Procedure Calls

- Remote procedure call (RPC) abstracts procedure calls between processes on networked systems.
- Stubs client-side proxy for the actual procedure on the server.
- The client-side stub locates the server and *marshalls* the parameters.
- The server-side stub receives this message, unpacks the marshalled parameters, and peforms the procedure on the server.





Execution of RPC








Remote Method Invocation


- Remote Method Invocation (RMI) is a Java mechanism similar to RPCs.
- RMI allows a Java program on one machine to invoke a method on a remote object.







Marshalling Parameters







Threads

- A thread (or lightweight process) is a basic unit of CPU utilization; it consists of:
 - program counter
 - register set
 - stack space
- A thread shares with its peer threads its:
 - code section
 - data section
 - operating-system resources collectively know as a *task*.
- A traditional or heavyweight process is equal to a task with one thread






Threads (Cont.)

- In a multiple threaded task, while one server thread is blocked and waiting, a second thread in the same task can run.
 - Cooperation of multiple threads in same job confers higher throughput and improved performance.
 - Applications that require sharing a common buffer (i.e., producerconsumer) benefit from thread utilization.
- Threads provide a mechanism that allows sequential processes to make blocking system calls while also achieving parallelism.
- Kernel-supported threads (Mach and OS/2).
- User-level threads; supported above the kernel, via a set of library calls at the user level (Project Andrew from CMU).
- Hybrid approach implements both user-level and kernelsupported threads (Solaris 2).





Multiple Threads within a Task







Threads Support in Solaris 2

- Solaris 2 is a version of UNIX with support for threads at the kernel and user levels, symmetric multiprocessing, and real-time scheduling.
- LWP intermediate level between user-level threads and kernel-level threads.
- Resource needs of thread types:
 - Kernel thread: small data structure and a stack; thread switching does not require changing memory access information – relatively fast.
 - LWP: PCB with register data, accounting and memory information,; switching between LWPs is relatively slow.
 - User-level thread: only need stack and program counter; no kernel involvement means fast switching. Kernel only sees the LWPs that support user-level threads.





Solaris 2 Threads

