
LC Temperature and Matter Lecture Notes

Year 1 Semester 2

Ash Stewart

MSci Physics with Particle Physics and Cosmology

School of Physics and Astronomy
University of Birmingham

Table of Lectures

Lecture 1: Matter I: Welcome and Intro	2
Lecture 2: Matter II: Atomic Physics and LJP	4
Lecture 3: Matter III: Lennard-Jones Potential	9
Lecture 4: Matter IV: Surface Tension and Capillary Action	14
Lecture 1	20
Lecture 1	21
Lecture 7: Introduction to Temperature	22
Lecture 8: Thermodynamics I	24
Lecture 9: Laws of Thermodynamics	28
Lecture 10: Thermodynamic Transitions	33
Lecture 11: PV Planes and Transitions	37
Lecture 12: Heat Transfer	42
Lecture 13	46
Lecture 14: Statistical Physics I: Introduction	50
Lecture 15: Statistical Physics II: The Atmosphere	52
Lecture 16: Statistical Physics III: Atmosphere and Boltzmann Factors	54
Lecture 17: Statistical Physics IV: Boltzmann Factors and Degeneracies	56
Lecture 18: Statistical Physics V	59
Lecture 19: Statistical Physics VI: Something or Other	60

Tue 20 Jan 2026 12:00

Lecture 1 - Matter I: Welcome and Intro

1 Course Welcome

- Study guide and full revision notes (from Prof. Mike Gunn) on Canvas.
 - The course has changed a bit recently, so the full revision notes have additional theory/content which isn't examinable.
- Series of non-assessed problems also on Canvas.

1.1 Course Aims

We want to be able to explain the properties of matter (in the macroscopic world) of various kinds, based on their microscopic behaviour. We also want to be able to understand more about the microscopic behaviour of matter from macroscopic observables.

1.2 Recommended Reading

- Young and Freedman, Ch14 and Ch17-19.
- Properties of Matter, Flowers and Mendoza.
- Introduction to Thermal Physics, Adkins.

2 Intro to Matter

2.1 States of Matter

We want to move away from a simple "cold stuff is a solid, warmer stuff is a liquid and hotter stuff is a gas" by also considering how different materials change state as a function of both pressure and temperature:




Figure 1.1: Phase Diagram for Water




Figure 1.2: Phase Diagram for CO2

At “Standard Pressure and Temperature” (at 20°C and 1ATM), we see that increasing pressure of CO2 takes it to a liquid state. However, at lower temperatures, decreasing the pressure can cause it to sublime straight from a solid to a gas, without a liquid intermediary.

Taking water as an example, pushing the pressure/temperature causes another high-energy state altogether called a “supercritical fluid”. The gradient for the initial vertical portion of the solid/liquid boundary around the freezing point is slightly negative, so applying pressure to ice on this boundary causes it to become liquid. This is uncommon for many materials.

This is because water is weird, where the solid form is less dense than the liquid form. This is how ice skating works, where applying pressure (from a skate) causes a thin upper layer of ice to melt. This thin water layer is what the ice skate can travel on.

Every material also has a “triple point” where the material can act simultaneously in all three standard states of matter.

Thu 22 Jan 2026 13:00

Lecture 2 - Matter II: Atomic Physics and LJP

1 Atomic Sizes

As we increase proton number, we might expect that the atomic radius increases (as there's physically more stuff). We might expect that adding more electrons would expect a corresponding increase in the atomic radius to fit these extra electrons.

This doesn't actually prove to be true, and atomic size and properties are generally determined by the outermost electrons, and atomic radius stays mostly constant.




Figure 2.1: Variation of Atomic Radius with Atomic Number

We do see a large increase in atomic radius for the group one metals, where the outermost electron is very weakly attracted to the nucleus (is easily ionised). For an exam, we can consider atomic radius to be approximately 10^{-10} .

We see a similar trend when considering ionisation energy (the energy required to remove the outermost electron):




Figure 2.2

This is approximately the same for all atomic numbers, with the exception of noble gases (which are extremely difficult to ionise as a result of having full capacity outer shells).

This doesn't apply however to the nuclear radius, R , as the nucleus is compressed to a much higher degree, so there's not space to fit additional nucleons without increasing radius. For atomic radius A , and modelling the nucleus as a sphere, we get:

$$R = r_0 A^{\frac{1}{3}}$$

Where $r_0 = 1.2 \times 10^{-15} \text{ m} = 1.2 \text{ fm}$ is a constant.

2 Atomic Masses

Given the extremely small mass scales, we generally give masses of atoms or molecules in terms of atomic mass units, amu, where:

$$1 \text{ amu} = 1.66 \times 10^{-27} \text{ kg}$$

This is defined as 1/12th the mass of a Carbon-12, ^{12}C atom. The atomic mass of Carbon-12 is thus 12 amu, however a proton and neutron each have mass 1.007 amu and 1.009 amu respectively. Why is there a discrepancy if we add the masses of the individual nucleons?

This is because, when combining these nucleons into a nucleus, some of this mass is converted into energy. This is called "binding energy" and is used to hold the nucleus together.

2.1 Moles

A mole (mol) is an SI base unit used to describe the amount of a substance. 1 mole of a substance is defined by Avogadro's number, $N_A = 6.022 \times 10^{23}$, where one mole has N_A atoms/molecules. We again use Carbon 12, as 12 grams of Carbon-12 has N_A atoms.

We further have:

$$\text{amount, mol} = \frac{N}{N_A}$$

$$\text{amount, mol} = \frac{\text{Mass}}{\text{Atomic Mass}}$$

For gasses, one mole occupies exactly 22.4 L or 22.4 dm³ at standard temperature and pressure (0°C, 10⁵ Pa = 1 atm), regardless of the gas in consideration.

3 Rayleigh's Oil Drop Measurement

Rayleigh conducted an experiment where he took a large volume of water, and placed a drop of olive oil (of known volume V) on top. He postulated that, due to the nature of olive oil being long-chained hydrocarbons, the oil would spread out perfectly thinly, and produce a layer exactly one atom tall.

He said that this would form a circular layer of radius R and height d . If we take the film to be a cylinder (and d is too small to measure directly), we can measure R and use the known volume to determine d :

$$V = \pi R^2 d \implies d = \frac{V}{\pi R^2}$$

When he carried this out, he determined the atomic radius ¹, as $\sim 1\text{nm}$, i.e. being one order of magnitude out. This wasn't bad for how rudimentary the experiment was!

4 Latent Heat

We know that there has to be some kind of force between two atoms. If we consider a diatomic molecule, separating these atoms from each other to infinity requires some amount of energy ϵ . Because there are two atoms, the work done per atom is $\epsilon/2$.

Lets consider a more complex example with many more atoms (i.e. converting a solid to liquid):




Figure 2.3

In this case, extracting the red atom from all its 12 nearest neighbours will take $12\epsilon/2$. We should additionally consider the 6 next nearest neighbours and so and so on. Each increase in number of n th next nearest neighbours has a decreasing impact in the force required, so leads to diminishing returns. In this course, we often ignore the next nearest neighbours and further. If asked to estimate, we use 6 – 10 for a liquid, and 8 – 12 for a solid.

While we're considering this in a solid, lets use it as an approximation for a liquid. The latent heat of vaporisation $L(\text{Jkg})$ is the amount of heat required to completely vaporise a liquid into a gas.

$$L = 12\epsilon/2 \times \frac{\text{number of atoms}}{\text{mass of material, kg}}$$

And the number/mass is given by:

$$\frac{\text{kg}}{\text{atoms}} = \rho \times d^3 \implies \frac{\text{atoms}}{\text{kg}} = \frac{1}{\rho d^3}$$

Hence:

$$d = \sqrt[3]{\frac{1}{\text{atoms per kg} \times \rho}}$$

¹Strictly, an upper limit for the radius

5 Forces Between Atoms

What causes the forces between atoms? It can't be the electrostatic (coulomb) force, as atoms are electrically neutral.

It can't be the nuclear force, as the range is too small. Likewise, it can't be the weak force as this mediates the wrong particles and has an even smaller range.

Finally, it can't be gravitational as atoms have far too low a mass for the gravitational force to have any real impact.

Even though the electrostatic component has no impact, the electromagnetic force as a whole can.

5.1 Water Example

Oxygen is slightly electronegative, while hydrogen is not. This means that if we have a H_2O water molecule, the electrons will be pulled ever so slightly closer to the oxygen and away from the hydrogen. Across the whole atom, this causes a slight charge on each side of the atom:




Figure 2.4

Water is “polar molecule” and forms a permanent dipole, where the positive and negative poles of molecules attract.

6 “Normal” Atoms

This only works for some atoms. A block of iron for example cannot be explained by this, as all the atoms are the same, so have equivalent electronegativity.

Here, fluctuations in the electron cloud cause an instantaneous dipole to form. This may be very brief, but lasts for sufficiently long to impact another atom. This atom has electron distribution impacted by this force, causing it to become a dipole. This creates a field which impacts the original atom etc. This causes the atoms to be stuck as instantaneous dipoles, resulting in a net attractive force called the Van der Waal's force.

As the electric field due to a dipole goes as $|E| \propto 1/r^3$, the induced dipole in the first atom depends on the strength of its dipole field and the size of the induced dipole in the second atom:

$$|E| = \frac{1}{r^3} \frac{1}{r^3} = \frac{1}{r^6}$$

The force induced by these dipoles explains attraction for non-polar molecules. Force between two atoms is considered positive (by convention) if they repel and negative if they attract.

However, the fact that atoms have a consistent interatomic spacing and do not collapse into black holes suggests that there is some kind of repulsive force that keeps them at fixed distances.

We can infer that this force must be very strong at small distances, but much weaker at larger distances.

7 LJ Potential

We can divide particles into fermions (half integer spin) and bosons (integer spin). The wave function of a boson is symmetric about y , so overlapping two bosons causes superposition. Fermions are antisymmetric (i.e. a sine wave). This means that two fermions in the same position causes destructive interference, with a net wave function of 0.

This means that two fermions in the same quantum state (same wave function) cannot share a position, and have a force repelling each other should they try. We approximate this as a potential of the form:

$$V \propto \frac{1}{r^{12}}$$

Lennard-Jones combined these, describing the net potential of the form:

$$V_{LJ} = \frac{A}{r^{12}} - \frac{B}{r^6}$$

Tue 27 Jan 2026 12:00

Lecture 3 - Matter III: Lennard-Jones Potential

1 Potential Distance Plots

If the values of the constants A, B are known, the general form of a Lennard-Jones potential plot is:

$$V_{LJ} = \underbrace{\frac{A}{r^{12}}}_{+ \text{ so repulsive}} - \underbrace{\frac{B}{r^6}}_{- \text{ so attractive}}$$




Figure 3.1

The potential is at some baseline minimum value $-\epsilon$ at distance r_0 .

For our LJP force, we require:

- Repulsive at very short distances (smaller than interatomic spacing).
- Attractive force for intermediate distances (larger than interatomic spacing).
- No force as $r \rightarrow \infty$.
- The atoms equilibrium point is roughly the size of the interatomic spacing in liquids and solids.

In order to describe this more effectively, we need to find expressions for A, B . We do this based on the earlier initial conditions of $V_{LJ} = -\epsilon$ at $r = r_0$

2 Deriving A and B

At the equilibrium point $r = r_0$, we have:

$$V_{LJ} = -\epsilon$$

$$F = 0$$

We can get an expression for force by $F = -dV/dr$:

$$F = -\left(-\frac{12A}{r^{13}} + \frac{60}{r^7}\right) = \frac{12A}{r^{13}} - \frac{6B}{r^7}$$

At equilibrium:

$$F = 0 = \frac{12A}{r_0^{13}} - \frac{6B}{r_0^7}$$

Disregarding trivial case where $r_0 = 0$, as there cannot be any atoms in this case. Therefore, $r_0 \neq 0$:

$$12A = 6Br_0^6$$

$$\frac{2A}{B} = r_0^6 \implies r_0 = \sqrt[6]{\frac{2A}{B}}$$

And considering potential at equilibrium:

$$\begin{aligned} -\epsilon &= \frac{A}{r_0^{12}} - \frac{B}{r_0^6} \\ \implies -\epsilon &= \frac{A}{\left(\frac{2A}{B}\right)^2} - \frac{B}{\left(\frac{2A}{B}\right)} \\ \implies -\epsilon &= \frac{B^2}{4A} - \frac{B^2}{2A} \\ \epsilon &= \frac{B^2}{2A} - \frac{B^2}{4A} = \frac{B^2}{4A} \end{aligned}$$

Putting it all together:

$$\epsilon = \frac{B^2}{4A} \tag{1}$$

$$r_0^6 = \frac{2A}{B} \tag{2}$$

Hence:

$$\frac{2A}{r_0^6} = B \implies \epsilon = \frac{(2A)^2/(r_0^6)^2}{4A}$$

$$A = \epsilon r_0^{12}$$

$$B = 2\epsilon r_0^6$$

So the final functional form of the LJP is:

$$V_{LJ} = \epsilon \left[\left(\frac{r_0}{r}\right)^{12} - 2\left(\frac{r_0}{r}\right)^6 \right]$$

Sometimes in textbooks we see:

$$V_{LJ} = 4\epsilon \left[\left(\frac{\sigma}{r}\right)^{12} - 2\left(\frac{\sigma}{r}\right)^6 \right]$$

Here, σ is the distance where potential is zero, rather than r_0 being the distance where force is zero (potential is $-\epsilon$).

3 Full LJP




Figure 3.2: The full LJP and the two contributing forces

This gives us the overall LJP that satisfies our three requirements:

- At distances below r_0 , the Pauli Exclusion Principle force dominates, causing net repulsion.
- As $r \rightarrow \infty$, both components (and the overall potential) tend to zero.
- At distances above, but close to r_0 , the Van der Waal's force dominates, causing net attraction.

Where $r/r_0 = 1$, we have a stable equilibrium position, needing $-V(r_0) = -\epsilon = U_0$ to break these apart.

3.1 Implications of LJP

Consider a two dimensional atomic lattice:




Figure 3.3

The central atom sits in a potential well of approximate depth $N\epsilon$, where N is the number of nearest neighbours. In the equilibrium position, all of these atoms are separated by a distance $r = r_0$.

The next nearest neighbours and beyond do contribute, but to a much smaller degree. It's not zero, but the next nearest neighbours have approximate potential $\epsilon/30$.

We have:

$$V_{LJ} = \epsilon \left[\left(\frac{r_0}{r} \right)^{12} - 2 \left(\frac{r_0}{r} \right)^6 \right]$$

Hence, using $F(r) = -\frac{dV(r)}{dr}$:

$$F(r) = 12\epsilon \left(\frac{r_0^{12}}{r^{13}} - \frac{r_0^6}{r^7} \right)$$

This has a very similar form to the potential:




Figure 3.4

Just noting that while potential is $-\epsilon$ at $r_0 = r$, the force is zero.




Figure 3.5

3.2 Empirical Data

The LJP provides a surprisingly accurate model for the genuine empirically measured data:




Figure 3.6

It does have limitations though:

- The fact its an infinite range potential means it's very computationally expensive to calculate. We need to truncate the potential once it shrinks below a value below which its negligible.
- For large molecules (such as an amino acid), they are often too large. The distance between the centres of adjacent molecules is too large for the LJP as LJP assumes that they are effectively point like. Amino acids can have forces all the way along their chains and this is not well modelled by the LJP.

Thu 29 Jan 2026 13:00

Lecture 4 - Matter IV: Surface Tension and Capillary Action

Recap from last time:

- Force and potential are related, with $F = \frac{-dV}{dx}$, with x relating to position.
- At equilibrium, neighbouring atoms sit at distance r_0 (average bond length) from each other. They sit in a potential well of depth $N\epsilon$ where N is the number of nearest neighbours.
- At $x < r_0$, the force is +ve (repulsive), at $x > r_0$ the force is -ve (attractive).

1 Coordination Numbers




Figure 4.1

In a densely-packed Face-Centred Cubic (left) or Hexagonally Close-Packed Solid (3D, middle - 2D, right) configuration, the maximum coordination number (number of nearest neighbours) is 12. The outermost.

For solids, we expect an interatomic spacing of $\sim 2 \times 10^{-12}\text{m}$, for liquids we expect $3 \times 10^{-10}\text{m}$ and for gases at STP we expect about $40 \times 10^{-10}\text{m}$.

For liquids, we expect a coordination number $n < 10$.

2 Molecular/Structural Binding Energies

To first order (nearest neighbours only), how much energy do we need to remove the innermost atom (orange in the middle figure) from the centre of the structure.

We might expect 12ϵ , the total binding energies of all of the nearest neighbours. Instead however, we are leaving the 12 nearest neighbours in place and only taking one atom to infinity. Since moving both atoms to infinity is given by ϵ , we have:

$$E = \frac{n\epsilon}{2}$$

Where n is the number of nearest neighbours.

To remove one mole of connected atoms, we have:

$$E = \frac{nN_A\epsilon}{2}$$

Again, the factor of two arises to avoid double-counting bonds, i.e. a mole consists of $N_A/2$ pairs of atoms.

3 Latent Heat

Moving macroscopically, we have seen:

$$L = 10\epsilon/2 \times \frac{\text{number of atoms}}{\text{mass of material, kg}}$$

For a liquid of coordination number 10. This is very similar to the just seen:

$$E = \frac{nN_A\epsilon}{2}$$

As N_A gives us atoms per mol, this is effectively identical - one just considers moles and one considers mass in kg.

The molar latent heat equation assume however that the molecular energy comes exclusively from potential energy. This is an approximation that works when kinetic energy is much less than potential energy, i.e. at low temperatures. We can empirically see that molar latent heat varies with temperature:




Figure 4.2

This is because, at higher temperatures, the average bond length increases (as the particles have a greater kinetic energy, so vibrate with a larger magnitude):




Figure 4.3

Because the LJP is antisymmetric, at higher temperatures the molecules spend less vibrational time in the contracted position and more time in the expanded position, resulting in a larger average bond length. Effectively, they experience more repulsion when they are together than they do attraction when apart, hence a larger bond length on average. This also explains thermal contraction.

We can see from the potential graph that this results in a lower ϵ , which is why we see a change in latent heat at different temperatures.

4 Surface Tension

Consider a (literal) sea of particles. Does a particle surrounded on all sides deep in the liquid experience a lesser or greater potential than a particle on the surface?

The particle deep in the liquid has twice as many nearest neighbours (being surrounded on all sides) so has a greater potential. The particle on the surface will have:

$$V = \frac{n\epsilon}{4}$$


So requires $n\epsilon/4$ amount of work to take a deeper particle to the surface.

We define a quantity called surface tension γ , the work done to move 1m^2 of particles, N to the surface from deeper inside the liquid:

$$\gamma = \left(\frac{n\epsilon}{2} - \frac{n\epsilon}{4} \right) \times N$$

Where N is the number of particles per m^2 . It has units of energy over area (force over length).

This allows animals such as small insects who can sit on the surface of the liquid to do so, because allowing the insect to submerge would require an increase in the water's surface area. The work required to generate this new surface area is not achievable by the insects gravitational potential energy.

Figure 4.4: Object sinks if $\Sigma F_s < F_w$

What other consequences does this have?

- Given a body of water wants to minimise its surface area (for a constant volume), drops of water will form spheres.

5 Surfaces Revisited

Consider a liquid contained in some beaker. Consider a particle on the surface of the *beaker* (purple):




Figure 4.5

There are two forces in effect here, the interatomic forces of the liquid and of the beaker. We call the forces between the liquid itself cohesion, and between the liquid and a foreign body adhesion.

5.1 Wetting

“Wetting” is the ability of a liquid to maintain contact with a solid surface and is inversely proportional to surface tension. Most liquids are “wetter” than water, due to water’s high surface tension.

If there are strong adhesive forces, the liquid preferentially sticks to the side of the container, causing the formation of a concave meniscus.

If there are strong cohesive forces, minimisation of surface area causes the formation of a convex meniscus.

6 Capillary Action

If an open tube is placed into contact with the surface of a liquid with strong adhesion, the liquid will rise up the sides of the tube:




Figure 4.6: Capillary action for water and mercury. Note that mercury, being strongly cohesive, minimises surface area so does not rise up.

We can describe this mathematically in terms of the angle formed by the meniscus, the width of the meniscus and the height reached by the liquid:




Figure 4.7

There are two competing forces here:

- Surface tension, pulling the liquid up.
- The weight of the liquid, pulling it down.

The weight is given by the volume (if we approximate the meniscus as being small compared to the total volume, hence just a cylinder) and density:

$$F_W = mg = \rho Vg = \rho \pi r^2 hg$$

Surface tension has units of force divided by length. We can therefore get the force by multiplying by the active contact length, which is the circumference of the cylinder. Finally, we only care about the vertical component, so take $\cos \theta$:

$$F_\gamma = \gamma 2\pi r \cos \theta$$

Hence, as equilibrium:

$$F_\gamma = F_W$$

$$2\gamma \pi r \cos \theta = \rho \pi r^2 hg$$

$$2\gamma \cos \theta = \rho grh$$

This gives:

$$h = \frac{2\gamma \cos \theta}{\rho gr}$$

Tue 20 Jan 2026 12:00

Lecture 1

Tue 20 Jan 2026 12:00

Lecture 1

Mon 09 Feb 2026 11:00

Lecture 7 - Introduction to Temperature

We're starting the portion of the module on thermodynamics, looking at temperature, pressure etc and transitions involving these.

1 What is Temperature?

Particle for a single particle isn't well defined for the definition of temperature we want to use. There is two definitions:

- One is statistical, looking at average kinetic energy of particles.
- One is based on entropy and isn't looked at until second year.

We define temperature as *a statistical collection of energies for particles that make up the system for which we are measuring the temperature*. A material will have a range of kinetic energies, some very large, some very small, so we care about a statistical average. Thermalisation happens as a result of these high kinetic energy particles striking lower kinetic energy particles.

Temperature: A statistical collection of energies of the particles that comprise the system in question.

We can express temperature as using the Maxwell-Boltzmann distribution:

$$P(v) = 4\pi \left(\frac{M}{2\pi RT} \right)^{\frac{3}{2}} v^2 \exp \left(\frac{-Mv^2}{2RT} \right)$$

We look at this in more depth when we cover statistical physics later, but for now we care about the key features. If we plot $P(v)$ (the probability of finding a particle at certain velocity) against these velocities for a range of temperatures:




Figure 7.1

This has exponential decay, so theoretically we can find a particle at any velocity within a gas of any temperature. Particles with higher temperatures have a higher peak, so a higher average velocity.

2 Temperature Scales

We can use a number of different temperature scales:

- The Fahrenheit scale is set such that the freezing point of water is 98.6°F, and the boiling point of water at 212°F. It's designed to be based around the range of temperatures that a person could realistically experience in the core range from 0-200. It's not a useful unit and won't be used in exams.
- Celsius is the standard unit.
- Kelvin is the common unit of thermodynamics. It has the same graduations as degrees celsius but is shifted such that absolute zero is at 0K. Note that Kelvin has no degrees symbol. °C → K can be converted between using:

$$T(\text{K}) = T(^{\circ}\text{C}) + 273.15$$

3 Thermal Expansion

As a solid is heated, it expands in all directions. Consider a cuboid of height, width, depth W, L, D , we have new dimensions of $D + \Delta W, L + \Delta L, D + \Delta D$ after a small change in temperature. We can define the linear expansion coefficient (a material property) α_L based on these dimensions and the change in temperature:

$$\alpha_L \Delta T = \frac{\Delta L}{L} = \frac{\Delta W}{W} = \frac{\Delta D}{D}$$

If we consider the area instead, we have the area expansion coefficient:

$$\frac{\Delta A}{A} = \alpha_A \Delta T \approx 2\alpha_L \Delta T$$

The latter approximation can be derived as follows. Consider one dimension, i.e. L :

$$\begin{aligned} \frac{\Delta L}{L} &= \alpha_L \Delta T \\ \implies \Delta L &= L\alpha_L \Delta T \end{aligned}$$

So:

$$L_{\text{new}} = L + \Delta L = L(1 + \alpha_L \Delta T)$$

Pairing this with width to find an area (of a face):

$$\begin{aligned} W_{\text{new}} &= W + \Delta W = W(1 + \alpha_L \Delta T) \\ A_{\text{old}} &= L \times W \\ A_{\text{new}} &= L_{\text{n}} \times W_{\text{n}} \\ A_{\text{n}} &= LW(1 + \alpha_L \Delta T)^2 \\ &= LW(1 + 2\alpha_L \Delta T + \alpha_L^2 \Delta T^2) \end{aligned}$$

For a small change in temperature, the second order term is very small, hence:

$$\frac{\Delta(LW)}{LW} \approx 2\alpha_L \Delta T$$

The linear expansion coefficient has units of K^{-1} .

3.1 Thermal Stress

Consider a rod fixed between two immovable walls. The rod attempts to expand, but is fixed. This provides a thermal stress on the wall. If the rod has cross-sectional area A and Young Modulus Y , the thermal stress is given by:

$$\frac{F}{A} = Y\alpha_L \Delta T$$

This is why bridges etc need to have thermal expansion joints, otherwise they would buckle/break under this thermal stress.

3.2 Lennard Jones and Thermal Expansion

Thu 12 Feb 2026 13:00

Lecture 8 - Thermodynamics I

1 Temperature Scales II

In order to measure temperature, we need to define a quantity which directly depends on temperature - ideally linearly.

We can't measure temperature directly, we need this extra intermediary quantity. For example, thermometers use volume and measure the volume of a known quantity of a substance which behaves nicely at known temperatures.

This means that:

$$T = T_0 + k \frac{x - x_0}{x_0}$$

Where T_0 is a calibration point, at which point our quantity has value x_0 . For the Celsius scale, we use $T_0 = 0^\circ\text{C}$ and we choose a value for the constant k such that when water boils, $T = 100^\circ\text{C}$.

However, $PV = nRT$ says that this is dependant on pressure too which isn't ideal, as for different pressures the relationship between volume and temperature differ and our scale is only consistent for a single pressure....

Instead of using the boiling/freezing point of water at 1ATM as our calibration point, we can use the "triple point" of water. This point only happens at a single pressure/volume, so is more consistent:




Figure 8.1

Alternatively, we could use the technique employed by the Kelvin scale and use absolute zero as our calibration point. Regardless of pressure/volume/amount of substance (provided its kept constant), they will all reach absolute zero at exactly the same theoretical temperature. We can therefore calibrate our scale off of this point.

2 Thermodynamics

Thermodynamics: The science of the relationship between heat, work, temperature and energy. Thermodynamics broadly deals with the transfer of energy from one place/form to another. Heat is a form of energy corresponding to a definite amount of mechanical work.

2.1 What is heat?

Heat is measure of thermal energy transfer between two systems. This shouldn't be confused with the colloquial understanding of heat i.e. being hot or cold, which is relative.

2.2 Systems

A system is a part of the universe we are investigating or discussing eg a room, bottle, galaxy etc. We often consider the ideal physics case of a closed system where the system doesn't exchange any heat with outside the system however this is not realistic.

We often discuss systems comprised of a container of some kind of fluid which either closed (with a lid) or open (no lid).

We can consider two types of walls:

- **Adiabatic walls:** No heat transfer possible (does not exist in practice).
- **Diathermal walls:** Heat transfer is possible through the wall.

2.3 Thermal Equilibrium

A system is in thermal equilibrium if it has a constant energy density throughout, so the system is in internal thermal equilibrium.

Two systems are in thermal equilibrium if there is no net transfer of heat energy between them. There will be some amount of heat transfer between both systems, and thermal equilibrium does not mean that there is no exchange of heat energy between the two. Some of the particles in one part of the system may statistically have higher energy and exchange energy, but there is no *net* transfer.

Consider some gas in a piston with volume, pressure and temperature V_i, P_i, T_i . As we pull out the piston, the volume of the gas changes and we have a new final temperature volume (and as pressure/volume are related to pressure), pressure and temperature V_f, P_f, T_f .

This does not happen instantly and there will be some time required to reach thermal equilibrium (a few seconds) after we have finished pulling out the system.

We can bring a system in contact with another system, i.e. placing a rubber duck (system B) in a bath (system A) or the ocean (system C). Which of these two pairs (A and B vs C and B) will thermalise first? While the duck will reach the temperature of the water faster when in the ocean than the bath, thermal equilibrium requires the entire system to thermalise. Therefore, as the ocean has much higher volume it takes longer for the ocean to entirely thermalise to the newer duck-adjusted temperature.

3 Definitions

- **Isothermal:** A change to a system which takes place at a **constant temperature**.
- **Isobaric:** A change to a system which takes place at a **constant pressure**.
- **Isochoric:** A change to a system which takes place at a **constant volume**.
- **Adiabatic:** A change to a system which takes place **without transfer of heat**. Temperature may change, but heat cannot enter or leave the system.

4 Heat Capacity

What is the relationship between heat energy ΔQ transferred to a system and the corresponding increase in system temperature ΔT ? This is given by:

$$\Delta Q = C \Delta T$$

Where C is the heat capacity in J/K, hence:

$$C = \frac{dQ}{dT}$$

C varies with the amount of material, so we additionally define specific and molar heat capacity:

- Specific Heat Capacity J/kgK: $C = mc$
- Molar Heat Capacity J/molK: $C = nc$

A higher heat capacity means a smaller increase in temperature for a given heat (i.e. more energy required to raise the temperature of the system by some amount).

To make things more difficult, heat capacity also varies with the system temperature. We also need to specify whether we are measuring isobaric or isochoric, as these will give different values:




Figure 8.2




Figure 8.3

Notably, isobaric heat capacity is mostly constant around the standard values of liquid water at standard temperature:




Figure 8.4

It is therefore not unreasonable to treat heat capacity as a constant in some circumstances, provided we state this as an assumption and justify it.

Tue 17 Feb 2026 12:00

Lecture 9 - Laws of Thermodynamics

1 0th Law of Thermodynamics

Consider two blocks next to each other, one with T_h and one with T_c . The blocks will thermalise to their mean $(T_h + T_c)/2$ in the trivial case where the blocks are identical.

Net heat will flow between the two systems until they have the same energy density and hence temperature.

If we have three systems: A, B, C. If we know that A and B are in thermal equilibrium, and A and C are in thermal equilibrium, then B and C are also in thermal equilibrium.

It's a fairly trivial axiom, so we denote it the zeroth law. Effectively, all objects in a system in equilibrium share the same temperature.

2 Ideal Gases

An ideal gas is defined as a collection of molecules (or atoms, if monatomic) that are non-interacting with each other (no interatomic forces) and collide elastically with each other.

The internal energy of the gas is dependant on the velocities of the molecules, and hence on the temperature, and not on pressure or volume.

Boyle's Law: "The absolute pressure exerted by a given mass of an ideal gas is inversely proportional to the volume it occupies, if the temperature and amount of gas remain unchanged within a closed system."

Effectively:

$$P \propto \frac{1}{V}$$

Charles' Law: "When the pressure of a sample of an ideal gas is held constant, the Kelvin temperature and volume will be in direct proportion."

Effectively:

$$T \propto V$$

Ideal Gas Law: Since $P \propto \frac{1}{V}$ and $T \propto V$, we have: $PV = kT$, where k varies with context, for example when considering moles:

$$PV = nRT$$

Where n is the number of moles and $R = 8.314 \text{ J mol}^{-1} \text{ K}^{-1}$ is the gas constant.

Or for molecules:

$$PV = Nk_bT$$

Where $N = N_a n$ is the number of molecules, and $k_b = R/N_a$ is the Boltzmann Constant.

This is called an equation of state and allows us to describe the gas' state macroscopically. We generally express this on a P/V diagram, where each point on the plot represents a specific gas state. If we keep the amount of gas present constant, we can use any two of the variables to determine the third.




Figure 9.1

2.1 Joule's Second Law

Consider a system with a box divided in two. An ideal gas is contained in the leftmost half, and the rightmost half is a vacuum. We separate the two with a divider constituting an impermeable membrane.

We remove the membrane laterally, doing no work on the gas. Joule observed that the gas stayed at the same temperature as it diffused into the vacuum.

Consider the internal energy of the gas, denoted U , assuming that U is a function of two of the state variables. We know the temperature did not change, and the volume did, so $U(T, V)$.

We would expect:

$$dU = \frac{\partial U}{\partial T} dT + \frac{\partial U}{\partial V} dV$$

Temperature was observed experimentally to not change, hence $dT = 0$, so:

$$dU = 0 + \frac{\partial U}{\partial V} dV$$

Volume did change, so $dV \neq 0$. We did no work on the gas, as the divider was removed laterally, hence there was no change in internal energy, so:

$$dU = \frac{dU}{dV} dV = 0$$

And since $dU = 0$, we must have:

$$\frac{dU}{dV} \neq 0$$

This means that there is no dependence on volume for internal energy, hence U is dependent only on T , as found by Joule. This means that the gas Joule chose was well approximated by an ideal gas.

This is easier at higher temperatures, as a high temperature leads to high kinetic energies, so the interatomic forces becomes less significant and easier to disregard in reality.




Figure 9.2

We see here that the ideal gas law becomes a better approximation as we increase temperature, and a worse and worse approximation as pressure increases.

From a LJP perspective, increasing the pressure decreases the average distance between gas molecules. This means that the potential between gas molecules is no longer negligible, and the assumption of zero potential no longer holds.

If we increase pressure even further, the force becomes repulsive and PV/nRT returns to being positive. At higher temperatures, this little dip isn't observed as a higher kinetic energy makes any interatomic forces relatively more negligible.




Figure 9.3

At low pressure or high temperature, the ideal gas law is a good assumption as:

- At low pressure, interatomic spacing is large enough to disregard interatomic forces.

- At high temperature, kinetic energy is large enough to comparatively disregard interatomic forces.

We deal solely with Maxwell-Boltzmann gases in this source that follow classical laws. We also have Fermi and Bose gases (made entirely of fermions and bosons respectively), but they're quantum mechanical, exotic and outside of this course.

2.2 Changing Energies




Figure 9.4

Say we want to go from T_1 to T_2 . We need to change the internal energy of the gas somehow. We have two general ways to change this:

- Add heat to the system by transferring heat to the gas at a constant volume.
- Do some work on the gas, i.e. by crushing it and reducing volume.

Consider a piston of area A , applying constant force F with extension ΔL . The pressure on the gas is $P = F/A$. The work done on the gas is:

$$\begin{aligned}\Delta W &= F\Delta L \\ \Rightarrow \Delta W &= P(A\Delta L) \\ \Rightarrow \Delta W &= P\Delta V\end{aligned}$$

Moving from infinitesimal Delta values:

$$W_{\text{on gas}} = \int dW = \int P dV$$

In the opposite case considering work done by the gas, conservation of energy says it must be oppositely signed:

$$W_{\text{by gas}} = - \int P dV$$

2.3 Mass Drop Experiment

The falling mass spins the paddles in the water, the work as potential energy is converted to kinetic energy raising the temperature of the water.

This tells us that mechanical work done and heat energy must be related in some manner.

3 1st Law of Thermodynamics

The change in internal energy of a system, ΔU is increased with increasing heat transfer into the system, Q_{in} and work done on the system, W_{on} :

$$\Delta U = Q_{\text{in}} + W_{\text{on}}$$

This is just conservation of energy.

Thu 19 Feb 2026 13:00

Lecture 10 - Thermodynamic Transitions

1 Thermodynamic Transitions

1.1 Isothermal (Fixed Temperature)

This may look like:

- A curve on a PV plot. As $PV = nRT$, a PV plot shows a $1/x$ relationship for constant T .
- A vertical straight line on a PT plot.
- A vertical straight line on a VT plot.

If the temperature change is 0, ΔU (which we derived last time only depends on temperature) follows:

$$\Delta T = \Delta U = 0$$

Hence:

$$0 = Q_{\text{in}} + W_{\text{on}}$$

1.2 Isochoric (Fixed Volume)

This may look like:

- A vertical straight line on a PV plot.
- A proportional relationship on a PT plot.
- A horizontal straight line on a VT plot.

For an isochoric transition, $\Delta U = Q_{\text{in}}$, as:

$$W_{\text{on}} = (-) \int P dV$$

And as $dV = 0$, $W_{\text{on}} = 0$

1.3 Isobaric (Fixed Pressure)

This may look like:

- A horizontal straight line on a PV plot.
- A horizontal straight line on a PT plot.
- A proportional relationship on a VT plot.

For an isobaric transition, P is just a constant, so the integral:

$$W_{\text{on}} = \int_{V_1}^{V_2} P dV = [PV]_{V_1}^{V_2}$$

Where P is constant, which is nice and easy. Generally:

$$W_{\text{on}} = - \int P dV = (-)P\Delta V$$

$$\Delta U = \Delta Q - P\Delta V$$

2 Heat Capacities of Ideal Gases

Recall that:

$$\Delta Q = C\Delta T \implies C = \frac{dQ}{dT}$$

At a fixed volume:

$$C_V = \left(\frac{dQ_{\text{in}}}{dT} \right)_T$$

And at a fixed pressure:

$$C_P = \left(\frac{dQ_{\text{in}}}{dT} \right)_P$$

Mayer's Relation says that:

$$C_P = C_V + nR$$

This is an examinable derivation.

2.1 Deriving Mayer's Relation

Proof. Consider a gas piston. We have state variables V, P, T , and N is constant as the piston is sealed. The first law of thermodynamics says:

$$\Delta U = Q_{\text{in}} + W_{\text{on}}$$

We can consider this for both a constant volume or a constant pressure. For a constant volume:

$$\Delta U = \Delta Q_1$$

And for a constant pressure:

$$\Delta U = \Delta Q_2 - P\Delta V$$

Noting that the two Q s are different as we have two different transitions. We can create a slightly different expression for constant volume by multiplying by $\Delta T/\Delta T$:

$$\Delta U = \frac{\Delta Q_1}{\Delta T} \times \Delta T = C_V \Delta T$$

And for constant pressure:

$$\Delta Q_2 = \Delta U + P\Delta V = \frac{\Delta Q_2}{\Delta T} \Delta T = C_P \Delta T$$

Hence:

$$C_P \Delta T = \Delta U + P\Delta V$$

$$C_V \Delta T = \Delta U$$

Setting equal to each other based on ΔU :

$$\Delta U = \boxed{C_V \Delta T = C_P \Delta T - P\Delta V}$$

$$C_P \Delta T - C_V \Delta T = P\Delta V$$

$$\Delta T(C_P - C_V) = P\Delta V$$

$$\implies C_P - C_V = \frac{P\Delta V}{\Delta T} \times P \quad \text{NB: } P \text{ is still constant.}$$

Using $PV = nRT$, for constant pressure we have $\frac{P\Delta V}{\Delta T} = nR$. Hence:

$$C_P - C_V = nR$$

$$C_P = C_V + nR$$

□

It is clear that $C_P > C_V$.

Note: We tend to use heat capacity at a constant volume unless specified.

3 Back to Thermodynamic Transitions

3.1 Adiabatic Transitions (No Heat Transfer)

These seem quite a bit like isothermal transitions, but look different on a PV plot:




Figure 10.1: Differences in transitions on a PV Plot




Figure 10.2: Adiabatic Transitions on a PV and VT Plot

For isothermal transitions, $PV = \text{const.}$

For adiabatic transitions, $PV^\gamma = \text{const}$ where $\gamma = \frac{C_P}{C_V}$

In a PV plane, adiabatic processes appear steeper than isothermal processes and adiabatic processing are steeper in the PV plane than the VT plane.

For an adiabatic transition, we can reduce the first law of thermodynamics like so:

$$\Delta U = Q_{\text{in}} + W_{\text{on}}$$

$Q_{\text{in}} = 0$ as there is no heat transfer, hence:

$$\Delta U = W_{\text{on}}$$

3.2 Derivations

Proof. For adiabatic transitions, where $Q = 0$.

The First Law becomes $\Delta U = Q_{\text{in}} + W_{\text{on}}$. Since $Q_{\text{in}} = 0$:

$$dU = 0 + dW_{\text{on}}$$

And assuming work is being done *on* the gas, the sign becomes negative:

$$dU = -PdV$$

$$\frac{dUdT}{dT} = -PdV$$

We slightly abuse the definition of heat capacity here, and this will be elaborated on in a later lecture:

$$C_V dT = -PdV$$

Using $PV = nRT$, we have: $d(PV) = nRdT$:

$$nRdT = PdV + VdP$$

$$dT = \frac{PdV + VdP}{nR}$$

$$C_V dT = -PdV$$

$$0 = C_V \frac{PdV + VdP}{nR} + PdV$$

$$0 = C_V (PdV + VdP) + nRpdV$$

$$0 = PdV(C_V + nR) + C_V VdP$$

$$0 = PdV(C_P) + VdP(C_V)$$

$$0 = \frac{C_P}{C_V} PdV + VdP$$

Let $\gamma = \frac{C_P}{C_V}$, and dividing through by pressure and volume:

$$\gamma \frac{dV}{V} + \frac{dP}{P} = 0$$

$$\int \gamma \frac{dV}{V} = - \int \frac{dP}{P}$$

$$\gamma \ln V + c_1 = -\ln(P) + c_2$$

Finally:

$$\gamma \ln(v) + \ln(p) = \text{const}$$

$$\ln(PV^\gamma) = \text{const}$$

$$PV^\gamma = e^{\text{const}} = \text{another constant}$$

Hence:

$$PV^\gamma = \text{const}$$

As required! □

Note that in a TV plane, we instead have:

$$TV^{\gamma-1} = \text{const}$$

Tue 24 Feb 2026 12:00

Lecture 11 - PV Planes and Transitions

Note RE: Last Lecture

To avoid confusion, the Physics convention is:

$$W_{\text{by}} = \int P dV$$

$$W_{\text{on}} = - \int P dV$$

1 PV Diagrams

We can move between points on a PV plane through processes which usually involve some kind of heat transfer and work. For example:




Figure 11.1

The two transitions from $A \rightarrow B$ are processes, and the nature of the process depends on the shape of the transition on the PV plot.

- Since the two possible transitions between A and B share the same start and end point, the change in internal energy U_{AB} is the same for both. Since we go from T_A to T_B in both cases (as U depends on T , which in turn depends on P, V so for the same P, V we have the same T), both paths have the same start/end internal energy, so the same change between them.
- The work done by the gas in the two paths is not the same, however. W_{by} is larger for the blue path as W is an integral of $\int P dV$, which represents the area under the curve. The blue line is further up the pressure axis, so the integral is larger and more work is done.

- What about heat input to the gas, Q_{in} ? Since the First Law says $\Delta U = Q_{\text{in}} + W_{\text{on}} \implies \Delta U = Q_{\text{in}} - W_{\text{by}}$.

ΔU is constant, and $-W_{\text{by}}$ has a larger magnitude for blue, so must Q_{in} to keep ΔU constant.

These transitions are called a *PV Cycle* as we can start at *A*, go to *B* and end back up at *A*.

Consider a simple example with straight lines:




Figure 11.2

Where $1 \rightarrow 2$ and $3 \rightarrow 4$ are isochoric processes and $2 \rightarrow 3$ and $4 \rightarrow 1$ are isobaric. We can also look at isothermal and adiabatic processes:




Figure 11.3

A cycle must follow these rules:

1. $\Delta U = 0$, for a full cycle.
2. Total work done is given by the area contained by the cycle.
3. Clockwise cycle for positive work, anticlockwise for negative work.

4. $Q_{\text{in}} + W_{\text{on}} = 0$ as $\Delta U = 0$.

2 Otto Cycle

This describes a petrol internal combustion engine:




Figure 11.4: Blue: Isobaric, Green: Isochoric, Red: Adiabatic

This has the following components:

1. 1 → 2: Intake stroke: Isobaric introduction of air and fuel to the system.
2. 2 → 3: Adiabatic compression of the fluid as the piston compresses it.
3. 3 → 4: Isochoric introduction of heat energy to the system (ignition of the fluid mixture).
4. 4 → 5: Adiabatic expansion of the fluid mixture as the gas does work on the piston (pushing it down).
5. 5 → 2: Isochoric expulsion of heat from the system.
6. 2 → 1: Mass of air and exhaust gases released at a constant pressure.

3 Diesel Cycle

Here, the ignition and combustion process is performed at a constant pressure where work is done by the gas:




Figure 11.5: Blue: Isobaric, Green: Isochoric, Red: Adiabatic

In both cases, heat is introduced (by combustion) from $3 \rightarrow 4$, denoted Q_1 and heat is lost from $5 \rightarrow 2$ when heat is expelled from the system. The useful work done is $Q_1 - Q_2$ and is given by the area enclosed by the loop.

3.1 Example

Consider the adiabatic gas compression stroke in a diesel engine. (This is the adiabatic stroke where pressure is increasing/volume is decreasing, i.e. from $2 \rightarrow 3$.)

10^{-3} m^3 of nitrogen gas is initially at atmospheric pressure and 298K and is compressed to 1/15th of its original volume.

You may assume that nitrogen is an ideal diatomic gas with $\gamma = 1.4$ and $C_V = 20.85 \text{ J/Kmol}$.

Calculate:

1. The final pressure.
2. The final temperature.
3. The number of moles in the gas.
4. The change in internal energy.
5. The work done by the gas.

Part I

Atmospheric pressure is $101325 \approx 10^5 \text{ Pa}$. As this is an adiabatic transition, $PV^\gamma = \text{const}$. Hence:

$$\begin{aligned}
 P_1 V_1^\gamma &= P_2 V_2^\gamma \\
 \Rightarrow P_2 &= P_1 \left(\frac{V_1}{V_2} \right)^\gamma \\
 \Rightarrow P_2 &= P_1 \left(\frac{V_1}{V_1/15} \right)^\gamma \\
 \Rightarrow P_2 &= P_1 (15)^\gamma = 4.5 \text{ MPa}
 \end{aligned}$$

Part II

We can use either $PV = nRT$ twice, using the initial conditions to determine n or we can use:

$$T_1 V_1^{(\gamma-1)} = T_2 V_2^{(\gamma-1)}$$

Using the same process gives:

$$T_2 = T_1 (15)^{(\gamma-1)} = 880\text{K}$$

Part III

Since we know P_1, V_1 or P_2, V_2 we can use $PV = nRT$, as mentioned above. It would be a good sanity check to do both and compare the values.

Part IV

It's an adiabatic transition, we can related $C_V = \frac{\partial U}{\partial T}$.

Integrating both sides gives:

$$\int dT = \int \frac{\partial U}{\partial T}$$

Thu 26 Feb 2026 13:00

Lecture 12 - Heat Transfer

1 Thermal Transport

Newton's Law of Cooling: "The rate of heat loss of a body is directly proportional to the difference in the temperatures between the body and the environment"

There are three means of thermal transport:

- **Conduction:** Heat is transmitted directly from one material to an adjoining material (or across parts of the same material) if there is a temperature difference between the two. There is no movement of the material.
- **Convection:** Movement of particles through a substances (often particles that comprise a fluid) that transport their heat energy along with them.
 - The Archimedes principle describes buoyancy based on the material's density ρ , g and the volume of the the fluid displaced by the object, V :

$$F_b = \rho g V$$

- In convection, heating a particle causes an increase in bond size (by the LJP), hence the density decreases. This causes it to displace gas of a larger density, hence it rises.
- **Radiation:** Emission of electromagnetic radiation by all bodies which have heat (i.e. all bodies full stop), depending on their temperature.

1.1 Heat Baths

A heat bath is an object with a sufficiently large heat capacity, C such that a large change in its heat energy will result in a negligible change in temperature.

2 Conduction

Suppose we have a small uniform rod of length L and cross-sectional area A linking two heat baths. The rod is conducting and the heat baths have temperature $T_1 < T_2$.




Figure 12.1

Eventually, we reach a “steady state” where all points on the rod have a $\dot{Q}$ which does not change with time.

$$\frac{dQ}{dt} = \dot{Q} = \text{constant}, \quad \forall x \text{ along rod (in steady state)}$$

What does this value of $\dot{Q}$ depend on? For a small section dx of the rod:

- Temperature change of the small section, dT .
- Cross-sectional area of the rod A .
- The “thermal conductivity” of the rod, κ ¹. It has units $\text{Wm}^{-1}\text{K}^{-1}$.

Putting these together gives us Fourier’s Law:

$$\dot{Q} = -\kappa A \frac{dT}{dx}$$

As T_2 is hotter, the flow of heat is from right to left. Therefore until thermalisation occurs, temperature increases from left to right across the rod ($\frac{dT}{dx} > 0$). However, the heat flow is in the opposite direction from right to left, hence the negative sign in the formula for $\dot{Q}$.

We want to show that $\frac{dT}{dx} = \frac{T_2 - T_1}{L}$:

$$\begin{aligned} \dot{Q} &= -\kappa A \frac{dT}{dx} \\ \frac{dT}{dx} &= -\frac{\dot{Q}}{\kappa A} \\ -\int \frac{\dot{Q}}{\kappa A} dx &= \int dT \\ -\int_0^L \frac{\dot{Q}}{\kappa A} &= \int_{T_1}^{T_2} dT \\ -\frac{\dot{Q}}{\kappa A} [x]_0^L &= T_2 - T_1 \\ \frac{dT}{dx} &= \frac{T_2 - T_1}{L} \end{aligned}$$

2.1 Thermal Conductivity

A higher value of κ means a material is more thermally conductive, for example:

- Diamond (natural): $\kappa = 2200 \text{Wm}^{-1}\text{K}^{-1}$.
- Copper: $\kappa = 400 \text{Wm}^{-1}\text{K}^{-1}$.
- Air: $\kappa = 0.02 \text{Wm}^{-1}\text{K}^{-1}$.
- Aerogel: $\kappa = 0.003 \text{Wm}^{-1}\text{K}^{-1}$.

Diamond is highly thermally conductive due to high frequency vibrations (“phonons”) being able to propagate through the material as a result of its rigidity.

There are two sources of heat conductivity, one being as a result of electrons and one as a result of phonons.

- Inside the material, we have two bands - valence and conduction. These bands are a thick collection of many energy levels very close together. As the Pauli exclusion principle says that no two electrons can share a quantum number, each level must shift infinitesimally to not overlap. The levels within each band are so close that we treat electron as being able to move freely between them.
- The valence band is where electrons are still bound to an atom, the conduction band is where they are bound to the material as a whole and are free to move through the material.
- For an insulator, the difference between the two bands is $\sim 10\text{eV}$. This represents a very small proportion of particles with sufficient energy and results in very little thermal excitation (hence little thermal conduction). As an electron is excited, it leaves a hole behind (that we treat as a particle h^+ for ease). We treat this hole as being able to move (as electrons themselves move).

¹We also have another very similar quantity labelled K which will be covered later and may be a source of confusion

- For an electron to fall back to the valence band, it must fall into a hole. In an insulator the conduction band is effectively empty. For a semiconductor, this gap is more like $\sim 1\text{eV}$, so a much higher number of electrons can jump, but this is still temperature dependant.
- In metals, the conduction and valence bands have little to no gap. Therefore, all electrons are free conduction electrons.

Diamonds sit on the boundary between being an insulator and a semiconductor. They work by phonons. As we heat a material, bonds in the material expand and cause a vibration. As diamond is very rigid, vibrating one bond causes a ripple effect - effectively a wave of excitation (where one of these waves is called a phonon). This phonon propagation causes the transfer of vibrations hence the transfer of heat energy.

2.2 Thermal Properties

We can also define the:

- Thermal Resistivity: $\rho = 1/\kappa$.
- Thermal Conductance $K = \kappa A/L$.²
- Thermal Resistance: $R = L/(\kappa A)$.

This are the heat analogues of the equivalent terms for electrical conductance in a circuit.

Annoyingly, thermal conductivity also varies with temperature...It also does so in a really weird way depending on the material:

²This is the aforementioned annoying symbol overlap between κ and K




Figure 12.2: κ for various materials, as a function of temperature.

This comes from phonon excitation and electron excitation being two different competing processes that both have different degrees of contribution at different temperatures.

This means that Newton's Law of Cooling no longer holds for $\kappa = f(T)$, as the proportionality no longer holds...

Tue 03 Mar 2026 12:00

Lecture 13

Recap from last lecture

- Three methods of heat transport: conduction, convection and radiation.
- Fourier's Law:

$$\dot{Q} = -\kappa A \frac{dT}{dx}$$

- We can show that:

$$\frac{dT}{dx} = \frac{T_2 - T_1}{L}$$

- Conduction determined by two distinct physical processes that transfer heat:
 - Movement of electrons.
 - Photon transfer.
- Thermal resistivity, thermal conductance and thermal resistance, acting as analogues of their electrical equivalents.

1 Conduction II

1.1 Combinations of Thermal Resistances

A derivation of why isn't examinable (but is shown in the non-assessed problems), but we have the same rules for Thermal Resistances as we do in electrical resistances:

- Thermal resistances add in series, $R_T = R_1 + R_2 + \dots R_n$.
- Thermal resistances add in inverse when in parallel $1/R_T = 1/R_1 + 1/R_2 + \dots + 1/R_n$.

1.2 Example: Pipe Lagging

Consider a solid copper pipe of radius r_0 , initial temperature T_0 and length L . We surround this pipe with insulation of initial temperature T_1 and resulting in a new radius r_1 . The insulation has $\kappa = 0.05 \text{ Wm}^{-1} \text{ K}^{-1}$ and the system is in a steady state.

We start from Fourier's law:

$$\dot{Q} = -\kappa A \frac{dT}{dr}$$

As the pipe is a cylinder:

$$\begin{aligned} \dot{Q} &= -\kappa(2\pi r l) \frac{dT}{dr} \\ - \int_{r_0}^{r_1} \frac{\dot{Q}}{2\kappa\pi r l} &= - \int_{T_0}^{T_1} dT \\ \int_{r_1}^{r_0} \frac{\dot{Q}}{2\kappa\pi l} \frac{dr}{r} &= \int_{T_1}^{T_0} dT \\ \frac{\dot{Q}}{2\kappa\pi l} [\ln r]_{r_0}^{r_1} &= [T]_{T_1}^{T_0} \end{aligned}$$

$$\frac{\dot{Q}}{2\kappa\pi l} \ln\left(\frac{r_0}{r_1}\right) = T_0 - T_1$$

$$\dot{Q} = (T_0 - T_1) \frac{2\kappa\pi l}{\ln(r_1/r_0)}$$

2 Convection



Figure 13.1

Consider a fluid suspended between two plates, distance L apart. The upper plate T_C is colder than the lower plate, T_H .

What governs whether or not convection can occur (and to what extent)?

- Buoyancy of the fluid $\beta = \frac{1}{V} \left(\frac{\partial V}{\partial T} \right)_P$
- The thermal conductivity, κ .
- The viscosity of the fluid, η .

To decide whether or not convection can occur, we use the Rayleigh number:

$$R_A = \frac{\rho L^3 (\beta \{T_H - T_C\}) g}{\eta \alpha}$$

Where:

$$\alpha = \frac{\kappa}{\rho C_P}$$

If $R_A > 1,000$ then convection occurs laminarly, and if $R_A > 100,000$ then convection occurs turbulently. Convection does not occur $R_A < 1,000$. Laminar flow is simple, predictable and consistent flow (i.e. straight out of a well made tap). Turbulent flow is much more complex and is pseudorandom. We can predict statistical effects, but turbulent flow is too complex to predict accurately to a very low level.

The details of convection (except for the basic concept) are not examinable.

3 Thermal Radiation

All bodies emit EM radiation characteristic of the object temperature (and not the temperature of the surroundings). The frequency is temperature dependant. We often use infrared (i.e. thermal imaging) as the frequencies are emitted by an object around the temperature of a human body are IR.

A black body perfectly emits and absorbs radiation of all wavelengths, without any reflection. A white body, on the other hand, perfectly reflects all incident light. A black body in thermal equilibrium with surroundings emits exactly the same power spectrum as it absorbs.

Classical mechanics predicts the Rayleigh-Jeans law for emission:

$$u(\lambda, T) = \frac{8\pi k_B T}{\lambda^4}$$

Where u is power emitted per unit area, T is temperature and λ is the wavelength of emitted light. As this is inversely proportional to λ , this causes the UV catastrophe, where $u \rightarrow \infty$ as $\lambda \rightarrow 0$. Max Planck developed an improved version¹.

$$u(\lambda, T) = \frac{8\pi hc}{\lambda^5} \frac{1}{\exp\left(\frac{hc}{\lambda k_B T}\right) - 1}$$

We can characterise non-black bodies by the emissivity, ϵ , the fraction of the black body spectrum which it absorbs. This gives $\epsilon = 1$ for a true black body and $\epsilon = 0$ for a true white body.

4 Wein's Approximation

We want to determine the maximum of the spectrum, to find the wavelength corresponding to the maximal power output.

$$u(\lambda, T) = \frac{8\pi hc}{\lambda^5} \frac{1}{\exp\left(\frac{hc}{\lambda k_B T}\right) - 1}$$

Letting $a = \frac{hc}{\lambda k_B T}$:

$$\begin{aligned} \frac{1}{\lambda} &= \frac{k_B T}{hc} a \\ \Rightarrow \frac{1}{\lambda^5} &= \left(\frac{k_B T}{hc}\right)^5 a^5 \\ \Rightarrow \frac{8\pi hc}{\lambda^5} &= 8\pi hc \left(\frac{k_B T}{hc}\right)^5 a^5 \end{aligned}$$

And:

$$\frac{1}{\exp\left(\frac{hc}{\lambda k_B T}\right) - 1} = \frac{1}{\exp(a) - 1}$$

$$\frac{\partial a}{\partial \lambda} = \frac{-hc}{\lambda^2 k_B T} = -\frac{1}{\lambda} \frac{hc}{\lambda k_B T} = -\frac{a}{\lambda}$$

Hence:

$$u(\lambda, T) = \underbrace{8\pi hc \left(\frac{k_B T}{hc}\right)^5}_{\text{constant} = C} a^5 \times \frac{1}{\exp(a) - 1}$$

$$u(\lambda, T) = \frac{Ca^5}{e^a - 1}$$

$$\frac{\partial u}{\partial \lambda} = \frac{\partial a}{\partial \lambda} \frac{d}{da} \left[\frac{Ca^5}{e^a - 1} \right]$$

$$= \frac{-a}{\lambda} \frac{d}{da} \left[\frac{Ca^5}{e^a - 1} \right]$$

¹See QM1

Using the quotient rule:

$$\frac{d}{da} \left[\frac{Ca^5}{e^a - 1} \right] = \frac{5Ca^4(e^a - 1) - Ca^5e^a}{(e^a - 1)^2}$$

Therefore:

$$\frac{\partial u}{\partial \lambda} = \frac{-a}{\lambda} \left[\frac{5Ca^4(e^a - 1) - Ca^5e^a}{(e^a - 1)^2} \right]$$

Solving for the maxima:

$$\frac{\partial u}{\partial \lambda} = 0$$

$$-a(5Ca^4(e^a - 1) - Ca^5e^a) = 0$$

As C is a non-zero constant:

$$-a(5a^4(e^a - 1) - a^5e^a) = 0$$

As $a \neq 0$:

$$5a^4(e^a - 1) - a^5e^a = 0$$

Dividing by a^4 :

$$5(e^a - 1) - ae^a = 0$$

$$5e^a - 5 - ae^a = 0$$

$$(5 - a)e^a = 5$$

Solving numerically:

$$a \approx 4.965$$

$$a = \frac{hc}{\lambda k_B T}$$

$$\lambda_{\max} T = \frac{hc}{k_B a}$$

Finally:

$$\lambda_{\max} T \approx 2.898 \times 10^{-3} \text{ m K}$$

Thu 05 Mar 2026 13:00

Lecture 14 - Statistical Physics I: Introduction

1 Stefan-Boltzmann Law

We can integrate across the whole spectrum to work out total energy emitted per unit time:

$$\dot{Q} = \epsilon \sigma A T^4$$

Where $\sigma = 5.67 \times 10^{-8} \text{Wm}^{-2}\text{K}^{-1}$ is the Stefan-Boltzmann constant, ϵ is the emissivity, A is the surface area of the radiating body and T is the temperature.

2 Kinetic Theory of Gases

We've now finished the module on temperature and move into statistical physics. We start with a kinetic theory of the motion of gas molecules. Gas molecules move "randomly" (effectively, it's not computationally viable to determine what's actually going on), with vastly different velocities and positions.

We would love to describe a gas using the individual molecules that make it up, but that's really difficult to do for $\sim 10^{23}$ molecules so it's not viable and we have to use statistical physics to describe it.

We've previously touched upon the Maxwell-Boltzmann distribution to describe the velocities of particles as a statistical distribution wrt temperature:




Figure 14.1

These statistical approximations improve as we increase the number of particles, and for very large numbers they become good approximations. We can in statistical physics have a probability > 1 . This seems mathematically strange, but we interpret it to mean that (if the probability represents the probability of an event occurring in a measurement), the event will take place multiple times. We still cannot have any probabilities < 0 .

The rest of the lecture then turned into a fun tangent on statistics which isn't examinable and needs no notes.

Tue 10 Mar 2026 12:00

Lecture 15 - Statistical Physics II: The Atmosphere

1 The Atmosphere

The very outer part of the atmosphere, from 90km to 350km is the ionosphere. This acts as a mirror which reflects EM radiation




Figure 15.1

This is how we're able to do international radio communications, by bouncing radio waves off of this layer in order to reach continents where there is no direct line of sight.

1.1 Isothermal Model of the Atmosphere

Consider an observer sitting in the troposphere above the earth, looking at a small cuboidal slice of the troposphere.

We will assume that:

- The atmosphere is isothermal. In reality, increasing height reduces temperature by approx. 10K per km.
- The atmosphere is solely comprised of an ideal gas. At the low pressure scales relevant for the atmosphere, this is a reasonable assumption.

- The earth is flat¹. Technically, assume that we consider small enough heights and cross-sectional areas that we can disregard the curvature of the earth.
- The atmosphere is stationary and is therefore in mechanical equilibrium. This can be a good approximation depending on weather conditions.

The slab of atmosphere we're considering has area A , height dh and sits at height h above the surface of the earth. From the ideal gas state equation:

$$\begin{aligned}
 PV &= \underbrace{nRT}_{\text{moles}} = \underbrace{Nk_B T}_{\text{particles}} \\
 \implies P &= \frac{N}{V} k_B T \\
 \implies P &= \rho_N k_B T
 \end{aligned}$$

Where $\rho_N = N/V$ is number density, and is defined as the number of molecules per unit volume.

The slab of atmosphere has two forces acting upon it, a force due to pressure and a force due to gravity. As we assume that slice is in mechanical equilibrium, we can equate these forces.

The pressure is going to vary across the slab. Force due to pressure increases the further down into the atmosphere you go. As the slab is in mechanical equilibrium, the force due to gravity must also vary across the slab in the opposite manner.*****

This gives us:

force due to gravity = force due to pressure

$$mg\rho_N V = AP(h) - AP(h + dh)$$

$$mg\rho_N V = -dP(h)A$$

$$mg\rho_N \times dh \times A = -d\rho(h)A$$

$$mg\rho_N \times dh = -d\rho(h)$$

$$\frac{d\rho(h)}{dh} = -mg\rho_N$$

$$\int d\rho(h) = - \int mg\rho_N dh$$

And considering number density in the density integral:

$$\int_{\rho(0)}^{\rho(h)} \frac{1}{\rho_N} d\rho(h) = - \int_0^h mg dh$$

And substituting $d\rho = d\rho_N k_B T$ to give a LHS integral entirely in number density:

$$\int_{\rho_N(0)}^{\rho_N(h)} \frac{k_B T}{\rho_N} d\rho_N = -mgh$$

$$\int_{\rho_N(0)}^{\rho_N(h)} \frac{k_B T}{\rho_N} d\rho_N = -\frac{mgh}{k_B T}$$

$$[\ln(\rho_N)]_{\rho_N(0)}^{\rho_N(h)} = -\frac{mgh}{k_B T}$$

$$\frac{\rho_N(h)}{\rho_N(0)} = \exp\left(-\frac{mgh}{k_B T}\right) \implies \boxed{\rho_N(h) = \rho_N(0) \exp\left(-\frac{mgh}{k_B T}\right)}$$

¹Oh dear...

Thu 12 Mar 2026 13:00

Lecture 16 - Statistical Physics III: Atmosphere and Boltzmann Factors

Recap from last lecture:

- We derived:

$$\rho_N(h) = \rho_N(0) \exp\left(-\frac{mgh}{k_B T}\right)$$

$$P(h) = P(0) \exp\left(-\frac{mgh}{k_B T}\right)$$

To give the number density and pressure as an exponential function of height in the atmosphere.

- Since $mgh/k_B T$ is being passed into an exponential, it must be dimensionless. Hence $k_B T/mg$ must have dimensions of h .
- This leads to the scale height h_0 where $P(h_0) = P(0)/e$

1 Atmosphere Continued

We have established that the number density (number of fluid molecules per unit volume), at height 0, $\rho_N(0)$ can be related to atmospheric pressure ($P_{\text{at}} = P(0)$) by:

$$\rho_N(0) = \frac{P_{\text{atmospheric}}}{k_B T}$$

To determine the total number of gas molecules in the slab of atmosphere with cross-sectional area A , we can integrate number density across all h :

$$\begin{aligned} N &= A \int_0^\infty \rho_N(h) dh \\ &= A \int_0^\infty \rho_N(0) \exp\left(-\frac{mgh}{k_B T}\right) dh \\ &= A \rho_N(0) \int_0^\infty \exp\left(-\frac{mgh}{k_B T}\right) dh \\ &= A \rho_N(0) \left[-\frac{k_B T}{mg} \exp\left(-\frac{mgh}{k_B T}\right) \right]_0^\infty \\ &= -A \rho_N(0) \frac{k_B T}{mg} [0 - 1] \\ N &= A \rho_N(0) \frac{k_B T}{mg} \\ \Rightarrow \rho_N(0) &= \frac{Nmg}{Ak_B T} \end{aligned}$$

And using:

$$h_0 = \frac{k_B T}{mg}$$

$$\rho_N(0) = \frac{N}{Ah_0}$$

This has a physical definition, being the average number density of the slab of atmosphere between $h = 0$, $h = h_0$

We further define a new quantity:

$$\text{Pr}(h) = \frac{A\rho_N(h)}{N}$$

Which gives the probability of (for a particle) finding it at height h

1.1 Probability Normalisation

We start from:

$$\text{Pr}(h) = \frac{A\rho_N(h)}{N}$$

$$h_0 = \frac{k_B T}{mg}$$

$$\rho_N(h) = \rho_N(0) \exp(-mgh/k_B T)$$

Hence:

$$\text{Pr}(h) = \frac{A}{N} \times \frac{N}{Ah_0} \exp(-mgh/k_B T)$$

$$\text{Pr}(h) = \frac{mg}{k_B T} \exp(-mgh/k_B T)$$

2 Boltzmann Factors

This is on the exam. We have the quantity $mgh/k_B T$, which is dimensionless. What does this quantity actually mean? mgh is a term for the potential energy (gravitational in this example), $k_B T$ is the thermal energy

Tue 17 Mar 2026 12:00

Lecture 17 - Statistical Physics IV: Boltzmann Factors and Degeneracies

Recap from last lecture:

- We can predict the microscopic behaviour of a system using a probability density function defined using macroscopic terms.
- We can predict the likelihood of a given energy state being populated for a system (discrete or continuous) with the Boltzmann factor.
- For a two level system with $E_1 < E_0$ we have:

$$Pr(E_i) = \frac{\exp\left(\frac{-E_i}{k_B T}\right)}{\exp\left(\frac{-E_0}{k_B T}\right) + \exp\left(\frac{-E_1}{k_B T}\right)}$$

- For a system with N levels, we have:

$$Pr(E_i) = \frac{\exp\left(\frac{-E_i}{k_B T}\right)}{\sum_{j=0}^{N-1} \exp\left(\frac{-E_j}{k_B T}\right)}$$

1 Degeneracies

In an atom, electrons can have the same energy in multiple different combinations (multiple ways of having the same result). For example, considering only one energy level, electrons can be spin up or spin down. This gives two possible options, hence a degeneracy of two.

With electrons in shells, the degeneracy gives the number of electrons which can fit in a shell. The Pauli exclusion principle says that no two atoms can occupy a shell if they share a quantum number, so the number of possible combinations of distinct states is equal to the number of possible electrons in the shell.

Given the degeneracy $g(E)$, we can modify the Boltzmann Factor accordingly:

$$Pr(E_i) \propto g(E) \exp\left(\frac{-E_i}{k_B T}\right)$$

For $n = 1$, $g(E) = 2$, for $n = 2$, $g(E) = 4$, and so on.

2 Boltzmann Factors and Ideal Gases

For an ideal gas, we have some assumptions (in terms of energy) that have been discussed previously. The most important of these in terms of energy is:

- Internal energy all comes from the average kinetic energy of the molecules (temperature) and not from potential energy.
- The Boltzmann Factor for an ideal gas hence takes the form:

$$Pr(E_i) \propto \exp\left(\frac{-E_K}{k_B T}\right)$$

Our other assumptions are:

1. The gas is in thermal equilibrium, hence $\langle E_K \rangle$ is constant.
2. No gravity (as molecules are extremely light).
3. Assume that the average separation of each molecule is much larger than the molecule size, hence collisions are infrequent.
4. There is a very large number of molecules $\sim 10^{23}$ to allow us to treat the gas statistically without high statistical uncertainties.
5. All molecules have the same mass and size. This is not a good assumption for gases made up of multiple component gases mixed.
6. We assume that the direction of molecular motion is effectively random, i.e. is unbiased to any particular direction.
7. Molecules can collide, but do so elastically (and as previously mentioned, infrequently).
8. Molecules are not relativistic, so $E_K = 0.5mv^2$ holds.

3 Model of Ideal Gas

We can split the velocity of a gas into three cartesian coordinates by adding in quadrature:

$$v = \sqrt{v_x^2 + v_y^2 + v_z^2}$$

By assumption 6, we assume that all of these components are effectively equal, so we can consider the x-direction alone initially (and extrapolate out).

We want to consider the probability of having a velocity somewhere between v_x and $v_x + dx$.

$$\begin{aligned} \Pr(v_x \rightarrow v_x + dx) &= \int_{v_x}^{v_x+dx} \Pr(v + x) dv_x \\ &= \int_{v_x}^{v_x+dx} C \exp\left(-\frac{0.5mv_x^2}{k_B T}\right) dv_x \end{aligned}$$

And using the standard integral: $\int_{-\infty}^{\infty} e^{-ax^2} dx = \sqrt{\pi/a}$:

3.1 Density of States

While we had no degeneracies in each component direction, we do have degeneracies for v itself. For example, $v^2 = 100$ could mean that x, y are zero and z = 10, or any other number of combinations.

We therefore want to define the degeneracies as a function of v . As a model, consider a grid of infinitesimally small dots in 2D (but for the actual application we would want a 3D model). For some radius, we can count the number of dots which are present on the circumference:

Applying this to the Maxwell-Boltzmann distribution, we obtain:

$$\Pr(v) = 4\pi \left(\frac{m}{2\pi k_B T}\right)^{3/2} v^2 \exp\left(-\frac{mv^2}{2k_B T}\right) \quad \text{where: } v \neq 0$$

This finally gives us the Maxwell-Boltzmann distribution we encountered before (although we have derived it for molecules vs moles):




Figure 17.1

Tue 17 Mar 2026 12:00

Lecture 18 - Statistical Physics V

Recap from last lecture:

Tue 24 Mar 2026 12:00

Lecture 19 - Statistical Physics VI: Something or Other