


Converting a 2D seismic line to a point set with attributes


In some situations you might need to convert your seismic data into a set of points, for instance, when you want to perform a crossplot and the client doesn't have QI xplot. Another possibility would be to export the seismic line as an ASCII file. Regardless of the reasons, the following workflow can help you accomplish that:




And here's the explanation for the workflow:

Line(s)	Description
1	Define the Seismic sample rate (usually 4ms)
2	Define which 2D seismic line will be converted
3-7	Create a polygon from the seismic line layout, convert it to points, and keep the house clean
8-9	Get Z (or t) minimum and maximum from the 2D seismic
10	Move the pointset previously created to the position of the first sample of seismic.
11	Create a "base" set of points which we are going to use to "move" through all sample positions
12	Define the number of samples (trace samples)
13-16	Keep adding a translated "base" pointset to our final point set. This will create a set of points with the exact same geometry as the original seismic line
17-18	Get the seismic amplitude and assign it as an attribute to the pointset we have just created
19-22	Housecleaning

In the end you should get a result similar to this:



Where the image on the right actually is a point set with attributes:



Observation:

Although this workflow can be used to implement some rudimentary crossplots, its performance is far worse than QI's. This workflow does not substitute the crossplot feature from QI, and should be seen as just a quick and low cost way of getting what the client wants, with the tools at hand.