

Windows 11 Keybindings

Learn these first

Win	Start; just type to search
Alt + Tab	Cycle windows (Shift: back)
Win + 1..9	Open / focus taskbar app N
Win + ←/→	Snap left / right
Win + ↑/↓	Maximize / restore, minimize
Win + Ctrl + ←/→	Previous / next desktop
Alt + F4	Close window
Win + E	File Explorer
Win + V	Clipboard history
Win + Shift + S	Screenshot a region
Win + L	Lock

Open a terminal

Win + 1	Terminal pinned in taskbar slot 1
Win + Shift + 1	New terminal window
Win + X	then I: Terminal · A: admin
Win + R	type wezterm or wt
Win + `	Windows Terminal quake drop-down

Ctrl + Shift + Enter In Start: run as admin
Pin terminal 1st, browser 2nd. A Start-menu shortcut can carry its own Ctrl+Alt+letter hotkey (Properties → Shortcut key).

Windows & snapping

Win + Shift + ←/→	Window to other monitor
Win + Shift + ↑	Stretch to full height
Win + Z	Snap layouts; number picks zone
Win + D	Show desktop
Win + M	Minimize all (Shift: restore)
Win + Home	Minimize all but active
Win + Tab	Task view
Alt + Space	Window menu: M move, S size
Win + Ctrl + 1..9	Last window of app N
Win + Alt + 1..9	Jump list of app N
Win + T	Walk the taskbar
Win + B	Walk the tray icons

Virtual desktops

Win + Ctrl + D	New desktop
Win + Ctrl + ←/→	Switch desktop
Win + Ctrl + F4	Close desktop (windows move left)
Win + Tab	Overview; Shift+F10 on a window → Move to
Win + Tab + Tab	Desktop row: F2 rename, Delete close

No default key jumps to desktop N or sends a window there.

Without the mouse

Tab	Next control (Shift: previous)
←↓→	Move in lists, menus, groups
Space	Toggle checkbox, press button
Enter	Default button / open
Esc	Cancel, close menu or dialog
Alt	Tap: show access-key letters
Alt + letter	Underlined button or field
F10	Focus the menu bar
Shift + F10	Right-click menu
F6	Cycle panes (Explorer, browser)

Ctrl + Tab	Next tab in apps and dialogs
Win + I	Settings, then type to search

Browser

Ctrl + L	Address bar
Ctrl + T/W	New / close tab
Ctrl + Shift + T	Reopen closed tab
Ctrl + 1..8/9	Tab N / last tab
Alt + ←/→	Back / forward
Ctrl + F	Find on page
`	Firefox: quick find in links

Tridactyl or Vimium: f puts a letter hint on every link.

System

Win + R	Run: cmd, pwsh, regedit
Win + X	Power-user menu
Win + I	Settings
Win + A	Quick settings: wifi, sound, bt
Win + N	Notifications, calendar
Ctrl + Shift + Esc	Task Manager
Win + P	Display mode
Win + K	Cast
Win + .	Emoji, symbols, kaomoji
Win + H	Dictation
Win + PrtSc	Full screenshot to Pictures
Win + Alt + R	Record screen (Game Bar)
Win + G	Game Bar
Win + Ctrl + Shift + B	Restart graphics driver
Win + +	Magnifier (Win+Esc: off)

File Explorer

Alt + ↑	Parent folder
Alt + ←/→	Back / forward
Ctrl + L	Address bar (type pwsh for a shell)
Ctrl + T/W	New / close tab
Ctrl + Shift + N	New folder
F2	Rename
Ctrl + Shift + C	Copy path
Alt + Enter	Properties
Shift + Del	Delete, skip Recycle Bin

Text editing

Ctrl + ←/→	Jump by word
Ctrl + Backspace	Delete word back
Ctrl + Del	Delete word forward
Shift + Home/End	Select to line start / end
Ctrl + Home/End	Top / bottom
Ctrl + Shift + V	Paste plain text (many apps)
Ctrl + Z/Y	Undo / redo

IME & input languages

Win + Space	Next input language / IME
Win + Shift + Space	Previous
Alt + Shift	Switch language (if enabled)
Ctrl + Shift	Switch layout (if enabled)

Japanese (Microsoft IME)

Alt + `	IME on / off (あ ↔ A)
Ctrl + Caps	Hiragana
Alt + Caps	Katakana

Laptop keys in every section · HHKB Hybrid Type-S chords at the end

Space	Convert / candidate list
Enter/Esc	Confirm / cancel
Tab	Predictions
Shift + ←/→	Resize segment
F6/F7/F8	ひらがな / カタカナ / かな
F9/F10	Full / half-width romaji

Caps is Fn+Tab on the HHKB. IME settings → Key and touch customization can put IME on/off on Ctrl+Space.

Chinese (Pinyin)

Shift	中 / 英 mode
Ctrl + Space	IME on / off
Shift + Space	Full / half width
Ctrl + .	Chinese / English punctuation

Korean

Right Alt	한 / 영
Right Ctrl	Hanja

Drill: two windows → desktop 3, 50/50

1	Win + Ctrl + D	Repeat until desktop 3 exists
2	Win + Ctrl + ←	Back to where the windows are
3	Win + Tab	Task View
4	←/→	Highlight the window
5	Shift + F10	Its menu (HHKB: Shift+Fn+O)
6	↓ ... →	Move to , open the list
7	↓ ... Enter	Desktop 3
8	4-7	Same for the other window, then Esc
9	Win + Ctrl + →	Go to desktop 3
10	Alt + Tab	Focus the first window
11	Win + ←	Snap it to the left half
12	→ ... Enter	Snap Assist fills the right half

Instead of 11-12: Win+Z, 1, then 1 or 2. Resize the split: Alt+Space, S, arrows, Enter.

HHKB Hybrid Type-S

HHK mode: ◇ is Win. No arrows or F-keys, they live on the Fn layer.

◇	Win
Fn + [; ' /	↑ ← → ↓
Fn + K / ,	Home / End
Fn + L / .	PgUp / PgDn
Fn + 1..=	F1-F12
Fn + I	PrtSc
Fn + Tab	Caps Lock

Laptop shortcut → HHKB chord

◇ + Fn + ; / '	Win+←/→ snap
◇ + Fn + [/ /	Win+1/↓ maximize, minimize
◇ + Ctrl + Fn + ; / '	Win+Ctrl+←/→ switch desktop
◇ + Ctrl + Fn + 4	Win+Ctrl+F4 close desktop
◇ + Shift + Fn + ; / '	Win+Shift+←/→ other monitor
◇ + Fn + K	Win+Home minimize others
◇ + Fn + I	Win+PrtSc full screenshot
Alt + Fn + 4	Alt+F4 close window
Shift + Fn + 0	Shift+F10 right-click menu
Fn + 2	F2 rename
Fn + 6	F6 cycle panes
Alt + Fn + [	Alt+↑ parent folder
Alt + Fn + ; / '	Alt+←/→ back / forward
Ctrl + Fn + ; / '	Ctrl+←/→ jump by word
Shift + Fn + K / ,	Shift+Home/End select line
Ctrl + Fn + Tab	Ctrl+Caps hiragana
Fn + 6..0	F6-F10 IME conversion

Tip: PowerToys Keyboard Manager can map Right ◇ to the Menu key, a one-key Shift+F10.