# **Operating Systems**

# 9. CPU: Synchronization (1)

Hyunchan, Park

http://oslab.chonbuk.ac.kr

Division of Computer Science and Engineering

**Chonbuk National University** 

### Contents

- Background
- Problem: Race condition
- The Critical Section
  - Peterson's Solution
- Hardware Support for Synchronization
- Synchronization mechanisms
  - Mutex Locks
  - Semaphores
  - Monitors



# Background

- Processes can execute concurrently
  - Both on uni-processor and multi-processor systems (or single- and multi-core systems)
  - May be interrupted at any time, partially completing execution
- Concurrent access to shared data may result in data inconsistency
- Maintaining data consistency requires mechanisms to ensure the orderly execution of cooperating processes



# Background

- Illustration of the problem:
  - Suppose that we wanted to provide a solution to the consumer-producer problem that fills all the buffers
  - We can do so by having an integer counter that keeps track of the number of full buffers
  - Initially, counter is set to 0.
  - It is incremented by the producer after it produces a new buffer and is decremented by the consumer after it consumes a buffer



### Producer

```
while (true) {
       /* produce an item in next produced */
      while (counter == BUFFER SIZE) ;
             /* do nothing */
      buffer[in] = next produced;
       in = (in + 1) % BUFFER SIZE;
      counter++;
```



### Consumer

```
while (true) {
    while (counter == 0); /* do nothing */

    next_consumed = buffer[out];
    out = (out + 1) % BUFFER_SIZE;
    counter--;
    /* consume the item in next consumed */
}
```



### Race Condition

counter++ could be implemented as

```
register1 = counter
register1 = register1 + 1
counter = register1
```

counter -- could be implemented as

```
register2 = counter
register2 = register2 - 1
counter = register2
```

Consider this execution interleaving with "count = 5" initially:

```
• S0: producer execute register1 = counter
S1: producer execute register1 = register1 + 1
S2: consumer execute register2 = counter
S3: consumer execute register2 = register2 - 1
S4: producer execute counter = register1
S5: consumer execute counter = register2

{register1 = 5}
{register1 = 5}
{register2 = 5}
{register2 = 4}
{counter = 6}
```



### **Critical Section**

- Consider system of n processes  $\{p_0, p_1, ..., p_{n-1}\}$
- Each process has critical section segment of code
  - Process may be changing common variables, updating table, writing file,
     etc
  - When one process in critical section, no other may be in its critical section
- Critical section problem is to design protocol to solve this
- Each process must ask permission to enter critical section in entry section, may follow critical section with exit section, then remainder section



### **Critical Section**

• General structure of process  $P_i$ 

```
do {
     entry section
          critical section
     exit section
          remainder section
} while (true);
```



# Example: Algorithm for Process Pi

```
do {
    while (turn == j);
        critical section
    turn = j;
    remainder section
} while (true);
```



### Solution to Critical-Section Problem

#### Three conditions to be satisfied for the CS solution

- Assume that each process executes at a nonzero speed
- No assumption concerning relative speed of the n processes

#### 1. Mutual Exclusion

• If process  $P_i$  is executing in its critical section, then no other processes can be executing in their critical sections



### Solution to Critical-Section Problem

#### 2. Progress

 If no process is executing in its critical section and there exist some processes that wish to enter their critical section, then only those processes that are not executing in their remainder sections can participate in deciding which will enter the critical section next, and this selection cannot be postponed indefinitely

#### 3. Bounded Waiting

A bound must exist on the number of times
 that other processes are allowed to enter their critical sections
 after a process has made a request to enter its critical section and before
 that request is granted

# Problem with two processes

- Shared variables:
  - int turn = 0; (initial value)
  - When **turn = 0**,  $P_0$  enters the critical section
- Process  $P_0$

```
while (turn != 0);
critical section
turn = 1;
remainder section
```

Process P<sub>1</sub>

```
while (turn != 1);
critical section
turn = 0;
remainder section
```

- Satisfied: mutual exclusion, bounded waiting
- Unsatisfied : progress
  - If P<sub>1</sub> is scheduled before P<sub>0</sub> at starts of executions



### Problem with two processes: another algorithm

- Shared variables:
  - boolean flag[2]; flag [0] = flag [1] = false (initial value)
  - When flag [0] = true,  $P_0$  enters the critical section
  - When flag [1] = true,  $P_1$  enters the critical section
- Process  $P_0$

```
flag[0] = true;
while (flag[1]);
    critical section
flag[0] = false;
    remainder section
```

Process P<sub>1</sub>

```
flag[1] = true;
while (flag[0]);
    critical section
flag[1] = false;
    remainder section
```

- Satisfied: mutual exclusion, bounded waiting
- Unsatisfied : progress
  - Two flags can be set as TRUE at same time



### Peterson's Solution

- Good algorithmic description of solving the problem
- Assume that the load and store machine-language instructions are atomic; that is, cannot be interrupted
- The two processes share two variables:
  - int turn;
  - Boolean flag[2]
- The variable turn indicates whose turn it is to enter the critical section
- The flag array is used to indicate if a process is ready to enter the critical section. flag[i] = true implies that process P<sub>i</sub> is ready!



### Problem with two processes: Peterson's solution

- Shared variables:
  - int turn = 0; boolean flag[2]; flag [0] = flag [1] = false (initial value)
  - When flag [0] = true and turn = 0,  $P_0$  enters the critical section
  - When flag [1] = true and turn = 1,  $P_1$  enters the critical section
- Process  $P_0$

```
flag [0] = true;
turn = 1;
while (flag [1] && (turn == 1));
    critical section
flag [0] = false;
    remainder section
```

Process P<sub>1</sub>

```
flag [1] = true;
turn = 0;
while (flag [0] && (turn == 0));
    critical section
flag [1] = false;
    remainder section
```

Satisfied: mutual exclusion, progress, bounded waiting



### Peterson's Solution: Limitation

- How about with more than three processes?
  - Hard to implement
  - Hard to prove that it satisfies all the three conditions
  - There is an assumption: atomic Load and Store instructions

We need more general and simple solution





# Critical-Section Handling in OS

- Two approaches depending on if kernel is preemptive or nonpreemptive
  - Preemptive: allows preemption of process when running in kernel mode
  - Non-preemptive: runs until exits kernel mode, blocks, or voluntarily yields CPU
    - Essentially free of race conditions in kernel mode
- Preemptive kernel is more preferred, but hard to implement
  - Pros: More responsiveness for the processes
  - Cons: Need to manage the shared kernel data structures with finegrained manner
    - Can be slow down for the management



# Synchronization Hardware

- Many systems provide hardware support for implementing the critical section code.
- All solutions below based on idea of locking
  - Protecting critical regions via locks
- Uniprocessors could disable interrupts
  - Currently running code would execute without preemption
  - Generally too inefficient on multiprocessor systems
    - · Operating systems using this not broadly scalable
- Modern machines provide special atomic hardware instructions
  - Atomic = non-interruptible (or indivisible)
  - Either test memory word and set value
  - Or swap contents of two memory words



# Solution to Critical-section Problem Using Locks



# test\_and\_set Instruction

#### **Definition:**

```
boolean test_and_set (boolean *target)
{
    boolean rv = *target;
    *target = TRUE;
    return rv:
}
```

- 1.Executed atomically
- 2. Returns the original value of passed parameter
- 3.Set the new value of passed parameter to "TRUE".



# Mutual exclusion using test\_and\_set()

- Shared Boolean variable lock, initialized to FALSE
- Solution:



# compare\_and\_swap Instruction

#### Definition:

```
int compare_and_swap(int *value, int expected, int new_value){
    int temp = *value;
    if (*value == expected)
        *value = new_value;
    return temp;
}
```

- 1.Executed atomically
- 2. Returns the original value of passed parameter "value"
- 3.Set the variable "value" the value of the passed parameter "new\_value" but only if "value" == "expected". That is, the swap takes place only under this condition.

# Mutual exclusion using compare\_and\_swap

- Shared integer "lock" initialized to 0;
- Solution:

### Example: Bounded-waiting Mutual Exclusion with test\_and\_set()

```
/* Process P, ,
Initialization: waiting[all], key, lock = false*/
do {
   waiting[i] = true;
   key = true;
   while (waiting[i] && key)
      key = test and set(&lock);
   waiting[i] = false;
   /* critical section */
```



#### Example: Bounded-waiting Mutual Exclusion with test\_and\_set()

```
next = (i + 1) % n;
  while ((next != i) && !waiting[next])
     next = (next + 1) % n;
  if (next == i)
      lock = false;
  else
     waiting[next] = false;
  /* remainder section */
} while (true);
```



# Synchronization Hardware: Limitation

- Mutual exclusion is easily solved and implemented with HW support
  - The others (progress, bounded waiting) must be solved by SW

We need the more comprehensive synchronization mechanisms



# Synchronization mechanisms

- Mutex locks
- Semaphore
- Monitor



# Mutex lock (spinlock)

- Simplest solution
  - Previous solutions are complicated and generally inaccessible to application programmers
  - OS designers build software tools to solve critical section problem
- Protect a critical section by first acquire() a lock then release()
   the lock
  - Boolean variable indicating if lock is available or not
- Calls to acquire() and release() must be atomic
  - Usually implemented via hardware atomic instructions
- Cons: requires busy waiting
  - This lock therefore called a spinlock



# acquire() and release()

```
• acquire() {
       while (!available)
          ; /* busy wait */
       available = false;;
• release() {
       available = true;
```

# Semaphore

- Synchronization tool that provides more sophisticated ways (than Mutex locks) for process to synchronize their activities.
- Semaphore S integer variable
- Can only be accessed via two indivisible (atomic) operations
  - wait() and signal() (or P() and V())

```
wait(S) {
    while (S <= 0);
        // busy wait
    S--;
}</pre>
```

```
signal(S) {
    S++;
}
```

# Semaphore Usage

#### Counting semaphore

• Integer value can range over an unrestricted domain

#### Binary semaphore

- Integer value can range only between 0 and 1
- Same as a mutex lock
- Can solve various synchronization problems



# Semaphore Usage

• Consider  $P_1$  and  $P_2$  that require  $S_1$  to happen before  $S_2$ Create a semaphore "synch" initialized to 0 P1:  $S_1;$ signal(synch); P2: wait(synch); S<sub>2</sub>;

Can implement a counting semaphore S as a binary semaphore



### Semaphore Implementation: Binary semaphore

- Binary semaphore with Test-and-Set instruction
- Semaphore S: if True, there is a process inside the critical section (True or False)
- P(S)
  - while(testandset(&S));
  - Current value of S is returned, and S is changed to True
- V(S)
  - S = false;
  - Enables that the process waiting with Wait() can be entered into critical section



### Semaphore Implementation: Counting semaphore

- Counting semaphore implementation using Binary semaphore
  - CS: Counting semaphore, value is C
  - Two binary semaphore S1, S2
  - Initialize S1 = 1, S2 = 0, C = n
    - (n is number of co-executed process in critical section)

#### wait operation

signal operation

```
P(S1);
C++;
if (C <= 0) {
      V(S2);
}
V(S1);
```

# Semaphore Implementation

- Must guarantee that no two processes can execute the wait()
   and signal() on the same semaphore at the same time
- Thus, the implementation becomes the critical section problem where the wait and signal code are placed in the critical section
  - Could now have busy waiting in critical section implementation
    - But implementation code is short
    - Little busy waiting if critical section rarely occupied
- Note that applications may spend lots of time in critical sections and therefore this is not a good solution



### Semaphore Implementation with no Busy waiting

- With each semaphore there is an associated waiting queue
- Each entry in a waiting queue has two data items:
  - value (of type integer)
  - pointer to next record in the list

```
typedef struct{
  int value;
  struct process *list;
} semaphore;
```

#### Two operations:

- block place the process invoking the operation on the appropriate waiting queue
- wakeup remove one of processes in the waiting queue and place it in the ready queue



# Implementation with no Busy waiting (Cont.)

```
wait(semaphore *S) {
    S->value--;
    if (S->value < 0) {
        add this process to S->list;
        block();
    }
}
```

```
signal(semaphore *S) {
   S->value++;
   if (S->value <= 0) {
      remove a process P from S->list;
      wakeup(P);
   }
}
```

# **Problems with Semaphores**

- Incorrect use of semaphore operations:
  - signal (mutex) .... wait (mutex)
  - wait (mutex) ... wait (mutex)
  - Omitting of wait (mutex) or signal (mutex) (or both)

Deadlock and starvation are possible.



### Deadlock and Starvation

- Deadlock two or more processes are waiting indefinitely for an event that can be caused by only one of the waiting processes
- Let s and g be two semaphores initialized to 1

```
P<sub>0</sub>
wait(Q);
wait(S);
...
signal(Q);
signal(S);
```

```
P<sub>1</sub>
wait(S);
wait(Q);
...
signal(S);
signal(Q);
```



### Deadlock and Starvation

- Starvation indefinite blocking
  - A process may never be removed from the semaphore queue in which it is suspended
- Priority Inversion Scheduling problem when lower-priority process holds a lock needed by higher-priority process
  - Solved via priority-inheritance protocol



### **Monitors**

- A high-level abstraction that provides a convenient and effective mechanism for process synchronization
  - Abstract data type, internal variables only accessible by code within the procedure
  - Only one process may be active within the monitor at a time

- Pros: Easy to use
- Cons: But not powerful enough to model some synchronization schemes



### **Monitors**


```
monitor monitor-name
{
    // shared variable declarations
    procedure P1 (...) { ..... }

    procedure Pn (...) { ......}

    Initialization code (...) { ... }
}
```



### Schematic view of a Monitor






### **Condition Variables**

- condition x, y;
- Two operations are allowed on a condition variable:
  - x.wait() a process that invokes the operation is suspended until
     x.signal()
  - x.signal() resumes one of processes (if any) that invokedx.wait()
    - If no x.wait() on the variable, then it has no effect on the variable



### **Monitor with Condition Variables**





### **Condition Variables Issues**

- If process P invokes x.signal(), and process Q is suspended in x.wait(), what should happen next?
  - Both Q and P cannot execute in paralel. If Q is resumed, then P must wait
- Options include
  - Signal and wait P waits until Q either leaves the monitor or it waits for another condition
  - Signal and continue Q waits until P either leaves the monitor or it waits for another condition
  - Both have pros and cons language implementer can decide
  - Monitors implemented in Concurrent Pascal compromise
    - P executing signal immediately leaves the monitor, Q is resumed
  - Implemented in other languages including Mesa, C#, Java

