MIRAI BANK PROJECT

Milestone 2 [B1]

User Interface Functional Design Document

Table of Contents

0. Scope of Implementation in the Milestone 3 Prototype 3

0.1 Comparison of Prototype and Production Implementations 4

0.2 Screen IDs 5

1. Screens and Screenshots 7

1.1 SCREEN-01 Login 7

1.2 SCREEN-02 First-Time Registration 8

1.3 SCREEN-03 Dashboard 9

1.4 SCREEN-04 Capsule Creation 10

1.5 SCREEN-06 Piece Registration 12

1.6 SCREEN-08 NFT Confirmation 13

1.7 SCREEN-09 Opening Viewer 16

1.8 SCREEN-10 Wallet Information 18

2. Wallet Connection (Corresponding to: B1-1) 20

3. Data Registration (Corresponding to: B1-4) 21

4. NFT Finalization and Transaction Status (Corresponding to: B1-2 and B1-3) 23

5. Opening Viewer (Corresponding to: B1-5) 26

6. Mapping Between Screens and the Backend 27

7. Functions Implemented in Production 28

8. Summary 29

0. Scope of Implementation in the Milestone 3 Prototype

This document distinguishes two stages of implementation using the terms "prototype" and "production." The prototype refers to the system developed in Milestone 3. It runs on the Cardano Preprod testnet, and the opening decision is made by the server (Node.js) without using Aiken. Production refers to the production environment built in the full development that follows the prototype. It runs on Cardano Mainnet and introduces Aiken validators. Section 0.1 summarizes the overall comparison, and Section 0.2 shows the screen IDs used in Milestone 1 and in this document.

This document defines the screens and operations of the prototype, narrowing the full user interface design (eleven screens for smartphones and PCs) to the scope needed for the prototype. The screenshots in this document are taken from the UI prototype (an HTML mock-up for PC browsers). The narrowing is made on the condition that it does not contradict the basic design established in Milestone 1 (the four-layer conceptual model, the three-role permission model, and the confirmed design decisions). The data model and design decisions themselves are unchanged; only the scope of the UI and implementation is narrowed.

Item	Full Design (Production)	Prototype (Minimal Configuration)
Devices	Smartphones plus PCs and tablets	PC browsers only
Number of screens	11 screens	6 screens (plus login and first-time registration)
Supported wallets	Lace, Eternl, and other CIP-30 wallets	Lace only

Item	Full Design (Production)	Prototype (Minimal Configuration)
Capsule types	Single (SOLO) and group (REAL)	Single (SOLO) only
Piece types	Text, images, and files	One text, image (JPEG or PNG), or PDF; images and PDFs up to 1 MB
Approval flow (SCREEN-07)	Approval or rejection by the capsule owner	Not included (in a single capsule, the registrant is the capsule owner)
Manager operations (SCREEN-05)	A dedicated screen for piece slot progress and permitted operations by state	Not included (integrated into SCREEN-03 (Dashboard))
Group management (SCREEN-11)	Invitations, role changes, distribution of master certificates	Not included
Opening mode	Choice of ① registrant only, ② managers together, ③ emergency opening	Fixed to ① (modes ② and ③ are kept in the data model; only the UI choice is omitted)
Transaction status	Five states and eight failure reason codes	Three states (pending, confirmed, failed) with an error message and a reason code
Fee display	Breakdown by cost item	Network fee, data storage cost, and total
Connection state display	Six states (not connected, connecting, mismatch, awaiting signature, connected, failed)	A simple flow from the connect button to registration

Table 0-1 Full Design and the Prototype

0.1 Comparison of Prototype and Production Implementations

Table 0-2 summarizes the differences between the prototype and production implementations of the screens and operations.

Item	Prototype (Milestone 3)	Production
Devices	PC browsers only	Smartphones plus PCs and tablets
Supported wallets	Lace only	Lace, Eternl, and other CIP-30 wallets
Network	Cardano Preprod testnet	Cardano Mainnet
Screens	6 screens plus login and first-time registration	All 11 screens of the full design
Capsules and pieces	Individual capsules only. One piece per capsule (text, image, or PDF; images and PDFs up to 1 MB); opening mode ① only	Individual and group capsules. Text, images, and files (limits by type and plan); opening modes ①, ②, and ③
Display of NFT information	Asset name, policy ID, and an explorer link on SCREEN-03 (Dashboard), SCREEN-08 (NFT Confirmation), and SCREEN-09 (Opening Viewer)	The same, plus detailed transaction status and step-by-step verification status
Notification of openable capsules	None (evaluated at the time of the opening operation)	Notification when a capsule becomes openable
Minimum opening date/time	Current time plus 1 hour (can be shortened to 5 minutes with the test setting)	Current time plus 1 hour
Disclosure of trust assumptions	SCREEN-01 (Login) states that opening decisions are made by the operator's server	Not needed, because opening decisions are made by Aiken validators

Table 0-2 Comparison of Prototype and Production Implementations (Screens and Operations)

0.2 Screen IDs

The screen IDs and names in this document follow those of the Milestone 1 UI and

Operations Research Report (Output B1). Table 0-3 shows the correspondence and which screens are implemented in the prototype.

Screen ID	Name in Milestone 1	Name in This Document	Prototype
SCREEN-01	QR Login	Login	Implemented. The prototype runs on PC browsers only and connects through the Lace browser extension, so no QR code is used
SCREEN-02	First-Time Registration	First-Time Registration	Implemented
SCREEN-03	Dashboard	Dashboard	Implemented (including the per-user NFT list)
SCREEN-04	Capsule Creation	Capsule Creation	Implemented
SCREEN-05	Manager Operations	—	Not implemented (integrated into SCREEN-03)
SCREEN-06	Piece Registration	Piece Registration	Implemented (text, image, or PDF)
SCREEN-07	Piece Approval Management	—	Not implemented (no approval in single capsules)
SCREEN-08	NFT Confirmation	NFT Confirmation	Implemented (including NFT information after issuance)
SCREEN-09	Opening Viewer	Opening Viewer	Implemented
SCREEN-10	Wallet Information	Wallet Information	Implemented
SCREEN-11	Group Management	—	Not implemented (production)

Table 0-3 Screen IDs and Names

1. Screens and Screenshots

The prototype consists of wallet connection (two gate screens) and the application itself (six screens). The following sections show, in the order of screen transitions, a screenshot of each screen, a description, and a table of its elements and the corresponding Milestone 3 acceptance criteria.

1.1 SCREEN-01 Login




Figure 1-1 SCREEN-01 Login

On this screen, which corresponds to the QR Login screen of the full design, the user clicks "Connect with Lace wallet" to start connecting the wallet. Users are identified by their wallet address only, and no password is required. The top of the screen states that this is a

prototype, its scope (PC browsers only, individual capsules only), and that in the prototype opening decisions are made by the operator's server (Cardano testnet only).

Item	Content
Purpose	Establish a connection with a Cardano wallet (CIP-30 compliant) and authenticate the user with the wallet address as the user ID.
Main roles	All users (not yet connected)
Screen elements	"Connect with Lace wallet" button; notice about the prototype (PC only, individual capsules only, opening decisions made by the operator's server, testnet only)
Milestone 3 acceptance criteria	A1-1 User management and wallet connection

Table 1-1 Elements and Acceptance Criteria of SCREEN-01 Login

1.2 SCREEN-02 First-Time Registration




Figure 1-2 SCREEN-02 First-Time Registration

After connecting, a first-time user registers only a nickname. Optional items such as affiliation and notification e-mail are omitted in the prototype, reducing the required input to one item.

Item	Content
Purpose	Register a nickname at the first connection and automatically create the user's personal (SOLO) group.
Main roles	All users
Screen elements	Confirmation of the connection, nickname field (one required item), "Register and start" button
Milestone 3 acceptance criteria	A1-1 User management and wallet connection

Table 1-2 Elements and Acceptance Criteria of SCREEN-02 First-Time Registration

1.3 SCREEN-03 Dashboard




Figure 1-3 SCREEN-03 Dashboard

The starting screen, showing the list of certificates (NFTs) and capsules held by the user. For sealed and opened capsules, it shows the asset name of the certificate, the policy ID (shortened), and a "View on explorer" link, so that the screen functions as a per-user NFT list. Capsules before finalizing (DRAFT) are shown as "Certificate: not issued." The group

list tab is omitted because group functions are out of scope.

Item	Content
Purpose	**The starting screen for checking the certificates (NFTs) and capsules held by the user.**
Main roles	**All users**
Screen elements	**Summary of registered items; list of certificates (NFTs) and capsules (status badge, opening date, asset name, shortened policy ID, "View on explorer" link); "Create a new capsule" button**
Display by state	**DRAFT: "Certificate: not issued (before finalizing)." Sealed and opened: asset name, policy ID, and explorer link**
Milestone 3 acceptance criteria	**A2-1 User management and dashboard (per-user NFT list); A1-2 NFT display**

Table 1-3 Elements and Acceptance Criteria of SCREEN-03 Dashboard

1.4 SCREEN-04 Capsule Creation




Figure 1-4 SCREEN-04 Capsule Creation

Only the title, the opening date/time, and the storage are entered. The opening date/time is specified as a date and time, at least one hour and at most 100 years from now. In an environment where the test setting is enabled, the minimum can be shortened to five minutes (Chapter 3). The choice of group, opening mode, and forced-sealing threshold is out of scope; the opening mode is fixed to ① (registrant only), and the screen says so.

Item	Content
Purpose	Enter the basic information of an individual (single) capsule and create it in the DRAFT state.
Main roles	All users (the creator becomes the capsule owner)
Screen elements	Fields for title, opening date/time (date and time), and storage (display only); explanation of the constraints on the opening date/time; notice that the opening mode is fixed to ①
Input constraints	The opening date/time must be at least 1 hour and at most 100 years from now. With the test setting enabled, it can be set from 5 minutes from now (Chapter 3)
Milestone 3 acceptance criteria	A2-2 Registration and display of "thoughts"

Table 1-4 Elements and Acceptance Criteria of SCREEN-04 Capsule Creation

1.5 SCREEN-06 Piece Registration




Figure 1-5 SCREEN-06 Piece Registration (with an Image Selected)

The user chooses the type from the "Text," "Image," and "PDF" tabs and registers one item. For text, the body is entered (up to 100 KB); for images (JPEG or PNG) and PDFs, a file is selected or dragged and dropped (up to 1 MB). The name, type, and size of the selected file are displayed, and a file that exceeds the limit or has the wrong format cannot be registered. The encryption progress display and the approval request step are out of scope, and saving is simplified to a single step. Encryption on the device (AES-256-GCM) itself is kept as a mandatory requirement.

Item	Content
Purpose	Register one text, image, or PDF, encrypt it on the device, upload it, and save it.
Main roles	All users (the registrant of the piece)

Item	Content
Screen elements	Type tabs (text, image, PDF); body field (text); file selection and drag-and-drop area (images and PDFs); name, type, and size of the selected file; notice about encryption; "Save and continue" button
Input constraints	Text up to 100 KB. Images in JPEG or PNG and PDFs only, each up to 1 MB. The format is checked using the file type and its leading bytes
Milestone 3 acceptance criteria	A1-3 Data storage (encryption); A2-2 Registration and display of "thoughts"

Table 1-5 Elements and Acceptance Criteria of SCREEN-06 Piece Registration

1.6 SCREEN-08 NFT Confirmation




Figure 1-6 SCREEN-08 NFT Confirmation (Before Signing)




Figure 1-7 SCREEN-08 NFT Confirmation (Pending)




Figure 1-8 SCREEN-08 NFT Confirmation (Confirmed)




Figure 1-9 SCREEN-08 NFT Confirmation (Failed)

After confirming the content, the user signs with the wallet to issue the certificate (NFT). Before signing, the screen shows the estimated network fee for minting, the data storage cost, and their total. After signing, the screen shows one of three states: pending, confirmed, or failed. When issuance is confirmed, it shows the asset name, policy ID, transaction hash, and network, with a link to confirm the issuance on a Cardano explorer. When it fails, it shows an error message, the reason code, and a button to issue again, and the content that was entered is kept.

Item	Content
Purpose	**Confirm the content, sign with the wallet, and issue one certificate (NFT). After issuance, show the NFT information.**

Item	Content
Main roles	Capsule owner
Screen elements	Confirmation of the capsule information (including the encryption method, AES-256-GCM); estimated cost (network fee, data storage cost, and total); warning; "Sign with wallet and issue" button; status display for pending, confirmed, and failed; on confirmation, the NFT information (asset name, policy ID, transaction hash, network) and the "View on Cardano explorer" link; on failure, the error message, the reason code, and the "Issue again" button
Milestone 3 acceptance criteria	A1-2 NFT issuance and display (testnet)

Table 1-6 Elements and Acceptance Criteria of SCREEN-08 NFT Confirmation

1.7 SCREEN-09 Opening Viewer




Figure 1-10 SCREEN-09 Opening Viewer (Text)




Figure 1-11 SCREEN-09 Opening Viewer (Image)

The content of a capsule whose opening date/time has passed is displayed according to the type of the piece. Text is shown as the body; images are shown on screen and can be downloaded; PDFs open in the browser's PDF viewer and can be downloaded. In addition to "Verified: the content is unchanged since sealing," the verification banner shows the asset name and policy ID of the certificate and a link to the explorer. The detailed display of decryption steps and displays related to modes ② and ③ are out of scope.

Item	Content
Purpose	Decrypt, verify, and display the content of the piece of a capsule whose opening date/time has passed.
Main roles	All users
Screen elements	Capsule name and opening date; verification banner ("Verified," asset name and policy ID of the certificate, explorer link); content of the piece (text as the body; images on screen with a download

Item	Content
	button; PDFs in the browser PDF viewer with a download button)
When content is not shown	If the opening date/time has not been reached, or if the database and the NFT metadata do not match (Output A1, Section 4.3), the content is not shown and the reason is displayed
Milestone 3 acceptance criteria	A1-3 Display (decryption); A2-2 Registration and display of "thoughts"

Table 1-7 Elements and Acceptance Criteria of SCREEN-09 Opening Viewer

1.8 SCREEN-10 Wallet Information




Figure 1-12 SCREEN-10 Wallet Information

This screen shows basic information about the connected wallet (wallet type, balance, network, and number of capsules held). The list of certificates (NFTs) is shown on SCREEN-03 (Dashboard), so this screen shows only the count.

Item	Content
Purpose	Check basic information about the connected wallet.
Main roles	All users
Screen elements	Nickname and address; wallet type (Lace), balance, and network; number of capsules held; "Log out" button
Milestone 3 acceptance criteria	A1-1 User management and wallet connection

Table 1-8 Elements and Acceptance Criteria of SCREEN-10 Wallet Information

2. Wallet Connection (Corresponding to: B1-1)

In the prototype, Lace is the only supported wallet. To limit the combinations of test items and functional checks, the prototype supports one wallet. The connection uses the common CIP-30 interface (the Mesh SDK's BrowserWallet), and no processing specific to a particular wallet is written. As a result, adding Eternl and other wallets in production requires only adding connect buttons.

Process	Treatment in the Prototype
Detecting and connecting the wallet	Call CIP-30 wallet.enable(). If Lace is not installed, guide the user to install it. The six state messages of the full design are handled as a simple "connecting" transition
Network check	The check with getNetworkId() is kept. If the network is not Preprod, guide the user to switch to Preprod in Lace's settings
Signature login	The flow GET /api/auth/challenge → signData() → POST /api/auth/verify is kept
First-time check	If not registered, go to the first-time registration screen. The automatic creation of the personal (SOLO) group is kept

Table 2-1 Handling of Wallet Connection

3. Data Registration (Corresponding to: B1-4)

Data registration consists of two screens: SCREEN-04 Capsule Creation and SCREEN-06 Piece Registration. Because only single capsules are in scope, the automatic creation of piece slots and the approval flow do not occur.

Input	Required	Validation and Storage
Title	Yes	1 to 60 characters. Project.title
Opening date/time	Yes	Specified as date and time. Minimum: current time plus 1 hour (plus 5 minutes where the test setting is enabled). Maximum: current time plus 100 years. Project.unlockAt
Storage	—	Fixed to IPFS in the prototype (the selector is display only)
Piece	Yes	One text, image, or PDF. Text up to 100 KB; images (JPEG or PNG) and PDFs up to 1 MB. The format is checked using the file type and leading bytes. Encrypted on the device with AES-256-GCM before upload

Table 3-1 Input Items for Data Registration

The test setting changes the minimum through a server environment variable (e.g., UNLOCK_MIN_MINUTES), and the screen validates input against the minimum received from the server. It is used for functional testing and for recording the Milestone 3 demonstration video; the default (one hour) is unchanged.

Registration has two stages. Pressing "Save and continue" on SCREEN-06 encrypts the piece on the device, uploads it, and leaves the capsule in the DRAFT state. This is the temporary save: the content can still be replaced or discarded, and SCREEN-03 shows the capsule as "Certificate: not issued (before finalizing)." Final registration takes place on

SCREEN-08, where the user signs with the wallet: the capsule moves to the LOCKED state, the certificate (NFT) is issued, and the content can no longer be changed (Chapter 4). The step of submitting a piece for a manager's approval, which exists in the full design, does not occur: in a single capsule the registrant is also the capsule owner (as defined in the Milestone 1 design), so omitting it does not contradict the basic design.

4. NFT Finalization and Transaction Status (Corresponding to: B1-2 and B1-3)

This chapter defines what the user is shown before signing (the estimate of the fees) and after signing (the status of the transaction). Because each capsule has one piece, the split minting of multiple NFTs and the progress display required in the full design are unnecessary.

Before signing, SCREEN-08 shows the estimate broken down as in Table 4-1. Both the network fee for minting the NFT and the cost of storing the data are shown, so that the user confirms the total before the transaction is built. The basis for each amount is defined in Output A1, Chapter 7, and for the storage cost in Output A2, Section 2.5.3.

Cost item	Shown on screen
Network fee (NFT minting)	About 1.5 ADA. The transaction fee plus the minimum ADA carried by the NFT, estimated from the transaction built with the Mesh SDK
Data storage cost (IPFS)	0 ADA, with the note that it is not charged to users in the prototype. Pinning is an operating cost of the service (Output A2, Section 2.5.3)
Estimated total	The sum of the two amounts above, shown with a warning that the content cannot be changed after finalizing

Table 4-1 Fee Items Shown Before Signing

After signing, the screen shows one of the three states in Table 4-2. The state is determined by polling the inclusion of the transaction through Blockfrost every 20 seconds, and it is also reflected on SCREEN-03 (Dashboard).

State	Display
Before finalizing	The estimate in Table 4-1 and a warning that the content cannot be changed
Processing (pending)	A message that the transaction has been submitted and that confirmation is awaited (usually 1 to 2 minutes), with the transaction hash. The "Sign with wallet and issue" button is disabled so that the same transaction is not sent twice
Completed (confirmed)	The message "The certificate (NFT) has been issued," plus the asset name, policy ID, transaction hash, and network, and a link to a Cardano explorer
Failed (failed)	An error message that states the reason in plain words, the reason code (Table 4-3), and an "Issue again" button. The capsule stays in the DRAFT state and the content that was entered is kept

Table 4-2 Display of the Transaction Status

Four reason codes are used in the prototype (Table 4-3). The eight reason codes of the full design are narrowed to the cases that can arise with one capsule and one piece; the remaining codes are added in production (Chapter 7). Every message states what happened, whether the content was kept, and what the user can do next.

Reason code	When it occurs	Message shown
SIGN_REJECTED	The user rejects the signature in the wallet, or closes the wallet window	The signature was rejected in the wallet. What you entered has been kept. Please try issuing again.
INSUFFICIENT_ADA	The wallet does not hold enough ADA for the fee and the minimum ADA	There is not enough ADA in the wallet. About 1.5 ADA is needed, including the network fee.
TX_REJECTED	The node rejects the submitted transaction, for	The transaction was not accepted. Please wait a moment and try issuing again.

Reason code	When it occurs	Message shown
	example because the inputs have already been spent	
TIMEOUT	The transaction is not included within its validity period (2 hours)	Confirmation did not finish within the time limit. Please check the status on the explorer, and issue again if the transaction was not included.

Table 4-3 Reason Codes and Messages Shown on Failure

The explorer link opens the asset or transaction page on an explorer for Preprod (e.g., CardanoScan Preprod). The policy ID and transaction hash are shortened on screen to their first and last characters, and the full values can be checked on the linked page.

5. Opening Viewer (Corresponding to: B1-5)

For a capsule whose opening date/time has passed, the content of its piece is displayed according to its type (text as the body; images on screen with a download option; PDFs in the browser PDF viewer with a download option). Because the opening mode is fixed to ① (registrant only), the manager path and the approval flow for emergency opening (mode ③) of the full design do not occur.

- **Verification banner:**

  In addition to "Verified: the content is unchanged since sealing," the banner shows the asset name and policy ID of the certificate and a link to the explorer.

- **Decryption steps:**

  The four-step display (identity check, retrieval, tamper check, decryption) is out of scope; only the result is shown.

- **Situational displays:**

  Of the situational displays (no certificate, insufficient agreement, and so on), only "opening date/time not reached" and "reconciliation mismatch (key not released)" can occur in the prototype. Displays related to mode ③ are out of scope.

6. Mapping Between Screens and the Backend

Screen	Main APIs	Chapter
SCREEN-01 Login	POST /api/auth/challenge, verify	2
SCREEN-02 First-Time Registration	POST /api/me (first-time registration, automatic creation of the personal group)	2
SCREEN-03 Dashboard	GET /api/projects (including assetName, policyId, and mintTxHash)	1.3
SCREEN-04 Capsule Creation	POST /api/projects (the minimum opening date/time is validated against the server setting)	3
SCREEN-06 Piece Registration	POST /api/storage/upload, POST /api/keys/:pieceId, PATCH .../pieces/:pid	3
SCREEN-08 NFT Confirmation	GET .../fee-estimate (simplified), POST /api/projects/:id/lock, POST .../lock/submit	4
SCREEN-09 Opening Viewer	GET .../verify, GET .../pieces, POST /api/keys/:pieceId/release	5
SCREEN-10 Wallet Information	GET /api/me, POST /api/auth/logout	1.8

Table 6-1 Mapping Between Screens and the Backend

7. Functions Implemented in Production

The following functions are consistent with the Milestone 1 basic design (data model and design decisions) but are excluded from the prototype and implemented in production.

Function	How It Is Handled in Production
Group (REAL) capsules and group management (SCREEN-11)	The confirmed Milestone 1 design (four-layer model and three roles) applies as is
Piece approval management (SCREEN-07)	The approval flow design is unchanged; UI components validated with single capsules can be reused
Images over 1 MB, files other than PDF, multiple pieces per capsule	The validation rules and limits of the full design (production limits in Output A2, Table 2-4) apply
Opening modes ② and ③ and emergency opening	The extended Datum fields are already retained; only the choice in the UI and the approval flow for mode ③ need to be added
The remaining transaction states and reason codes, and the fee breakdown by cost item	The prototype implements three states and four reason codes (Chapter 4). The five states, the eight reason codes, and the breakdown by cost item of the full design can be reused as is
Wallets other than Lace (Eternl, etc.)	Implemented through the common CIP-30 interface, so only connect buttons need to be added
Notification of openable capsules	A scheduled opening monitoring job and notification e-mail (Output A1, Section 3.5)

Table 7-1 Functions Implemented in Production

8. Summary

This document defines, as Milestone 2 Output B1, the user interface of the prototype and its relationship with the backend. The prototype is limited to PC browsers and individual (single) capsules, and the full design of eleven screens is narrowed to six screens plus login and first-time registration, without contradicting the Milestone 1 basic design. Each screen is presented with a screenshot, a description, and a table of its elements. Wallet connection is limited to Lace through the common CIP-30 interface, and a piece can be a text, an image, or a PDF. So that users can check the issued certificates (NFTs) on screen, NFT information and explorer links are shown on SCREEN-03 (Dashboard), SCREEN-08 (NFT Confirmation), and SCREEN-09 (Opening Viewer), and SCREEN-01 (Login) discloses that opening decisions are made by the operator's server in the prototype. Before signing, SCREEN-08 shows the network fee and the data storage cost with their total; after signing it shows the pending, confirmed, and failed states, with a message and a reason code when issuance fails. The status of each Milestone 2 acceptance criterion is shown in Table 8-1, and the correspondence between the screens and the Milestone 3 acceptance criteria in Table 8-2.

Acceptance Criterion	How It Is Addressed	Reference
B1-1 User management and wallet integration	Connection through CIP-30 and the Mesh SDK (Lace in the prototype), signature login, first-time registration with automatic creation of the personal group, and wallet information	Chapter 2, Sections 1.1, 1.2, and 1.8
B1-2 Transaction status feedback UI	Three states (pending, confirmed,	Chapter 4,

Acceptance Criterion	How It Is Addressed	Reference
	failed); on confirmation the asset name, policy ID, transaction hash, and explorer link; on failure an error message with one of four reason codes	Section 1.6
B1-3 Estimation and confirmation of network fees	Estimate shown before signing, broken down into the network fee for minting the NFT and the cost of storing the data, with the total and a warning	Chapter 4, Section 1.6
B1-4 File selection, temporary save, and final registration	Selection of a text, image, or PDF with format and size checks and encryption on the device; temporary save in the DRAFT state; final registration by signing on SCREEN-08	Chapter 3, Sections 1.4 to 1.6
B1-5 Recording and display of time conditions	Input and validation of the opening date/time (including the test setting), display of opening dates on SCREEN-03 (Dashboard), and SCREEN-09 (Opening Viewer) after the date/time has passed	Chapters 3 and 5, Sections 1.3 and 1.7
Relationship between screens and the backend	Mapping of each screen to the main APIs	Chapter 6

Table 8-1 Status of Response to the Acceptance Criteria

Milestone 3 Acceptance Criterion	Screens and Functions	Reference
A1-1 User management and wallet connection	SCREEN-01 Login (Lace connection and signature login), SCREEN-02 First-Time Registration, SCREEN-10 Wallet Information	Sections 1.1, 1.2, and 1.8; Chapter 2
A1-2 NFT issuance and display (testnet)	SCREEN-08 NFT Confirmation (issuance and NFT information on completion);	Section 1.6; Chapter 4

Milestone 3 Acceptance Criterion	Screens and Functions	Reference
	NFT information on SCREEN-03 Dashboard and SCREEN-09 Opening Viewer	
A1-3 Data storage (encryption) and display (decryption)	SCREEN-06 Piece Registration (encryption on the device and storage on IPFS); SCREEN-09 Opening Viewer (decryption and verification)	Sections 1.5 and 1.7; Chapters 3 and 5
A2-1 User management and dashboard (NFT list)	SCREEN-03 Dashboard (list of certificates and capsules held)	Section 1.3
A2-2 Registration and display of "thoughts" for each NFT	SCREEN-04 Capsule Creation, SCREEN-06 Piece Registration, SCREEN-09 Opening Viewer	Sections 1.4, 1.5, and 1.7

Table 8-2 Screens and the Milestone 3 Acceptance Criteria