Use-After-Free Vulnerability

Introduction

Generally speaking, use-after-free (also known as dangling pointer), is a condition when a program attempts to use a reference that points to an invalid object because it is already freed. In the real world, use-after-frees are bugs due to incorrect reference counting, which is supposed to be a common programming technique for tracking references in C/C++.

Use-after-free is considered highly exploitable, because in many cases, the attacker probably has enough time to inject an arbitrary payload into a specific region of memory, before that memory is used again. However, if this window of opportunity does not exist, then it's a denial-of-service at best.

Applications that support scripting, such as a browser, PDF reader, Flash player, etc, are more likely to have use-after-frees that are exploitable in theory, because you tend to have control of when to create an object, free it, when to use it again, also preparing for the ideal heap layout for arbitrary code execution, etc.

Sometimes you can also find use-after-free vulnerabilities on server-side applications, but normally they are much harder to exploit due to less control.

Reference Counting

Reference counting is a way to manage an object's lifetime. The idea is rather simple: every time you have a new copy of a reference for an object, you add one to a reference counter. If a reference is no longer needed, then minus one. When this count becomes zero, then the object is freed. Many Windows applications would probably use the IUnknown interface to do this, and use the AddRef() method to increment the counter, Release() to decrement.

An example of using reference counting:

```
void SomeFunction(Object* obj) {
   Object* newObj = obj;
   newObj->AddRef();
   newObj->SomeFunction();
   newObj->Release();
}
```

Discovering Use-After-Free

To discover use-after-free vulnerabilities, you would either audit the source code or reverse-engineer the binary, and pay attention to whether the application is correctly following the general rules of reference counting. According to Microsoft, these rules are:

- AddRef() must be called for every new copy of an pointer.
- Release() must be called for every destruction of a pointer
- In-out parameters to function: The caller must call AddRef() on the parameter.
- Fetching a global variable: When creating a local copy of a pinter from an existing copy of the pointer in a global variable, you must call AddRef() on the local copy, because another function might destory the copy oin the global variable while the local copy is still valid.
- New pointers synthesized out of thin air: A function that synthesizes a pinter using special internal knowledge rather than obtaining it from some other source must call AddRef() initially on the newly synthesized pointer.
- Retrieving a copy of an internally stored pointer: When a function retrives a copy of a pointer
 that is stored internally by the object called, that object's code must call AddRef() on the
 pointer before the function returns.

Fuzzing is also a common way to find use-after-free bugs. Usually, a test case would involve creating some object, and attempt to use and/or manipualte it, garbage collecting would also be needed to hopefully trigger that condition. For example, if we are fuzzing against a browser, you might want to create some element using CreateElement, and then try to access the methods, pass it to other JavaScript functions, and trigger frees such as CollectGarbage, innerHTML, document.write(), etc, and hopefully one of those combinations will find you a use-after-free.

Some publicly known fuzzers to consider:

- Domato
- funfuzz
- Web-browser-fuzzer
- Grinder

Debugging Use-After-Free

A very typical use-after-free crash would look like the following (in WinDBG)

```
0:000> r
eax=08332ff0 ebx=00d1c000 ecx=74beb560 edx=05740000 esi=00bbf63c edi=00bbf744
eip=00aleff9 esp=00bbf638 ebp=00bbf744 iopl=0 nv up ei pl zr na pe nc
cs=0023 ss=002b ds=002b es=002b fs=0053 gs=002b efl=00010246
ComClientExample!TestComServerSample+0x189:
00aleff9 8b08 mov ecx,dword ptr [eax] ds:002b:08332ff0=???????
```

We see that the value of EAX is $0 \times 0 \times 332$ fto, and is being dereferenced, which indicates this is a pointer. However, this pointer doesn't really take us to a valid memory location, hence the crash. Also, the <code>!address eax</code> command would tell us this is on the heap.

If we look at the instructions a little further, usually it would be this:

```
00aleff9 8b08 mov ecx,dword ptr [eax]; we crash here
00aleffb 8b55e0 mov edx,dword ptr [ebp-20h]
00aleffe 52 push edx
00alefff 8b411c mov eax,dword ptr [ecx+1Ch]
00alf002 ffd0 call eax
```

Notice after the dereference, the program wants to call <code>[ECX+1Ch]</code>, this indicates that the invalid memory is supposed to hold some kind of object where <code>ECX+1Ch</code> is an offset to that object's method.

Usually, the next step is to find out what caused the memory to be freed. To do this, we can use WinDBG's GFlags tool, and enable page heap and create user mode stack trace database:

```
gflags.exe /i VulnerableProgram.exe +ust +hpa
```

Next, we run the program and let it crash again at the dereference. This time, we can use the !heap command to find out who is responsible for the freed memory:

```
0:000> !heap -p -a eax
   address 08332ff0 found in
    DPH HEAP ROOT @ 5741000
   in free-ed allocation ( DPH_HEAP_BLOCK:
                                                    VirtAddr
                                                                     VirtSize)
                                    8252c64:
                                                     8332000
                                                                          2000
   5490ae02 verifier!AVrfDebugPageHeapFree+0x000000c2
   77a02fe1 ntdll!RtlDebugFreeHeap+0x0000003e
   77962745 ntdll!RtlpFreeHeap+0x000000d5
   77962312 ntdll!RtlFreeHeap+0x00000222
    5407c397 MSVCR120D! free base+0x00000027
[f:\dd\vctools\crt\crtw32\heap\free.c @ 50]
    5408d4ff MSVCR120D!_free_dbg_nolock+0x000004cf
[f:\dd\vctools\crt\crtw32\misc\dbgheap.c @ 1431]
    5408cffe MSVCR120D! free dbg+0x0000004e
[f:\dd\vctools\crt\crtw32\misc\dbgheap.c @ 1265]
    5429c1b2 mfc120ud!operator delete+0x00000012
[f:\dd\vctools\vc7libs\ship\atlmfc\src\mfc\afxmem.cpp @ 328]
*** WARNING: Unable to verify checksum for C:\Users\sinn3r\Documents\Visual
Studio 2013\Projects\ComServerExample\Debug\ComServerExample.dll
    53e0af0c ComServerExample!ATL::CComObject<CHelloWorld>::`scalar deleting
destructor'+0x0000003c
    53e0e9cf ComServerExample!ATL::CComObject<CHelloWorld>::Release+0x0000006f
[c:\program files (x86)\microsoft visual studio 12.0\vc\atlmfc\include\atlcom.h @
29341
```

So the most key information of the above backtrace is this line:

```
ComServerExample!ATL::CComObject<CHelloWorld>::Release
```

This tells us that the crash we are looking at is due to a <code>CHelloworld</code> object getting freed, and then some other code is still trying to use that again. At this point, we have enough explanation for a use-after-free.

Remember that in reference counting, an object is only freed when that reference count becomes zero. So to fix this type of problem, the program could add a <code>IHelloWorldObject->AddRef()</code> before the <code>Release()</code>, then it would keep the object alive.

Exploiting Use-After-Free

So the whole point of exploiting a use-after-free is being able to keep that crash alive. Since the object is gone due to the referenece count being zero, we need to supply a fake one in order to keep that crash alive.

To acheive this, we can take advantage of the fact that the operating system would tend to fill spaces (or holes) in memory, this means we could potentially create a memory block of the same object size, and then have something at offset [ECX+1Ch] to keep the crash alive. In other words, we want to create a fake object that mimics the CHelloworld object.

Finidng the Object Size

To find the size of <code>CHelloWorld</code>, typically there are two ways: either we can find the <code>new</code> operator responsible for <code>CHelloWorld</code>, or we find it at run-time.

In our previous backtrace, we understand the <code>CHelloWorld</code> comes from the <code>ComserverExample</code> component, so that's where we have to look. The quickest way for us to locate the <code>new</code> operator statically is by looking at the import table of <code>ComserverExample</code>:

```
Address Ordinal Name Library
00000001004943C 1640 operator new(uint) mfc120ud
000000010049464 267 operator new[](uint) mfc120ud
000000010049514 1647 CObject::operator new(uint,char const *,int) mfc120ud
```

And then by cross-referencing, we can tell what functions need new:

```
Direction Type Address Text
Down p
ATL::CComCreator<ATL::CComObjectCached<ATL::CComClassFactory>>::CreateInstance(vo
id *,_GUID const &,void * *)+A7 call j_??2@YAPAXI@Z; operator new(uint)
Down p std:: Allocate<char>(uint,char *)+37 call j ??2@YAPAXI@Z; operator
new(uint)
Down p std::_Allocate<std::_Container_proxy>(uint,std::_Container_proxy *)+3D
      j ??2@YAPAXI@Z; operator new(uint)
call
Down p ATL::AtlModuleAddTermFunc(ATL:: ATL MODULE70 *,void (*)(ulong),ulong)+37
      j_??2@YAPAXI@Z; operator new(uint)
call
Down p ATL::CComCreator<ATL::CComAggObject<CHelloWorld>>::CreateInstance(void
*, GUID const &, void * *)+A7 call
                                  j ??2@YAPAXI@Z; operator new(uint)
Down p ATL::CComCreator<ATL::CComObject<CHelloWorld>>::CreateInstance(void
*,_GUID const &,void * *)+A7 call j_??2@YAPAXI@Z; operator new(uint)
```

Since we are looking for CHelloworld, then the last one is what we want:

```
Down p ATL::CComCreator<ATL::CComObject<CHelloWorld>>::CreateInstance(void *,_GUID const &,void * *)+A7 call j_??2@YAPAXI@Z; operator new(uint)
```

CreateInstance pretty much implies its purpose is to create a new object for us, in this case for CHelloWorld. In it, we can tell how much space is given by looking at the argument of new:

```
push 8 ; unsigned int
call j_??2@YAPAXI@Z ; operator new(uint)
```

8 bytes is requested for our <code>CHelloworld</code> object. However, sometimes the actual size is different at run-time, so usually the best way to find the object size is WinDBG.

Since we know when the object was freed by

ComServerExample!ATL::CComObject<CHelloWorld>::Release, we can add a breakpoint there and inspect the memory block. When this breakpoint hits, we can see that the Release() method actually needs one argument (see push edx), which is different than what MSDN documents:

```
00alefcb 8b55e0 mov edx,dword ptr [ebp-20h]
00alefce 52 push edx
00alefcf 8b4108 mov eax,dword ptr [ecx+8]
00alefd2 ffd0 call eax {ComServerExample!ILT+1805(?Release?
$CComObjectVCHelloWorldATLUAGKXZ) (53df2712)}
```

The first argument basically tells Release() what to free. By inspecting this with !heap -p -a edx, we learn where the allocation occured, and how big:

```
0:000> !heap -p -a edx
   address 0802eff0 found in
   DPH HEAP ROOT @ 3401000
   in busy allocation ( DPH_HEAP_BLOCK:
                                                UserAddr
                                                                   UserSize -
VirtAddr
               VirtSize)
                                                   802efd0
                                7f52ccc:
                                                                         2c -
802e000
                    2000
   5490abb0 verifier!AVrfDebugPageHeapAllocate+0x00000240
   77a027ab ntdll!RtlDebugAllocateHeap+0x00000039
   779658e9 ntdll!RtlpAllocateHeap+0x000000f9
   779649c9 ntdll!RtlpAllocateHeapInternal+0x00000179
   7796483e ntdll!RtlAllocateHeap+0x0000003e
   5407c6e1 MSVCR120D! heap alloc base+0x00000051
[f:\dd\vctools\crt\crtw32\heap\malloc.c @ 58]
   5408d72f MSVCR120D! heap alloc dbg impl+0x000001ff
[f:\dd\vctools\crt\crtw32\misc\dbgheap.c @ 431]
   5408dbcd MSVCR120D! nh malloc dbg impl+0x0000001d
[f:\dd\vctools\crt\crtw32\misc\dbgheap.c @ 239]
   5408db7a MSVCR120D!_nh_malloc_dbg+0x0000002a
[f:\dd\vctools\crt\crtw32\misc\dbgheap.c @ 302]
   5408d90f MSVCR120D! malloc dbg+0x0000001f
[f:\dd\vctools\crt\crtw32\misc\dbgheap.c @ 160]
   5429bff6 mfc120ud!operator new+0x00000036
[f:\dd\vctools\vc7libs\ship\atlmfc\src\mfc\afxmem.cpp @ 302]
   53e0befc ComServerExample!ATL::CComCreator<ATL::CComObject<CHelloWorld>
>::CreateInstance+0x000000ac [c:\program files (x86)\microsoft visual studio
12.0\vc\atlmfc\include\atlcom.h @ 2000]
ComServerExample!ATL::CComCreator2<ATL::CComCreator<ATL::CComObject<CHelloWorld>
>,ATL::CComCreator<ATL::CComAggObject<CHelloWorld> > >::CreateInstance+0x00000069
[c:\program files (x86)\microsoft visual studio 12.0\vc\atlmfc\include\atlcom.h @
```

```
20961
   53e0c213 ComServerExample!ATL::CComClassFactory::CreateInstance+0x000000d3
[c:\program files (x86)\microsoft visual studio 12.0\vc\atlmfc\include\atlcom.h @
37381
   00alef19 ComClientExample!TestComServerSample+0x000000a9
[c:\users\sinn3r\documents\visual studio
2013\projects\comclientexample\comclientexample\comclientexample.cpp @ 42]
   00a16983 ComClientExample!wmain+0x0000000a3 [c:\users\sinn3r\documents\visual
studio 2013\projects\comclientexample\comclientexample\comclientexample.cpp @ 101]
   00a1c6a9 ComClientExample!__tmainCRTStartup+0x00000199
[f:\dd\vctools\crt\crtw32\dllstuff\crtexe.c @ 623]
   00a1c89d ComClientExample!wmainCRTStartup+0x000000d
[f:\dd\vctools\crt\crtw32\dllstuff\crtexe.c @ 466]
   75228484 KERNEL32!BaseThreadInitThunk+0x00000024
   7798305a ntdll! RtlUserThreadStart+0x0000002f
   7798302a ntdll!_RtlUserThreadStart+0x0000001b
```

As you can see, the actual size is 0x2c, not 8 like we previously saw. It is important to get this information right so that when this object is freed, we can correctly fill it up again with our fake object. There is also a manual way to verify this. By exaiming EDX a little further, we learned that we are dealing with a CHelloworld vftable:

And this vftable is mapped with the following functions:

```
0:000> dds poi(edx)
53e1e1d0 53df2e6f ComServerExample!ILT+3690(?QueryInterface?
$CComObjectVCHelloWorldATLUAGJABU GUIDPAPAXZ)
53e1e1d4 53df2d7a ComServerExample!ILT+3445(?AddRef?
$CComObjectVCHelloWorldATLUAGKXZ)
53e1e1d8 53df2712 ComServerExample!ILT+1805(?Release?
$CComObjectVCHelloWorldATLUAGKXZ)
53e1e1dc 53df2226 ComServerExample!ILT+545(?GetTypeInfoCount?
$IDispatchImplUIHelloWorld$1?IID IHelloWorld
53e1e1e0 53df2dd9 ComServerExample!ILT+3540(?GetTypeInfo?
$IDispatchImplUIHelloWorld$1?IID IHelloWorld
53e1e1e4 53df2091 ComServerExample!ILT+140(?GetIDsOfNames?
$IDispatchImplUIHelloWorld$1?IID IHelloWorld
53ele1e8 53df2744 ComServerExample!ILT+1855(?Invoke?$IDispatchImplUIHelloWorld$1?
IID IHelloWorld
53elelec 53df28ac ComServerExample!ILT+2215(?PrintSomethingCHelloWorldUAGJPADZ)
53elelf0 53df2384 ComServerExample!ILT+895(?? E?
$CComObjectVCHelloWorldATLUAEPAXIZ)
53e1e1f4 00000000
53e1e1f8 00000000
```

If you count the number of entries you have in this table, which is 11, each one is a pointer so that requires 4 bytes. $11 \times 4 = 44$, and 44 in hexadecimal is $0 \times 2C$. So yup, that's the correct object size.

Heap Feng Shui

Note: Starting from this point, you should turn off GFlags, otherwise you will not get the correct layout needed to gain control of the crash.

As previsouly mentioned, when the operating system allocates and frees heap blocks, it tends to refill the holes. What does that mean, really? Let's say we have a C program like this:

```
HANDLE hProcHeap = GetProcessHeap();

LPVOID h1 = HeapAlloc(hProcHeap, HEAP_ZERO_MEMORY, 0x2C);

LPVOID h2 = HeapAlloc(hProcHeap, HEAP_ZERO_MEMORY, 0x2C);

LPVOID h3 = HeapAlloc(hProcHeap, HEAP_ZERO_MEMORY, 0x2C);

LPVOID h4 = HeapAlloc(hProcHeap, HEAP_ZERO_MEMORY, 0x2C);

LPVOID h5 = HeapAlloc(hProcHeap, HEAP_ZERO_MEMORY, 0x2C);
```

When there is a lot of heap allocations of the same size, the operating system would tend to put them next to each other in memory, like this:

Block 1	Block 2	Block 3	Block 4	Block 5
0x2C	0x2C	0x2C	0x2C	0x2C

If we free one of the blocks, let's say Block 3, then the memory would look like this:

Block 1	Block 2	Empty	Block 4	Block 5
0x2C	0x2C		0x2C	0x2C

At this point, the freed block is considerd as a "hole" of this memory layout, so that's where the term came from. Now, if we try to allocate the same size again, we fill that hole:

Block 1	Block 2	New Block	Block 4	Block 5
0x2C	0x2C	0x2C	0x2C	0x2C

If there is a reference to where the new block is, then it would give us a chance to get arbitrary code exectuion. If you recall, our crash is trying to call some function at offset 0x1C, which is the 8th pointer in our CHelloworld vftable. Since the 8th pointer is the Printsomething() function, we have to create a fake object that hijcks this function.

Creating a Fake Object

Since we know what the CHelloworld vftable structure looks like, we can mimic the same thing. In some applications, you have take advantage of an array of vector to create that list of pointers, for example:

```
// The new operator means we are putting this on the heap
int* fakeObj = new int[2];
int[0] = 0x0c0c0c0c; // Fake pointer
int[1] = 0x0c0c0c0c; // Fake pointer
```

However, before you do that, you should really spend some time researching on how an array (or vector) is created in memory. For example, in C++, it would look like since there are only two pointers, the size would be 0x08, right? No, turns out it's 0x2C under WinDBG.

For demonstration purposes, let's use a string and put it on the heap to mimic our 0x2C-byte object:

If we run the above code after the Release(), but before the invalid reference is used again, we may get a chance to gain control of that code:

```
0:000> r
eax=000dd558 ebx=0022d000 ecx=41424328 edx=000dd558 esi=0056f6d0 edi=0056f7f0
eip=01385dc1 esp=0056f6c8 ebp=0056f7f0 iopl=0 nv up ei pl zr na pe nc
cs=0023 ss=002b ds=002b es=002b fs=0053 gs=002b efl=00010246
ComClientExample!TestComServerSample+0x1d1:
01385dc1 8b411c mov eax,dword ptr [ecx+1Ch] ds:002b:41424344=???????
```

Sometimes, it does require a little spraying to get right. The important thing is, as long as you still have that window of opportunity, you will manage to hit that empty hole.

Heap Spraying

Heap spraying is an exploitation technique that takes advantage of large heap allocations in order to make the operating system create an address pattern, which would allow us to put data at a more predictable place in memory. For example, you can target your spray to land data at an address such as 0x0c0c0c0c, that way when you want to redirect the crash to 0x0c0c0c0c, your data will be there.

For previous Windows systems such as Windows 7 or before, heap spraying was much more effective. But on Windows 10, the allocations would need to be much bigger to have a similar effect.

Cod example of a heap spray routine:

```
#define BLOCKSIZE 0x1000000/4 - 0x100

void CreatePayload(HANDLE hProcHeap) {
    LPVOID h = HeapAlloc(hProcHeap, HEAP_ZERO_MEMORY, BLOCKSIZE);
    memset(h, 0x41, BLOCKSIZE-1);
```

To debug heap spraying, usually you would begin with this WinDBG command to find what sizes are available to look up:

```
0:001> !heap -stat -h
Allocations statistics for
heap @ 01230000
group-by: TOTSIZE max-display: 20
   size
            #blocks
                       total (%) (percent of total busy bytes)
   3fff00 64 - 18ff9c00 (99.99)
   2cc2 1 - 2cc2 (0.00)
   27be\ 1 - 27be\ (0.00)
   800 2 - 1000 (0.00)
   670\ 1 - 670 \ (0.00)
   d0 6 - 4e0 (0.00)
   440 \ 1 - 440 \ (0.00)
   220 2 - 440 (0.00)
   400\ 1 - 400 \ (0.00)
   200\ 2 - 400 \ (0.00)
   3bc 1 - 3bc (0.00)
   306 1 - 306 (0.00)
   a8 4 - 2a0 (0.00)
   120 2 - 240 (0.00)
   208 1 - 208 (0.00)
   181 1 - 181 (0.00)
   12e 1 - 12e (0.00)
   128 1 - 128 (0.00)
   80\ 2\ -\ 100\ (0.00)
    fc 1 - fc (0.00)
```

It looks like there are a lot of blocks for size 0x3fff00, we can list all these with:

```
!heap -flt s 0x3fff00
```

If the allocations are big enough, WinDBG should tell you they are "busy VirtualAlloc"s:

```
171f3018 80000 0000 [00]
                          171f3020
                                      3fff00 - (busy VirtualAlloc)
                                      3fff00 - (busy VirtualAlloc)
17602018 80000 0000 [00]
                          17602020
                                      3fff00 - (busy VirtualAlloc)
17a17018 80000 0000 [00]
                          17a17020
                                      3fff00 - (busy VirtualAlloc)
17e2d018 80000 0000 [00]
                          17e2d020
18235018 80000 0000 [00]
                          18235020
                                      3fff00 - (busy VirtualAlloc)
18646018 80000 0000 [00]
                                      3fff00 - (busy VirtualAlloc)
                          18646020
                                      3fff00 - (busy VirtualAlloc)
18a5f018 80000 0000 [00]
                           18a5f020
18e6d018 80000 0000 [00]
                                      3fff00 - (busy VirtualAlloc)
                           18e6d020
```

And hopefully, you can always find data at a predicable place:

```
0:001> dd 0c0c0c0

0c0c0c0c 41414141 41414141 41414141 41414141

0c0c0c1c 41414141 41414141 41414141 41414141

0c0c0c2c 41414141 41414141 41414141 41414141

0c0c0c3c 41414141 41414141 41414141 41414141

0c0c0c4c 41414141 41414141 41414141 41414141

0c0c0c5c 41414141 41414141 41414141 41414141

0c0c0c6c 41414141 41414141 41414141 41414141

0c0c0c6c 41414141 41414141 41414141 41414141
```

Note that as Windows improves, heap spraying becomes harder and harder to use. Therefore sometimes, exploit developers might try to avoid heap spraying completely, and try to leak the memory addresses instead, and hopefully that can leak an object that we control, which points to our payload.

Strategies for Information Leaks

Thanks to ASLR an DEP (see below), leaking memory information is becoming a valuable skill to have nowadays for exploit developers. The problem is that when ASLR and DEP are enabled, it is much harder to the exploit to hardcode anything. For example, you no longer can grab a JMP ESP from ntdll.dll because the addresses always change. Instead, you might want to consider finding NTDLL's base address in memory, and then find gadgets from there, so this is where the info leak technique comes in.

For use-after-frees, here are some generic techniques to leak something in memory:

UAF with Uninitialized Variable

Applicable once you have the pointer to your fake object. Look for things like:

```
push ecx
call module!Object::NonVirtualFunction
```

Where ECX is the object pointer to stack. The whole point of picking this type of scenario is to avoid crashing due to calling a virtual function, that way there might be more interesting things that could happen later on.

UAF with Controlled Variable to READ

Try to read some value from a controlled place in memory, for example:

```
class SomeClass {
  private:
    void* ptr; // attacker could control this once the free chunk is controlled

public:
    DWORD Func() {
       return *(DWORD *) ptr;
    }
};
```

This technique is more applicable against applications that support scripting.

UAF with Controlled Variable to WRITE

Ideally, try to write an arbitrary value to a memory that you have control of, and then read it.

An example of setting this up is, let's say we have an array of one element like this:

```
int* arrayObject = new int[1];
arrayObject[0] = 0x41424344; // Let's stay this is our payload
```

Let's say we want to find the address of this array using an info leak, we could put it next to a string like this layout:

```
| 41 41 41 00 | Pointer to array |
```

If we have a use-after-free that allows to write anywhere, we could modify the null byte like this:

```
| 41 41 41 41 | Pointer to array |
```

That way, when we want to read the string again, we can end up reading longer than 4 bytes, because the null-byte terminator is gone, and then get the pointer to the array.

Other things you can overwrite include:

- The string length from a string block.
- A variant type of an array attribute, which basically causes a type confusion (Example: Object being modified to as String)
- Etc

Mitigations

vTable Guards

The purpose of having a vTable guard is because in order to exploit a lost object, the attacker has to replace it with a fake one. So the idea is that, if we can place a special value at the end of the real vtable, like this:

```
SomeObj::`vftable` |
| Virtual Method 1 |
| Virtual Method 2 |
| Virtual Method 3 |
| Virtual Method 4 |
| __vtguard |
```

When there is some code that needs to use it, the special value should be checked. If the special value is invalid, then the object is treated as corrupt. Basically, like this code:

```
If (vftable[vtguard_vte] != vtguard) {
    TerminateProcess();
}
```

However, note that not all vTables are guarded, you just have to find that low-hanging fruit.

Address Space Layout Randomization (ASLR)

The purpose of having ASLR is to prevent multiple exploitation techniques. When the address layout is randomized all the time, it is much more difficult for the attacker to hardcode anything. For example, a RETN address for a buffer overflow.

To defeat ASLR alone, you could look for components don't support it (except that most should nowadays), or you find a way to leak memory addresses from the target program. Sometimes, some researchs do discover some regions in memory aren't actually randomized, such as shared memory, we could use something like that too if left unpatched.

Data Execution Prevention

Data Execution Prevention marks some memories as non-executable. This mitigtaion works best with ASI R.

To defeat DEP, Return-Oriented Programming (ROP) would be invovled.