# Audulus 3 Module Library Documentation

Mark Boyd

January 29, 2019

# Contents

1	Modules and How They Work				
	1.1	Signal	Standards	7	
		1.1.1	Gate	8	
		1.1.2	Modulation	9	
		1.1.3	1/Octave	9	
		1.1.4	Audio	10	
	1.2	Catego	ories of Modules	11	
		1.2.1	Tempo Modules	11	
		1.2.2	Beat Modules	11	
		1.2.3	Pitch Modules	11	
		1.2.4	Audio-Generating Modules	11	
		1.2.5	Audio-Modifying Modules	11	
	1.3	Wiring	g Modules Together	11	
		1.3.1	Sequencer-Driven Subtractive Synthesizer	11	
		1.3.2	Keyboard-Controlled FM Synthesizer	11	
		1.3.3	Drum Patterns and Mixing	11	
		1.3.4	Stereo Effects	11	
		1.3.5	Generative Sequencing	11	
		1.3.6	Automation	11	
		1.3.7	DAW Integration	11	
		1.3.8	Eurorack Integration	11	
2	Clo	ck Mo	dules	13	
	2.1	Clock	Divider	13	
	2.2	Maste	er Clock	13	
	2.3	Berno	ulli Gate	13	
	2.4	Chanc	ce Select Gate	13	
	2.5	Pachir	nko Machine	13	
	2.6	Rando	om Bursts	13	

4 CONTENTS

	2.7	uClock										
3	Dri	ım Modules 15										
	3.1	uKick										
4	Effe	ect Modules 17										
	4.1	Delay										
		4.1.1 Stereo Delay										
		4.1.2 Looper Sync										
		4.1.3 Tempo Sync										
		4.1.4 uDelay										
	4.2	Distortion										
		4.2.1 Asymmetrical Drive										
		4.2.2 Fold Processor										
	4.3	Dynamics										
	4.4	Reverb										
		4.4.1 Really Humungous Reverb										
		4.4.2 uVerb										
5	Env	relope Modules 19										
-	5.1	Analog Envelope										
	5.2	EOC Max ADSR										
	5.3	uADSR										
6	Input-Output Modules 21											
Ū	6.1	Audio Input										
	6.2	Audio Output										
	6.3	Expert Sleepers ES-3										
	6.4	Expert Sleepers ES-6										
	6.5	Expert Sleepers ES-8										
	6.6	MIDI Input										
	6.7	VPO Converter										
7	LFO Modules 23											
•	7.1	Basic LFO										
	7.2	Octature Sine LFO										
	7.3	TZFM LFO										
	7.4	uLFO										
8	Mix	cer Modules 25										
-		uMix Audio										

CONTENTS	ļ	5

	8.2	uMix CV	25
9	Qua	ntizer Modules	27
	9.1	Chromatic Quantizer	27
	9.2	Gateable Quantizer	27
	9.3	Modulation Quantizer	27
	9.4	Neo-Reimannian Triad Transformer	27
	9.5	Quick Quantizer	27
10	Seq	uencer Modules	29
	_	8 Step Sequencer	29
		16 Step Gate Sequencer	29
		Binary Gate Sequencer	29
		Euclidean Gate Sequencer	29
		Matrix Gate Sequencer	29
		Shape Gate Sequencer	29
11		ity Modules	31
		Attenuate-Offset	32
		Attenuverter	32
		Audio Attenuverter-Offset	32
		Automation Lane	32
		Chaos Generator	32
		Modulation to 1/Oct	32
	11.7	Sample & Hold	32
	11.8	Slew	32
	11.9	Switch Sequential 8 Step	32
	11.10	OVC Switch	32
	11.1	luLogic	32
		PuSample & Hold	32
		BWindow Comparator	32
12	VC	A Modules	33
		Digital VCA	33
	12.2	Diode VCA	33
		uVCA	33
	12.0		99
13		F Modules	<b>35</b>
	13.1	Diode Ladder VCF	35
14	VC	O Modules	37

6 CONTENTS

14.1	Basic VCO	37
14.2	Chebyshev Additive VCO	37
14.3	Karplus-Strong VCO	37
14.4	Morphing VCO	37
14.5	Noise	37
14.6	Skew VCO	37
14.7	Supersaw VCO	37
14.8	TZFM VCO	37
14.9	uNoise	37
14 10	)uVCO	37

# Modules and How They Work

Modular synthesis is an exciting, freeing way to create music and design sounds. The freedom it offers can be intimidating at first, especially to a total beginner, but grasping the fundamentals is easier than it appears.

All Audulus modules are created using Audulus nodes. You can open up any module to see how it works. Some modules are very simple and may have only a few nodes inside. Others are a web of interconnected submodules, sometimes many layers deep.

The great thing about the Audulus module library is that you don't need to understand how each module is constructed to be able to use it. There are, however, a few things you need to know about the module library before getting started.

#### 1.1 Signal Standards

Modules in the Audulus library operate with a set of standardized signals. The job of the modules is to generate and modify these signals in interesting ways.

There are four main signal types: Gate, Modulation, 1/Octave, and Audio. As a general rule, you will connect like with like, meaning connect a Gate output to a Gate input, or an Audio output to an Audio input.

#### 1.1.1 Gate

The Gate signal is used to drive sequencers, open and close envelopes, and syncronize tempo, among other things. Its signal range is 0 or 1: off or on.

Gates are generated mainly by clock modules and keyboard or MIDI input. You can modify gate signals with modules like clock dividers and multipliers, gate sequencers, and Bernoulli gates. They are used by modules like sequencers, envelopes, and LFOs.

Gate inputs and outputs are always marked with a green light which is also called the Light node. When a gate input or output is equal to 0, the color of the light is dark green, and when the output is equal to 1, the color of the light is a bright green.

The only exception to this rule is when a gate is entering an envelope. Here, gate height, or the upper value of the gate, will set the maximum value that the Attack period rises to. This allows you to play with dynamics, or making your sounds softer or louder.

Gate inputs and outputs may be marked Gate, Gte, Reset or Rset, PWM, or Clk. Sometimes they may be unmarked except for the light node inside each input or output. These labels will have contextual meanings for each specific module, which are explained in their individual entries in the manual below.

Most modules will respond to only the rising edge of a gate. The rising edge is the moment where a gate transitions from 0 to 1. For example: a step sequencer will only step forward at the rising edge, but will not step forward again on the falling edge.

Other modules, like an envelope, respond to both the rising and falling edge of the gate signal. The rising edge of the gate will initiate the attack stage of the envelope whereas the falling edge will initiate the release stage.

If you are familiar with modular synthesis, you might be wondering if there is a difference between a pulse and a gate in Audulus. A pulse is a very short on/off burst, usually generated by clock modules, whereas gate signals can be any length from very short to very long.

In Audulus, no distinction is made between a pulse and a gate. That said, several clock modules give you control over the pulse width of their gate output. Pulse width is the ratio of on to off time. A 10% pulse-width gate is on 10% of the time and off 90% of the time whereas a 90% pulse-width gate is on 90% of the time and off 10% of the time.

#### 1.1.2 Modulation

The Modulation signal is used to tweak parameters like filter cutoff, VCO shape, and VCA level. Its signal range is 0 to 1.

Modulation signals are genereated by modules like LFOs, envelopes, sequencers, and sample & holds. They can be used to modulate any knob on any module and often have their own separate inputs as well.

Modulation inputs and outputs are often marked with a red light. The light indicates the relative strength of the incoming modulation. If the light is black (not lit) its value is 0. If the light is fully red its value is 1.

When a module has several outputs like the Basic LFO, lights may be omitted to save CPU time. If a portion of a module does not terminate in a Meter node or audio output, then everything that precedes it will not be calculated. This means if you use only the Sine output of the Basic LFO, only the sine path will be calculated. If lights were present at each output they would force Audulus to calculate the unused paths, wasting CPU time.

Modulation inputs and outputs may be marked Mod, Env (Envelope), a specific waveshape like Sine or Saw, or correspond to a knob label like Hz Mod or Q. Sometimes they may be unmarked and have contextual meanings for each specific module, which are explained in their individual entries in the manual below.

#### 1.1.3 1/Octave

The 1 per octave signal is a linearized pitch signal centered at 0 = A4 = 440Hz. To go an octave up, just add one: 1 = A5 = 880Hz. To go an octave down, subtract one: -1 = A3 = 220Hz. To go up or down in semitones, add or subtract in steps of 1/12th:  $1/12 = A\sharp 4 \approx 466$ Hz;  $-1/12 = A \flat 4 \approx 415$ Hz.

Hardware modular synthesizers typically use 1 volt per octave tracking where 0 volts is the lowest note, often C0. Audulus's 1/Octave signal is instead centered at the reference pitch, which is defaulted to A=440Hz.

The Keyboard node only outputs Hz, so make sure you use the MIDI Input module if you wish to use Audulus modules with a keyboard or pipe in a MIDI sequence from a DAW.

All non-gate sequencers in the Audulus module library generate a modulation signal only. This makes it easy to use these sequencers to modulate parameters as well as pitch. Their modulation output can be translated into a 1/Octave signal using a Modulation to 1/Oct utility module or with a quantizer module which all have this translation module built-in.

Translating a sequencer's output is simple. The Range parameter mul-

tiplies the 0 to 1 modulation output of the sequencer by 0 to 8. If the range is set to 2 then each knob of the sequencer covers 2 octaves. If the range is set to 0.5 then each knob covers 1/2 of an octave. The Shift parameter sets you lowest note. At 0, your lowest note will be A4. At -1, your lowest note will be A3. At 1, your lowest note will be A5.

The default reference pitch is set to  $A=440 \mathrm{Hz}$ , but you can change this in any VCO if you wish. Enter any VCO and look for the 1/Oct to Hz converter (it may be a layer or two down in the module). Look for the RefHz variable and alter it to whatever pitch you wish. This change will only affect that particular VCO, so if you want to globally change the reference pitch you will have to make sure you do it in every VCO you use.

#### 1.1.4 **Audio**

The Audio signal carries what you hear to your headphones or speakers. Its signal range is -1 to 1.

Audio signals are generated by VCOs (voltage-controlled oscillators) or an external audio input like a guitar or an audio track. They are modified by modules like VCFs (voltage-controlled filters), VCAs (voltage-controlled amplifiers), and effects like delay, reverb, and distortion.

Audio signals can be used as modulation at FM (frequency modulation) inputs of VCOs or as AM (amplitude modulation) at modulation inputs of VCAs. You can also modulate knobs at audio rates, but the knob will clip the negative portion of the audio signal. This means when the audio signal goes below 0, the knob will stay at 0.

It is not recommended to plug an audio signal into a modulation input. Doing so may cause unpredictable and undesireable behavior from some modules. The only exception to this rule is the VCA modulation input, as mentioned above.

Audio inputs and outputs are unmarked by any lights. They may be labeled Audio, Aud, In/Out, Left/Right or L/R for stereo modules, or have context-specific labels like Sine or Saw on a VCO. Inputs labeled FM always expect an audio signal.

When audio signals are mixed together, their total output may exceed a -1 to 1 range. You can even boost your audio signals creatively to drive a distortion module harder. The important thing to remember is that audio exiting Audulus to your speakers, headphones, or audio interface must be kept between -1 and 1 to prevent clipping distortion.

#### 1.2 Categories of Modules

- 1.2.1 Tempo Modules
- 1.2.2 Beat Modules
- 1.2.3 Pitch Modules
- 1.2.4 Audio-Generating Modules
- 1.2.5 Audio-Modifying Modules

#### 1.3 Wiring Modules Together

- 1.3.1 Sequencer-Driven Subtractive Synthesizer
- 1.3.2 Keyboard-Controlled FM Synthesizer
- 1.3.3 Drum Patterns and Mixing
- 1.3.4 Stereo Effects
- 1.3.5 Generative Sequencing
- 1.3.6 Automation
- 1.3.7 DAW Integration
- 1.3.8 Eurorack Integration

# **Clock Modules**

- 2.1 Clock Divider
- 2.2 Master Clock
- 2.3 Bernoulli Gate
- 2.4 Chance Select Gate
- 2.5 Pachinko Machine
- 2.6 Random Bursts
- 2.7 uClock

# **Drum Modules**

3.1 uKick

#### Effect Modules

- 4.1 Delay
- 4.1.1 Stereo Delay
- 4.1.2 Looper Sync
- 4.1.3 Tempo Sync
- 4.1.4 uDelay
- 4.2 Distortion
- 4.2.1 Asymmetrical Drive
- 4.2.2 Fold Processor
- 4.3 Dynamics
- 4.4 Reverb
- 4.4.1 Really Humungous Reverb
- 4.4.2 uVerb

# **Envelope Modules**

- 5.1 Analog Envelope
- 5.2 EOC Max ADSR
- 5.3 uADSR

# Input-Output Modules

- 6.1 Audio Input
- 6.2 Audio Output
- 6.3 Expert Sleepers ES-3
- 6.4 Expert Sleepers ES-6
- 6.5 Expert Sleepers ES-8
- 6.6 MIDI Input
- 6.7 VPO Converter

# LFO Modules

- 7.1 Basic LFO
- 7.2 Octature Sine LFO
- 7.3 TZFM LFO
- 7.4 uLFO

# Mixer Modules

- 8.1 uMix Audio
- 8.2 uMix CV

# Quantizer Modules

- 9.1 Chromatic Quantizer
- 9.2 Gateable Quantizer
- 9.3 Modulation Quantizer
- 9.4 Neo-Reimannian Triad Transformer
- 9.5 Quick Quantizer

# Sequencer Modules

- 10.1 8 Step Sequencer
- 10.2 16 Step Gate Sequencer
- 10.3 Binary Gate Sequencer
- 10.4 Euclidean Gate Sequencer
- 10.5 Matrix Gate Sequencer
- 10.6 Shape Gate Sequencer

# **Utility Modules**

- 11.1 Attenuate-Offset
- 11.2 Attenuverter
- 11.3 Audio Attenuverter-Offset
- 11.4 Automation Lane
- 11.5 Chaos Generator
- 11.6 Modulation to 1/Oct
- 11.7 Sample & Hold
- 11.8 Slew
- 11.9 Switch Sequential 8 Step
- 11.10 VC Switch
- 11.11 uLogic
- $11.12\quad \text{uSample \& Hold}$
- 11.13 Window Comparator

# VCA Modules

- 12.1 Digital VCA
- 12.2 Diode VCA
- 12.3 uVCA

# VCF Modules

13.1 Diode Ladder VCF

### VCO Modules

- 14.1 Basic VCO
- 14.2 Chebyshev Additive VCO
- 14.3 Karplus-Strong VCO
- 14.4 Morphing VCO
- 14.5 Noise
- 14.6 Skew VCO
- 14.7 Supersaw VCO
- 14.8 TZFM VCO
- 14.9 uNoise
- 14.10 uVCO