Linux Kernel Project1 Report

蒋逸伟 517161910005

1 HELLO LAB

1 hello lab

实验平台: Ubuntu

内核版本: 5.4.0-21-generic

1.1 模块一:加载和卸载模块时在系统日志输出信息

这个 lab 旨在了解 Linux 内核模块的接口调用和构成 代码如下

```
#include <linux/kernel.h>
2 #include <linux/module.h>
  #include ux/init.h>
  static int ___init hello_init(void)
  {
5
       printk(KERN_INFO "Hello world\n");
6
       return 0;
7
8
  static void __exit hello_exit(void)
10
       printk(KERN_INFO"Goodbye world \ n");
11
12
  module_init(hello_init);
13
  module_exit(hello_exit);
14
  MODULE_LICENSE("GPL");
  MODULE_AUTHOR("Jiang Yiwei");
17
  MODULE_DESCRIPTION("Hello test");
  MODULE_ALIAS("Project1");
```

module_init()宏表示程序人口

同理module_exit是程序退出

替

printk类似于printf() 用以输出第一个参数代表输出级别

内核中共提供了八种不同的日志级别,在 linux/kernel.h 中有相应的宏对应。同样也可以用<level>代

```
20
  #define KERN_EMERG
                       "<0>"
                               /* systemis unusable */
21
  #define KERN_ALERT
                       "<1>"
                               /* actionmust be taken immediately */
22
                               /*critical conditions */
23 #define KERN CRIT
                        "<2>"
24 #define KERN_ERR
                        "<3>"
                                /* errorconditions */
25 #define KERN_WARNING "<4>"
                                /* warning conditions */
26 #define KERN_NOTICE
                         "<5>"
                                /* normalbut significant */
27 #define KERN_INFO
                        "<6>"
                                /*informational */
```

2 PARAMETERS 3

```
#define KERN_DEBUG
                     "<7>" /*debug-level messages */
    makefile 的编写
  obj-m = hello.o
  all:
         make -C /lib/modules/$(shell uname -r)/build M=$(shell pwd) modules
  clean:
4
         make -C /lib/modules/$(shell uname -r)/build M=$(shell pwd) clean
    Tips:
    其中 object 的名字需要和.c 文件相同
    uname-r可以显示当前内核版本 pwd 表示当前目录
    同时可以由file命令查看*.ko的信息
    all:按下回车键后需要一个TAB键在这之间是一个制表符,否则会报错
    file hello.ko可以显示 module 的信息
    实验结果如下:
    > insmod hello.ko
    > rmmod hello
    > dmesg|tail -10
    [18959.294341] wlp3s0: send auth to fc:d7:33:94:96
    :60 (try 1/3)
    [18959.303252] wlp3s0: authenticated
    [18959.306578] wlp3s0: associate with fc:d7:33:94:
    96:60 (try 1/3)
    [18959.313810] wlp3s0: RX AssocResp from fc:d7:33:
    94:96:60 (capab=0x431 status=0 aid=4)
    [18959.320328] wlp3s0: associated
    [18959.339992] IPv6: ADDRCONF(NETDEV CHANGE): wlp3
    s0: link becomes ready
    [21423.423889] Hello build
    [21462.319796] Goodbye world
    [21474.539511] Hello build
```

2 parameters

2.1 模块二:支持整型、字符串、数组参数,加载时读人并打印

这个 lab 主要测试参数的传递需要包括头文件\linux\moduleparam.h
用到两个宏 module_param(name,type,perm),module_param_array(name,type,nump,perm)
其中nump是一个指向整数的指针,这个整数是数组中元素的个数
向参数中传递字符串需要制定type为charp而不是char
或者可以使用宏module_param_string(name, string, len, perm);
代码如下:

29 #include < linux / kernel.h>

2 PARAMETERS 4

```
#include < linux / module . h>
30
   #include < linux / init . h>
31
   #include < linux / moduleparam . h >
   static int int_var;
33
   static char* str_var;
34
   static int int_array[8];
35
   static int maxsize = 8;
36
   module_param(str_var, charp, 0660);
37
   module_param(int_var, int, 0660);
38
   module_param_array(int_array, int,&maxsize,0660);
39
   static int __init hello_init(void)
40
41
        int i=0;
42
        printk (KERN_INFO "Hello world \setminus n");
43
        printk (KERN_INFO "string: %s; \n", str_var);
        printk (KERN_INFO "int:%d; \n", int_var);
45
        for (i=0;i<(sizeof int_array / sizeof (int));i++)
46
47
             printk (KERN_INFO "int_array[%d]:%d",i,int_array[i]);
48
49
        return 0;
51
   static void __exit hello_exit(void)
52
53
        printk (KERN_INFO "Goodbye world \n");
54
55
   MODULE_LICENSE("GPL");
   MODULE_DESCRIPTION("parameters");
57
   MODULE_AUTHOR("Jiang Yiwei");
58
   module_init(hello_init);
59
   module_exit(hello_exit);
60
       实验效果如图:
       root@austinguish-GL502VSK /h/a/桌/L/project para#
       insmod parameters.ko int var=9 str var=helloworld int ar
       ray=1,2,3,5
       root@austinguish-GL502VSK /h/a/桌/L/project_para#
       dmesq|tail
       [28110.493682] Hello world
       [28110.493684] string:helloworld;
       [28110.493685] int:9:
       [28110.493686] int array[0]:1
       [28110.493687] int_array[1]:2
```

[28110.493688] int_array[2]:3 [28110.493689] int_array[3]:5 [28110.493690] int_array[4]:0 [28110.493691] int_array[5]:0 [28110.493692] int_array[6]:0 3 PROC_LAB 5

3 proc_lab

3.1 模块三,在/proc 下创建只读文件

创建只读文件需要先了解 filemode: 共有四位数字第一位是 sticky 位,第二位是文件属主的权限,第三位是组用户的权限,第四位是附加权限数字由下面的表说明。

$$\begin{aligned} \text{rwx} &= 111 = 7 \\ \text{rw-} &= 110 = 6 \\ \text{r-x} &= 101 = 5 \\ \text{r-} &= 100 = 4 \\ \text{-wx} &= 011 = 3 \\ \text{-w-} &= 010 = 2 \\ \text{-x} &= 001 = 1 \\ \text{--} &= 000 = 0 \end{aligned}$$

这里选择 444 作为只读的权限。

思路是先用proc_dir_entry *entry声明一个 proc 文件的人口,紧接着完成read函数,通过proc_create()函数进行文件创建。

```
#include <linux/module.h>
  #include <linux/init.h>
  #include <linux/kernel.h>
65
   #include <linux/proc_fs.h>
66
   static struct proc_dir_entry *entry;
67
68
   static struct file_operations ops =
69
   {
70
   };
71
72
   static int proc_init(void)
74
            entry=proc_create("hello_proc",0444,NULL,&ops);
75
            return 0;
76
77
78
   static void proc_exit(void)
79
80
            proc_remove(entry);
81
   }
82
83
   module_init(proc_init);
84
   module_exit(proc_exit);
```

4 可读可写的文件 6

```
效果如图:
austinguish@austinguish-GL502VSK /proc [SIGKILL]>
cat hello_proc
Hello proc!
austinguish@austinguish-GL502VSK /proc>
echo "hellobit">hello_proc
<W> fish: An error occurred while redirecting file 'hello_p
roc'
open: 权限不够
```

4 可读可写的文件

4.1 在/proc 下创建文件夹,并创建一个可读可写的文件

重点是实现file_operations

第一个操作.open 从内核中导出信息到用户空间有很多方法,可以自己去实现 file_operations 的 read 函数,但是这种方法不够简单,而且也会有一些限制,比如一次 read 读取大于 1 页时,模块就不得不去进行复杂的缓冲区管理。为此,就需要学习一下 seq_file 的用法,为了更简单和方便,内核提供了 single_xxx 系列接口,它是对 seq_file 的进一步封装。这里选用了 single_open。同时 my_proc_show 定义了文件打开时的操作,在屏幕上打印文件内容。

write 函数使用了kmalloc函数用以申请动态内存是 kernel 态的申请内存函数。可以防止内存溢出。copy_from_user()用来从用户态接收信息到内核态

struct proc_dir_entry *parent=proc_mkdir("",NULL) 用来创建一个文件夹供接下来的proc_create()使用

```
unsigned long copy_from_user (void *to, const void __user *from, unsigned long
   n);
   Arguments
88
89
   to
90
91
        Destination address, in kernel space.
92
   from
93
94
95
        Source address, in user space.
   n
96
97
       Number of bytes to copy.
98
```

代码如下:

```
#include < linux / module . h >

#include < linux / init . h >

#include < linux / proc_fs . h >

#include < linux / uaccess . h >

#include < linux / seq_file . h >

#include < linux / slab . h >
```

4 可读可写的文件 7

```
105
    static char *str = NULL;
106
107
    static int my_proc_show(struct seq_file *m, void *v){
108
             seq_printf(m, \frac{m}{s} n, str);
109
             return 0;
110
111
112
    static ssize_t my_proc_write(struct file * file , const char __user *buffer , size_t count
             char *tmp = kmalloc((count+1),GFP_KERNEL);
114
             if (!tmp)return -ENOMEM;
115
             if (copy_from_user(tmp, buffer, count)){
116
                      kfree (tmp);
117
                      return EFAULT;
118
             }
119
120
             str=tmp;
             return count;
121
122
123
    static int my_proc_open(struct inode *inode, struct file *file){
124
             return single_open(file,my_proc_show,NULL);
125
126
127
    static struct file_operations fops={
128
             .open = my_proc_open,
129
             . read = seq\_read,
130
             .write = my_proc_write
131
    };
132
    static int __init hello_init(void){
133
             struct proc_dir_entry *parent = proc_mkdir("proc_test", NULL);//create direct
134
             struct proc_dir_entry *entry;
135
             entry = proc_create("Hello_Proc",0666, parent,&fops);
136
             if (!entry){
137
                      return -1;
138
139
             return 0;
140
141
142
    static void __exit hello_exit(void){
143
             remove_proc_entry("Hello_Proc",NULL);
144
             printk (KERN_INFO "Goodbye world!\n");
145
```

4 可读可写的文件 8

```
146 }
147
148 module_init(hello_init);
149 module_exit(hello_exit);
150 MODULE_LICENSE("GPL");
```

实验效果如图:

```
Hello_Proc
root@austinguish-GL502VSK /p/proc_test# cat Hello_Proc
(null)
root@austinguish-GL502VSK /p/proc_test# echo "adsf ">Hello_Proc
root@austinguish-GL502VSK /p/proc_test# cat Hello_Proc
root@austinguish-GL502VSK /p/proc_test# cat Hello_Proc
adsf

root@austinguish-GL502VSK /p/proc_test# echo "将 fds">Hello_Proc
root@austinguish-GL502VSK /p/proc_test# cat Hello_Proc
将 fds

root@austinguish-GL502VSK /p/proc_test# cat Hello_Proc
```