

1. Inventory skew – raw bid / ask
(computeInventorySkewedRawBidAsk)

net_po from
position_state_

adjust_ticks: config +
verify only – not used in
skew

|net_po| < max_ll ?

no

yes

skew_tick_units = 0

skew_tick_units =
floor(net_po /
adjust_position)

theo_midpoint

basis

adjusted_theo = theo +
basis

skew_price =
skew_tick_units ×
quote_tick

raw_bid = adjusted_theo -
bid_spread_ticks × tick -
skew_price

span_ticks =
bid_spread_ticks +
ask_spread_ticks

raw_ask = raw_bid +
span_ticks × tick

→
finalizeMmPairOnTickGrid

