```
AmbientEnumMember:
PropertyName = IntegerLiteral
```

An AmbientEnumMember that includes an IntegerLiteral value is considered a constant member. An AmbientEnumMember with no IntegerLiteral value is considered a computed member.

12.1.5 Ambient Module Declarations

An ambient module declaration declares an internal module.

```
AmbientModuleDeclaration:
    module IdentifierPath { AmbientModuleBody }

AmbientModuleBody:
    AmbientModuleElementsopt

AmbientModuleElements:
    AmbientModuleElement
    AmbientModuleElements AmbientModuleElement

AmbientModuleElement:
    export_opt AmbientVariableDeclaration
    export_opt AmbientFunctionDeclaration
    export_opt InterfaceDeclaration
    export_opt AmbientEnumDeclaration
    export_opt AmbientEnumDeclaration
    export_opt AmbientEnumDeclaration
    export_opt InterfaceDeclaration
    export_opt InterfaceDeclaration
    export_opt ImportDeclaration
```

Except for *ImportDeclarations*, *AmbientModuleElements* always declare exported entities regardless of whether they include the optional export modifier.

12.1.6 Ambient External Module Declarations

An *AmbientExternalModuleDeclaration* declares an external module. This type of declaration is permitted only in the global module. The *StringLiteral* must specify a top-level external module name. Relative external module names are not permitted.

```
AmbientExternalModuleDeclaration:
    module StringLiteral { AmbientExternalModuleBody }

AmbientExternalModuleBody:
    AmbientExternalModuleElements<sub>opt</sub>
```