Migrate logins, database roles, users, and object-level permissions from Azure SQL Database to Amazon RDS for SQL Server

by Abdullah Sivaci, Jitendra Kumar, and Ramesh Babu Donti | on 24 MAY 2023 | in Intermediate (200), Multicloud, RDS for SQL Server, Security, Technical How-to | Permalink | Comments | Share

In this post, we demonstrate how to migrate logins, database roles, users, and object-level permissions from Azure SQL Database to Amazon Relational Database Service (Amazon RDS) for SQL Server.

Within SQL Server, a SQL login acts as a security principal, allowing a user or application to connect to a SQL Server instance. Database roles are used to group permissions together and assign them to multiple users or applications. Migrating SQL logins to Amazon RDS for SQL Server ensures that your connection authentication information, access rights, and permissions essential for users and applications to connect and interact with databases. While native backup and restore is the recommended method for migrating SQL Server databases, you can also migrate databases using AWS Database Migration Service (AWS DMS). AWS DMS is ideal for migration jobs and ad hoc replication.

SQL Server security components overview

In SQL Server, a SQL login is a security principal that allows a user or application to connect to an instance. These SQL logins are associated with access to the server's resources and permissions. Authentication in SQL Server involves the following components:

- Principals – These are entities capable of requesting resources within SQL Server. Principal access levels are configured at three scopes. You can categorize principals into each level based on their scope: server-level principals and database-level principals.
- Securables – These are the database objects to which authentication can be granted, such as tables or endpoints. Securables are further categorized based on their scope: server-scoped, database-scoped, and schema-scoped.
- Permissions – Permissions define control of accessible to the principal. Principals can run specific operations on securables based on the permissions granted to them. In general, permissions are managed through roles and users roles, whereas at the database level, permissions are regulated using database users and roles.

The following table illustrates the SQL Server security administration differences between Azure SQL Database and Amazon RDS for SQL Server.

Activities	Amazon RDS for SQL Server	Azure SQL Database
Where you manage server-level objects	Standalone SQL Server, Amazon Management Studio's Object Explorer	SQLCMD and through the Azure portal
Database authentication	With Managed Microsoft AD	Azure Active Directory identities
Switching to a specific existing database	USE<DATABASE>; format query	USE<DATABASE>; database not in the format query
Commands for managing logins	CREATE LOGIN, ALTER LOGIN, DROP LOGIN	CREATE LOGIN, ALTER LOGIN, DROP LOGIN (there are a few differences in the syntax)	Because we're on the master database and you must be connected to the master database
View that stores all logins	sys.server_principals	sys.sql_logins (you must be connected to the master database)
Server-level role that has full administrative rights	SELECT * from sysadmin	dbmanager database roles in the master database

Solution overview

A seamless Azure logins and user permissions are not migrated as part of the database migration process, such as when using SwissSQLKey, AWS DMS, or BCP, we utilize the built-in generate script utility and T-SQL dynamic scripts to create the logins, roles, users, and object-level permissions for each database.

The following diagram illustrates the high-level architecture of migrating logins and database users from Azure SQL Database to Amazon RDS for SQL Server.

The following steps are involved to migrate the SQL logins and their dependent security components:

1. Migrate logins and validate the existence of logins and the users between Azure SQL Database to Amazon RDS for SQL Server.
2. Migrate server roles and server permissions and validate the permissions.
3. Migrate users and database roles and validate the users and the roles.
4. Migrate object-level permissions and validate the permissions.

Prerequisites

To get started, you need to have the following:

- An Azure SQL database as a source
- An Amazon RDS for SQL Server instance (single-AZ or Multi-AZ) as a target
- SwissSQLKey between Azure SQL Database to Amazon RDS for SQL Server
- A target RDS for SQL Server database with required user-defined objects (tables, views, functions, and stored procedures) and the SQL_Latin1_General_CP1_CI_AS collation. Test database size is under 100 GB for this post.
- An Azure login with minimum permissions to "master" to fetch login and user info like "loginname", and more information to view that the primary login name of Azure SQL Database is the "dbmanager" for SQL Server.

Migrate logins

You can access the Azure SQL database using SSMS with Microsoft Entra server principals, or a managed identity. Identify the Microsoft Entra server principals and managed identity by fetching the login information from the sys.sql_logins and sys.server_principals catalog views. Run the following T-SQL script on the Azure SQL DB to fetch the SQL Server's server principals, you cannot grant equivalent privileges to users at the target.

To migrate SQL logins from Azure SQL Database to Amazon RDS for SQL Server, you can script out the create login scripts with a hashed password and SID. However, when using Azure SQL database as the source, the generated SID will be incompatible with the target Amazon RDS for SQL Server instance. For more info, see KB918992.

In this section, we explain how to generate the create script script from a source SQL Server instance and migrate it to the target RDS for SQL Server instance.

1. Connect to your source Azure SQL Server SQL Server Management Studio (SSMS) with the primary user or a user that has security admin fixed role permissions to script logins.
2. In the SSMS query editor, choose the **Results to Grid** option (Ctrl+D) option.
3. Run the following script from the new query window to generate the create logins script.

```
-- Script to generate create logins
SET NOCOUNT ON
SELECT 'USE [master]; DROP LOGIN [' + name + ']; CREATE LOGIN [' + name + '] WITH PASSWORD = ' + CONVERT(nvarchar(MAX), password_hash, 1) + ' HASHED, SID = ' + CONVERT(nvarchar(MAX), sid, 1) + ', DEFAULT_DATABASE = [' + default_database_name + '], DEFAULT_LANGUAGE = [' + default_language_name + '], CHECK_EXPIRATION = ' + CASE WHEN is_expiration_checked = 1 THEN 'ON' ELSE 'OFF' END + ', CHECK_POLICY = ' + CASE WHEN is_policy_checked = 1 THEN 'ON' ELSE 'OFF' END + ';'
FROM sys.sql_logins
WHERE default_database_name = 'master' and sid <> 0x01
ORDER BY name;
```

The output of the query provides the logins creation script.

4. Copy the logins creation script and run it using the **Results to Query** editor area on a login with the "drop any login" permissions. Make sure that the **principal_id** and **sid_password** fixed server roles in the RDS for SQL Server instance.
5. Check for any errors and fix them accordingly.
6. Validate the number of logins created in the Azure SQL database and RDS for SQL Server database. To test the login if working properly, connect to RDS for SQL Server with any of the logins migrated with the password used to connect to the Azure SQL database.

After the successful migration of logins, you can continue with the server role membership migration.

You should be responsible and cautious while copying the output and pasting it at the target database because it contains sensitive data.

Migrate server roles and server permissions

In Amazon RDS for SQL Server, you don't have superuser or sysadmin privileges. The primary user is the highest privilege login that you can create in Amazon RDS for SQL Server instances. The primary user is granted the rds_superuser_role role. rds_superuser_role is a database role created with a user name and password. The primary user is the user that you initially allowed with RDS, but not full sysadmin privileges. Only **principal_id** and **sid_password** fixed server roles can be granted to logins by the primary user. Refer to the fixed server roles in the RDS for SQL Server instance for more information.

In Azure SQL Database, you can use the built-in server-level roles to manage permissions at the logical server level rather than granular permissions at the level below. Refer to Azure SQL Database server roles for permissions management for more information.

The key steps to migrate server-level roles and permissions from Azure SQL Database to an RDS for SQL Server instance are as follows:

1. For each login, identify the server-level roles they are a member of using the following script.

```
SELECT r.name AS 'Master_Roles' , name AS 'MyLogin'
FROM sys.server_role_members AS rm
JOIN sys.server_principals AS r ON rm.role_principal_id = r.principal_id
JOIN sys.server_principals AS l ON rm.member_principal_id = l.principal_id
```

2. After the logins are scripted in Azure SQL Database, you can execute the server roles for "**principal_id**" and "**sid_password**" fixed server roles in the RDS for SQL Server instance. Refer to the fixed server roles and their permissions comparison and Microsoft Entra server principals for more information. You can add the login as a member to the "**principal_id**" and "**sid_password**" fixed server roles in RDS using the following statements:

```
ALTER SERVER ROLE [principal_id] ADD MEMBER [<MyLogin>];
GO
ALTER SERVER ROLE [sid_password] ADD MEMBER [ <MyLogin> ];
GO
```

Refer to the permissions for the "**principal_id**" and "**sid_password**" fixed server roles before manually adding logins to those roles on Amazon RDS.

Migrate users and database roles

To migrate your users and database roles, complete the following steps:

1. Connect to your source Azure SQL Test SSMS with the primary user or user that has security admin fixed role permissions.
2. Choose Script role as the database and choose **Generate Scripts**.
3. Choose **Next**.
4. Select **Select specific database objects**, then select **Users**.
5. Choose **Next**.
6. Select **Save as script file**.
7. Enter a location to save the file.
8. Choose **Next**.

A script will be generated in the provided location.

9. Run the copied script on the target RDS for SQL Server database.
10. Connect to your source Azure SQL Database with SSMS using the SQL database and match them with the RDS for SQL Server database by querying and joining the system tables:

```
sys.database_principals, database_role_members, database_permissions, and
sys.database_permissions.
```

Migrate object-level permissions

Complete the following steps to migrate object-level permissions:

1. Connect to your source Azure SQL Test SSMS with the primary user or user that has security admin fixed role permissions to script logins.
2. In the SSMS query editor, choose the **Results to Grid** option (Ctrl+D) option.
3. Run the following script from the new query window to generate the object-level permissions create script.

```
SET nocount ON;
WITH [object_permissions]
AS (SELECT permission_name,
           [state_desc],
           'OBJECT'                                    AS [type],
           Quotename(Schema_name(o.[schema_id]), '[') + '.'
           + Quotename(NAME,'[')                       AS [object_name],
           Quotename(USER_NAME(grantee_principal_id), '[') AS [principal]
    FROM   sys.[all_objects] AS o
           JOIN sys.[database_permissions] AS p
             ON p.major_id = o.[object_id]
    WHERE  class = 1)
SELECT 'USE [' + DB_NAME() + ']; ' + [state_desc] + ' ' + permission_name + ' ON '
       + [object_name] + ' TO ' + [principal] COLLATE database_default
FROM   [object_permissions]
```

4. Run the created object-level permissions script on the target RDS for SQL Server database and validate.
5. Connect to the target Amazon RDS for SQL Server using SSMS and copy the output scripts generated in Step 4.
6. Validate the script output for any errors.

Clean up

To avoid future charges, remove all of the components you created while testing this use case by completing the following steps:

1. On the Amazon RDS console, choose **Databases** in the navigation pane.
2. Select the database you want to delete and, on the **Actions** menu, choose **Delete**.
3. Follow the prompts to confirm deletion.

For more information about deleting an instance, refer to Deleting a DB instance.

Conclusion

In this post, we described how to migrate logins, database roles, users, and object-level permissions to Amazon RDS for SQL Server using T-SQL. If you have any questions or suggestions, leave a comment.

About the Authors

Indu Raja Kilpari is a Senior Lead Database Consultant at AWS. She has over 10 years of experience working with Microsoft technologies with a specialization in SQL Server. She focuses on helping customers build highly available, cost-effective database solutions and migrate their large-scale SQL Server databases to AWS.

Jitendra Kumar is a Lead Database Migration Consultant with AWS Professional Services. He helps customers migrate and modernize workloads to the AWS Cloud, with a special focus on modern application architectures and development best practices.

Ramesh Babu Donti is a Lead Database Consultant with AWS Professional Services based out of Hyderabad, India. He focuses on helping customers build highly available, cost-effective database solutions and migrate their large-scale SQL Server databases to AWS.

TAGS: Microsoft Azure SQL

Like | Share

Comments

Log in to comment

Sign In | Create Account