OSPREYFLOW

Installation and Administration Guide

OspreyFlow is an open-source intelligence mapping platform for crime analysis, anti-money-laundering, fraud detection, and event monitoring and alerting.

Version	1.63
Date	2026-11-10
Describes	OspreyFlow v0.4.12
Status	Issued

Document control

Version 1.63 · 2026-11-10 · For OspreyFlow v0.4.12 · Issued

Version	Date	What changed
1.63	2026-11-10	Admin's L2.7 and platform's P5 as built. §9.1: Proposed types removed, Connections' four kinds, Grading scheme built. §9.2: the role tips, *What each role and level lets a person do*, the refusal that names the roles, `write_sql_transforms` given on its own. §8: `map build --unit`. §10a: the unit the place names are held by, and a dataset's gazetteers (on screen, coming).
1.62	2026-11-10	§9.10: Admin's screen offers the dry runs, though its delete route exists, named.
1.61	2026-11-10	Promotion as built (case lane's L3.4). §9.10: a removed case's layer merged or deleted by the dataset's Authors in the Ingest Studio, Admin's dry runs. §9.11: promotions waiting for review, listed and overdue. §9.2: its words are copies of `help/roles.ts`, held to it by a test. §9.9: Disable's confirming button.
1.60	2026-11-09	Brought up to the product as built (docs lane, D2a). §9.1: Admin as a place of its own, its sections and each one's right, the coming ones said so. §9.2: the roles in the Glass's own words, the places each opens, every right in plain words, custom roles and the Super user. §9.3: the invite form as built. §9.5 and §9.6: where lists and influencers now live. New §9.8 teams and leads, §9.9 Disable and what a person owns, §9.10 datasets, their Authors and linked cases, §9.11 Operations and Audit. §10.1: Admin › Models. New §10a: Admin › Maps. §12: the Alert monitoring board in the Glass. §13: backups to a folder named at setup, coming. The architecture has its own guide now.
1.59	2026-11-09	§7: `grading.scheme`, the scheme drawn items are graded in (a built-in scheme or a scheme file). §8: `ospreyflow grading change`, its dry run and its change (ADR-143 decision 11 and Amendment 6). Appendix A regenerated: the `grading` section.
1.58	2026-11-09	Appendix A regenerated: `connectors.private_hosts`, the private hosts or networks an operator admits the Studio's SQL and API connectors to, and `connectors.secrets`, the connection secrets only the Conduit is given (ADR-140 Amendment 15).
1.57	2026-11-08	§8: `ospreyflow map list`, `map verify`, `map prefetch` and `map build` (ADR-147). Appendix A regenerated: a WMTS provider's `credential_param`.
1.56	2026-11-08	Appendix A regenerated from the deployment schema: `components.source_path`'s description, reworded without a build-calendar note.
1.55	2026-11-05	Describes v0.4.12 (v0.4.11 was not released). No change to its content.
1.54	2026-11-05	Describes v0.4.11. No change to its content.
1.53	2026-11-05	The owner's rulings (build order step 33; ADR-112 Amendment 3, ADR-114 Amendment 33 "Step 33"): §5a.1, someone whose email an account holds can be joined to that account in Admin → People, or the account removed; joining by email (`sign_in.organisation.trust_email`, off by default) and its account-takeover risk; §7 the answer; §8 what `repair-sign-in` now also does; §9.1 and new §9.7, removing someone and joining an organisation account; §16 the refusal's new answers, an empty *Refused organisation sign-ins*, the Conduit needing `view-events`, a refused removal, and the joining-by-email warning. Appendix A: `governance.organisation_provider.trust_email`.
1.52	2026-11-04	The owner's ruling (build order step 29; ADR-114 Amendment 34): §14, an offline bundle carries one platform's images, `linux/amd64` unless `ospreyflow update --make-bundle FILE --platform linux/arm64` names the other, from any machine; any other platform is refused, and `update --from` refuses a bundle for another platform than its machine's, in words, before anything is checked or loaded.
1.51	2026-11-04	The owner's rulings on sign-in (build order step 28): §5a.1, the welcome page's button names the organisation's provider by `sign_in.organisation.label` (ADR-115 Amendment 5), and someone whose email an OspreyFlow account already holds is told so in words and never joined to it (ADR-114 Amendment 33); §8, `repair-sign-in` also gives the workspace's client no refresh token (ADR-050 Amendment 2) and registers the organisation's first sign-in; §9.1, Admin → System's **Acting for people** says when the Conduit cannot act for people and to run `ospreyflow repair-sign-in` (ADR-114 Amendment 36); §16, that line, an arrival whose email is held, and windows that ask to sign in again after about half an hour left alone (a window renews only after the person has done something, ADR-050 Amendment 2). Appendix A: `governance.organisation_sign_in` and `governance.organisation_provider.label` name the button.
1.50	2026-11-04	The owner's ruling (ADR-099 Amendment 11; build order step 27), "no role, no list": §5a.1 and §9.2, a person holding no role is told no dataset's name or id, even when their unit is set before a role; Home says *No cases to show* when they hold no case.
1.49	2026-11-04	As found on the first server (ADR-114 Amendment 35 point 7): §13 and §14, Valkey's data was inside its container and is now moved too; a move that is refused puts back every file the command wrote, so `ospreyflow start` runs the deployment on its old data, and its words say so; the move checks each store apart from the deployment's own containers; a restore starts the identity provider again after PostgreSQL. §16 the move's refusal, and a restore refused with "could not authenticate to Keycloak: 500".
1.48	2026-11-04	The owner's ruling (ADR-114 Amendment 35; build order step 26): the stores keep their data in named volumes. §8 `uninstall --keep-data` now keeps data a later install finds; §13 where each store's data is kept, what a backup reads, and OpenSearch; §14 the one-time move of an existing deployment's data, its words, and what a failed move does to an update; new §14.1 removing the old volumes; §16 a move that is refused.
1.47	2026-11-04	The owner's ruling (ADR-127 Amendment 46; build order step 25): §1a and §11, the Prison Intelligence pack handles post-ingest resolution itself — an install that chooses it writes `components.post_ingest_resolution: false`, and `ospreyflow demo add prison-intelligence` refuses, in words, while it is on.
1.46	2026-11-04	The owner's ruling (ADR-114 Amendment 33; build order step 25): §5a and §7, `server.certificate` and `server.key` are required, and an answers file without them is refused in words; the doctor no longer checks port 80 for a certificate the proxy would obtain itself.
1.45	2026-11-04	Found on the first server (ADR-114 Amendment 33; build order step 25): §4 and §5a, the install waits for the extraction model to download, says so with its size, and only then says it is installed.
1.44	2026-11-04	Describes v0.4.10. No change to its content.
1.43	2026-11-04	§5a.4: on a GPU the model stays loaded (`OLLAMA_KEEP_ALIVE=-1`), so the first question after a pause does not wait for it to load.

Version	Date	What changed
1.42	2026-11-04	Describes v0.4.9. No change to its content.
1.41	2026-11-04	The owner's ruling (ADR-132 Amendment 5): §1a, the GOV.UK service's name is shown in the page title on every page, the sign-in page's included; no band under the GOV.UK header names it any more. Appendix A: `appearance` and `appearance.service_name` say the same.
1.40	2026-11-04	As measured and found on the first server (ADR-135 Amendment 1, ADR-114 Amendment 33): §5a.4 the model server's KV cache at q8_0 with flash attention on a GPU, the measured times, the doctor's 14 GiB for the 14b (was 12), and `apply` fetching a newly chosen model; §13 the object store copied as the account that runs the backup, and a failed backup's set it cannot remove marked incomplete; §16 a backup refused with "Permission denied", and Ask failing after the extraction model changed.
1.39	2026-11-04	Found on the first server (ADR-114 Amendment 33): §5a the Ingest Studio's upload folder, given to the Conduit's user (uid 10001) before anything starts, and never writable by every account; §16 an upload or a demo pack refused with "Permission denied" on Linux.
1.38	2026-11-04	Describes v0.4.8. No change to its content.
1.37	2026-11-04	Describes v0.4.7. No change to its content.
1.36	2026-11-04	The owner's ruling (ADR-114 Amendment 33): the first administrator holds the Admin and the Analyst roles from the start, whether or not demo packs load, so the cases they author open for them. §1a and §11 no longer ask anyone to give them the Analyst role; §5 and §5a say which roles the account is made with; §9.2 says so too, and that an `admin` made by v0.4.6 or earlier needs the Analyst role added.
1.35	2026-11-04	Found installing Small on the first server of its own (ADR-114 Amendment 33): §1a and §11 a demo pack on a deployment with no demo accounts — its case's Author is the first administrator, in their own unit, with no Editor, and the Admin role does not open a case's graph until someone holds the Analyst role; §5a the answers' `demo_packs` load after the first administrator exists, the installing account's umask does not matter, and `ca` must be readable by every account; §13 a fresh deployment's first backup, its empty items, and a failed backup leaving no partial set; §16 an unreadable CA.
1.34	2026-11-04	The local engine on an NVIDIA GPU (ADR-135 Amendment 1): §2.2a the NVIDIA driver and Container Toolkit, installed by the server's administrator; §2.4 and §5a the doctor's GPU checks; §5a the answers file's `server.gpu`; new §5a.4, what the GPU changes (the model server alone reserves it; the 14b extraction model unless one is named), what is checked before anything starts, and Lite on a Linux computer; §7 `server.gpu`; §16 a refused GPU. Appendix A: `resources.gpu`, and `models.extraction`'s default on a GPU.
1.33	2026-11-04	Describes v0.4.6. No change to its content.
1.32	2026-11-04	§5a: a `DOCKER-USER` rule that matches only arriving connections (`--ctdir ORIGINAL`), found on the first Linux server.
1.31	2026-11-04	Describes v0.4.5. No change to its content.
1.30	2026-11-03	Small on your own server, second part (ADR-114 Amendment 33 drop 2): §2.2a the backups folder and what the organisation's sign-in needs; §5a the answers file's `server.backups`, `server.memory_gib` and `sign_in`, and the doctor's new checks; new §5a.1 sign-in through the organisation's identity provider (Entra ID: the application, its two addresses, its client secret, assignment, the route out; no role until an administrator grants one); new §5a.2 memory sized to the server; new §5a.3 backups to `server.backups` with a cron line; §7 the answers' settings; §8 `repair-sign-in` restores the organisation's sign-in and gives a Small no demo accounts; §13 and §14 backup and `update` on this kind of Small; §16 the organisation's sign-in and the backups folder. Appendix A: `governance.organisation_provider`, `resources`.
1.29	2026-11-03	Small on your own server (ADR-114 Amendment 33, first part): §1 a fourth column and the organisation's own certificate under "HTTP or HTTPS"; new §2.2a, its prerequisites; §2.4 `ospreyflow doctor --mode small --config install.yaml`; new §5a, installing it — the answers file's `server:`, the three names and the one-label wildcard, what is checked before anything starts, port 443 alone, the first administrator, renewing the certificate, and what is not built yet; §5.2's refusal names all three ways; §7 `server`, `admin_email`, `sign_in`; §8.1 what it publishes; §16 the certificate's refusals and a network that cannot connect. Appendix A: `network.tls`, `network.redirect_http`, `network.listen_address`.
1.28	2026-11-03	§8: `ospreyflow repair-sign-in` also sets the Conduit's own client secret again, so a deployment whose stores were wiped can act for its people again. §16: rules that say "the rule's deployer could not be resolved", a hotlist that stops, and a list refresh that re-screens no one.
1.27	2026-11-03	"How OspreyFlow is built": a level 0 diagram (who uses OspreyFlow and what it talks to), a level 1 diagram (every component with the technology it is built on, and what each mode runs on), and a new section, "The interfaces, and what crosses each", giving each interface's direction, protocol, what crosses it and what guards it.
1.26	2026-11-02	Checked against the code end to end (build order step 10). §10: Ask to search carries the case's handling and datasets, so the analyst's engine choice applies to it as to Ask the case; it no longer always runs on the local engine.
1.25	2026-11-02	§9.2: the right to manage connection-strength influencers, held by the Analyst and Admin roles. §9.6: approving an installation-wide influencer version, a second person's decision; a case's own influencers need none.
1.24	2026-11-02	§1, "HTTP or HTTPS": Lite now answers on this computer only — every port it publishes is bound to `127.0.0.1`, the Conduit's own port included — so other machines cannot reach it; Small and Enterprise must have an `https://` address, and `osprey.yaml` refuses a plain-HTTP one; a gov.uk address is refused for Lite. §8.1 says the same.
1.23	2026-11-02	§1: a note, "HTTP or HTTPS" — Lite is plain HTTP on a `localhost` address and has no HTTPS option, and its port is published on every network interface, so it is never opened to a network; Small and Enterprise are HTTPS with a certificate Caddy obtains and renews, port 80 only for the certificate and the move to HTTPS; the managed services over TLS; a gov.uk service over HTTPS. §8.1 links to it.
1.22	2026-11-02	New §1a, Choosing a starter: a theme and a domain at install (`--starter`, and the guided page's first screen), the GOV.UK service's name, several deployments side by side (`--name`, `ospreyflow deployments`, `ospreyflow switch <name>`) and how the checkout's own deployment fits in, and a public dataset of your own choosing (`ospreyflow demo add public`) with the VAST Challenge catalogue and its terms. §7: `starter`, `appearance`, `demo_accounts`. §8: `ospreyflow deployments`, `ospreyflow starters`, `--name`. §11: the `cyber-intrusion` pack, and where each starter's demo comes from. Appendix A: `deployment.graph_port`.

Version	Date	What changed
1.21	2026-11-01	§9.5: a sixth connector, the FCDO's UK Sanctions List (the XML file, Open Government Licence v3.0); the OFSI connector marked as reading a closed list, on the Lists tab and in the subscribe form. §12: the `closed` section's labels are the five closing reasons as stored.
1.20	2026-11-01	§9.5: the UN and OpenSanctions connectors are marked "licence not confirmed" and read OspreyFlow's synthetic lists only, whatever this device's exceptions admit; the refreshes' counts of customers re-screened and alerts raised are your own unit's.
1.19	2026-11-01	§9.5: a list's refresh schedule, set in Monitoring → Lists and run as the person who set it. §9.6: approval rights — a second person for a rule for the whole deployment and for closing a high-severity alert, and who holds the right to approve; whole-deployment rules live before this version wait for approval after upgrading.
1.18	2026-11-01	§9.5: screening lists — subscribing to a list through its connector, each list's licence, the rule on real lists, and the refresh (*Refresh now*, `python -m scripts.refresh_screening_list`), which re-screens customers against the changed entries only.
1.17	2026-11-01	§12: the monitoring board, and the four monitoring sections the feed carries (`raised_by_rule`, `closed`, `time_to_close`, `hotlist_matches`).
1.16	2026-11-01	§9.4: monitoring, and whom a hotlist's alerts reach (`monitoring.hotlist_audience`, `hotlist_audience_editable`). Appendix A: the `monitoring` settings.
1.15	2026-11-01	§9.1: the Datasets tab. §10: a provider's privacy-contract mark (`privacy_contract`, `contract_reference`); each dataset's egress (`none`, `contracted`, `any`), set in Admin → Datasets and audited; every dataset is `none` after upgrading, so hosted engines receive nothing until an administrator changes one. Appendix A: the two new provider settings.
1.14	2026-11-01	§8: `ospreyflow apply`, and a new §8.3, "Changing a setting". `deployment.env` is readable by its owner alone. §10: a provider enabled on a running deployment, and key entry on the guided install's Models screen.
1.13	2026-11-01	§10 rewritten for several model engines: providers, defaults, labels, keys as `OSPREY_MODEL_KEY_<NAME>`, and what may leave. §8: `ospreyflow models`, `models key` and `models remove-key`. Appendix A: `models.providers`, `models.defaults` and a provider's `label`.
1.12	2026-11-01	The opening says what OspreyFlow is for: intelligence mapping, for crime analysis, anti-money-laundering, fraud detection, and event monitoring and alerting.
1.11	2026-11-01	§8: `ospreyflow switch`. Appendix A: `deployment.name`, the `appearance` settings (the GOV.UK look), and relative storage paths.
1.10	2026-10-29	§11: the Prison Intelligence pack's rehearsal commands are in `DEMO_GUIDE.md`, not the user guide.
1.9	2026-10-29	§11: the two Prison Intelligence packs, the demonstration case and its scale cohort.
1.8	2026-10-28	Describes v0.4.0. No change to how it is installed, updated or looked after.
1.7	2026-10-27	Appendix A: `components.post_ingest_resolution`, whether a load queues entity resolution afterwards.
1.6	2026-10-18	§11: the HMP pack as a prison intelligence network, and adding it again after an update.
1.5	2026-10-15	A cover page, contents, a list of figures, and this version history.
1.4	2026-10-15	§16: a model download that stopped with `rename …-partial …`, and how to finish it.
1.3	2026-10-15	§11: the Enron email corpus as an optional download, with its safeguards.
1.2	2026-10-14	`ospreyflow repair-sign-in`; no step sends an operator to `make`.
1.1	2026-10-14	§14 rewritten: which installs `update` moves, and checking for and moving to a release.
1.0	2026-10-14	First issue in the install package, with screenshots.
0.4	2026-10-14	Enterprise built from your own computer: `install --mode enterprise --cloud`.
0.3	2026-10-14	Enterprise on Kubernetes: the cluster's namespace, storage classes and managed services.
0.2	2026-10-14	The guided install page ships with each release.
0.1	2026-10-13	Lite and Small, with every setting taken from the deployment's own schema.

Contents

How OspreyFlow is built 7
The interfaces, and what crosses each 8
1. Choosing a mode 10
HTTP or HTTPS 10
1a. Choosing a starter 11
1a.1 Several deployments side by side 11
1a.2 Adding a public dataset 12
2. Before you start 13
2.1 Lite 13
2.2 Small 13
2.2a Small on your own server 13
2.3 Enterprise 13
2.4 Checking a machine: ospreyflow doctor 13
3. Getting the ospreyflow command 14
4. Installing Lite 14
4.1 The guided page: ospreyflow install --gui 14
5. Installing Small 14
5.1 What is made in your account 15
5.2 On the server, by hand 15
5a. Installing Small on your own server 15
5a.1 Sign-in through the organisation's identity provider 17
5a.2 Memory 18
5a.3 Backups 18
5a.4 The local engine on an NVIDIA GPU 18
6. Installing Enterprise 19
6.1 What is made in your account 19
7. The answers file, install.yaml 20
8. Running it 20
8.1 Addresses 21
8.2 Where things are 21
8.3 Changing a setting 22
9. People and accounts 22
9.1 The Admin place 22
9.2 Roles 23
9.3 Inviting someone 25
9.4 Monitoring: whom a hotlist's alerts reach 25
9.5 Screening lists: subscribing, licences and the refresh 25
9.6 Approval rights: a second person 26
9.7 Removing someone, and joining an organisation account 27
9.8 Teams and leads 27
9.9 Disable, and what a person owns 27
9.10 Datasets, their Authors and linked cases 27
9.11 Operations and Audit 28
10. Models 28
10.1 Models in Admin 29
10a. Maps 29
11. Demo packs 29
12. Dashboards 30
The monitoring board 31
13. Backup and restore 32
14. Updates 32
14.1 Removing the old store volumes 34
15. Scheduled and watched pipelines 34
16. When something is wrong 35
Appendix A — every osprey.yaml setting 36

List of figures

Figure 1 — Level 0: the people who use OspreyFlow, its three tiers joined by four ports, and the identity provider, reporting, data in and the optional outside services beside it 7
Figure 2 — Level 1: every component by tier with the technology it is built on, the ports between the Conduit and the Vault, identity, reporting, and what each mode runs on 8
Figure 3 — Admin → People and roles: each person's roles, with Access, Disable and Reset sign-in 23
Figure 4 — A person's access opened under their row: clearance, unit and handling codes 25
Figure 5 — Admin → Demo packs: what each pack shows, where it was loaded, and the command for the rest 30
Figure 6 — Admin → Dashboards: registering a dashboard's account and seeing when it last pulled 31
Figure 7 — Superset at bi.: the boards and charts built on the reporting figures 31
Figure 8 — Admin → System: each component's health, the models in use, the version, and the last update check 33
Figure 9 — Admin → Schedules and runs 35

OspreyFlow is an open-source intelligence mapping platform for crime analysis, anti-money-laundering, fraud detection, and event monitoring and alerting.

For whoever installs OspreyFlow and looks after it: **Lite** (one computer), **Small** (one cloud server on the cloud's managed services, or one server of your own with every store on it) and **Enterprise** (a Kubernetes cluster on the cloud's managed services). It describes what is built, and says plainly where something is not yet.

The other guides in this folder are the user guide (user-guide.pdf), for analysts, and the developer guide (developer-guide.pdf), for data engineers. Appendix A, every `osprey.yaml` setting, is made from the deployment's own schema, and is checked against it on every change.

How OspreyFlow is built

The architecture guide (architecture-guide.pdf) describes it in full, for a reader deciding whether it fits; this is what an administrator needs.




Figure 1. Level 0: the people who use OspreyFlow, its three tiers joined by four ports, and the identity provider, reporting, data in and the optional outside services beside it

Three tiers; everything that passes between them crosses one of four typed ports:

Tier	What it is
The Glass	The browser workspace, one web application with four places: the Glass itself (the graph, map, timeline and figures), the Ingest Studio, Rules and Monitoring, and Admin
The Conduit	The API (FastAPI). Every request is checked against the person making it: access control is applied inside each query to the stores, never after
The Vault	The stores: the graph store (ArcadeDB), the analytics database (DuckDB inside the Conduit, or ClickHouse shared by several Conduits), search (OpenSearch, or PostgreSQL full-text), PostgreSQL, the object store, and the models

Port	What passes through it
GraphPort	Typed traversal of the graph, with the person's clearance and handling injected into it
AnalyticsPort	Events, trends and histograms
ComputePort	Graph algorithms: centrality, communities, ownership chains
ModelPort	Extraction, vision, transcription and embedding, through the LiteLLM gateway

Two narrower ports sit beside them: the media store, for content files (an S3-protocol store — SeaweedFS or AWS S3 — or Azure Blob), and the recognition port.

The level 1 diagram names the technology in each component. Versions are those the release pins; Small and Enterprise use the cloud's managed services where the diagram's last row says.




Figure 2. Level 1: every component by tier with the technology it is built on, the ports between the Conduit and the Vault, identity, reporting, and what each mode runs on

One door in. A front proxy (Caddy) is the only published port: 80 on Lite, 80 and 443 with automatic HTTPS on Small and Enterprise. Behind it, at the deployment's address, are the Glass; sign-in (Keycloak) at `id.`; and dashboards (Superset) at `bi.`.

No route out by default. Every container sits on an internal network with no route to the internet. One joins the egress network only when a configured feature needs it: the model and speech-model downloads, the proxy's certificate, a client's own model provider, mail, an organisation's own sign-in, online map tiles, and on Small and Enterprise the cloud's managed services.

What the data is. Model-derived data stays *inferred* until a person confirms it. Records are never merged in storage: matching records are linked with a score and shown as one at query time. Every read is checked against the reader's clearance, unit and handling codes, and a hidden record cannot be detected from a count, a path length or a chart.

The interfaces, and what crosses each

Each interface has one direction, one owner and one guard. None of them lets a store's own query language, a source system's identifier or an unfiltered count reach the Glass.

Interface	From → to	How	What crosses	Guarded by
The front door	Browser → front proxy (Caddy) → the Glass, the Conduit (`/v1`, through the Glass's nginx), sign-in at `id.`, dashboards at `bi.`	HTTPS on 443, with 80 only for the certificate and the move to HTTPS (Small, Enterprise); HTTP on 80, bound to `127.0.0.1` (Lite)	Every request	The only published port; every other container is on an internal network

Interface	From → to	How	What crosses	Guarded by
Sign-in and token	The Glass, Superset → identity provider → the Conduit	OpenID Connect, authorisation code with PKCE; a signed JWT access token	Credentials, typed only at the identity provider; then who the person is, their clearance, unit, handling codes and roles	Every token's signature checked against the provider's keys on every call
Rights	The Conduit → the Glass (`GET /v1/me/rights`)	REST	What this person may do; the rail and menus follow it	Each route checks its own right, so the Conduit refuses whatever a stale screen offers
The API	The Glass → the Conduit (`/v1/…`)	HTTPS, JSON, a bearer token on every call	Searches, working sets, edits, loads, reports, exports	Access control inside each store query; a result too large is refused with `limit_exceeded`, never cut silently
Live updates	The Conduit → the Glass	WebSocket `/v1/investigations/{id}/stream`, opened with a one-time ticket that lasts 30 seconds; server-sent events for long-running progress	Changes to the open case; progress	The ticket is the person's own; the same access as the API
Administration	The Admin area → the Conduit (`/v1/admin/…`) → the identity provider's admin API	REST	People, roles and access; datasets and their egress; dashboard identities; schedules; health and freshness	Administration rights (`manage_people`, `manage_dashboards`, `administer_system` and others); a dashboard is never given more than its registrar holds
Case access	The Share panel → the Conduit (`/v1/investigations/{id}/access`)	REST	Who holds Viewer, Editor or Author on the case, by account id	The case's Author; every change kept in the case's history
GraphPort	The Conduit → the graph store (ArcadeDB)	Gremlin over ArcadeDB's HTTP API, on the internal network only	Typed traversals; writes; a load's revert	The person's clearance and handling codes and the case's datasets are part of the traversal itself
AnalyticsPort	The Conduit → DuckDB (inside the Conduit) or ClickHouse (HTTP)	In process, or HTTP on the internal network	Event aggregates, trends and histograms; never raw SQL from the Glass	The same filters inside the query; no count includes a record the reader cannot see
ComputePort	The Conduit → rustworkx and NetworkX; the Glass → graphology in a Web Worker	In process	Centrality, communities, ownership chains	Computed over what the reader can see only; the two engines are held to the same conformance suite
ModelPort	The Conduit → LiteLLM → Ollama, speaches, or a provider you configure	HTTP, OpenAI-compatible	Text, images and audio to extract from, describe, transcribe or embed; what returns is *inferred* until a person confirms it	Each dataset's egress (`none`, `contracted`, `any`) and the handling codes that may be sent (§10)
Recognition	The Conduit → the NER sidecar (Stanza)	HTTP on the internal network	Text to tag with names, places and organisations	No route out; what it finds is *inferred*
Media store	The Conduit and the ingest container → SeaweedFS, S3 or Azure Blob	The S3 protocol, or Blob's API	Content files, staging, site images, the tile cache	Private, encrypted storage; files reach the Glass only through the Conduit
Records, cache and search	The Conduit → PostgreSQL, Valkey, OpenSearch	The internal network (TLS and a token on Enterprise's managed cache)	The Conduit's own records and audit; caches, the job queue and the change stream; text search	Reached only from the deployment's own network

Interface	From → to	How	What crosses	Guarded by
Ingest	The Ingest Studio, the ingest folder and connectors → the Conduit → the ingest container	REST; a watched folder	Files and rows, loaded under a published recipe	`edit_pipelines` and `schedule_pipelines`; a run is made as the person who set it; the case's rules judge each load before and after it commits, and hold the rows they refuse
Reporting feed	report-sync → the Conduit (`/v1/reports/feed`)	REST, with the dashboard identity's own client credentials	Figures only, counted as that dashboard	The dashboard's own token and the cases it was given; every pull in the export ledger
Reporting mart	report-sync → PostgreSQL `osprey_reports` → Superset or another BI tool	SQL, a read-only login	The feed's rows; pull times and failures	A read-only login; never the Conduit's own tables
Embedded board	The Glass → the Conduit → Superset	Superset's embedded SDK, with a read-only guest token that lasts five minutes	One board	Given only to a viewer who could count every figure on it
Updates	`ospreyflow update` → the repository's releases on GitHub and its images on `ghcr.io`	HTTPS	The list of releases, the release's lock and its images	The release's signature, made by this repository's own release workflow, checked with cosign before anything changes (§14)
Outside services	A container on the egress network → model and speech-model downloads, a provider you configure, mail, your organisation's sign-in, online map tiles, the cloud's managed services	HTTPS	Only what the feature needs	A container joins the egress network only when its feature is switched on

1. Choosing a mode

	Lite	Small	Small, on your own server	Enterprise
Where it runs	One computer (a laptop or a workstation)	One cloud server (AWS or Azure)	One Linux server you provide, inside your own network	A Kubernetes cluster (EKS or AKS), three or more nodes
Who looks after the data	You, with `ospreyflow backup`	The cloud: managed PostgreSQL, S3 or Blob, daily backups	You: every store is in a container on the server's disk (section 5a)	The cloud, for its managed services; the graph store in the cluster is not yet backed up (section 13)
Its address	`http://ospreyflow.localhost`	`https://<your domain>`	`https://<a name in your network>`, with your organisation's certificate	`https://<your domain>`
First sign-in	Demo accounts, passwords in `deployment.env`	A first administrator, by a one-time code	A first administrator, by a one-time code	A first administrator, by a one-time code
Built with	`ospreyflow install --mode lite`	`ospreyflow install --mode small --cloud aws|azure`, from your own computer	`ospreyflow install --mode small --config install.yaml` with a `server:` section, on the server	`ospreyflow install --mode enterprise --cloud aws|azure`, from your own computer, or onto a cluster you already have

All three run the same product: the same containers, the same Glass, Ingest Studio and Admin area. Small swaps the deployment's own PostgreSQL and object store for the cloud's, and gets a real domain with HTTPS. Small on your own server keeps every store in a container, as Lite does, and is reached over HTTPS with your organisation's own certificate, on port 443 alone. Enterprise runs the same services as replicas across the cluster's nodes, the graph store and the analytics database as clusters of their own.

HTTP or HTTPS

- **Lite serves plain HTTP** at a `localhost` address: `http://ospreyflow.localhost`, or a named deployment's `http://<name>.localhost:<port>` (section 1a.1). That is deliberate. Lite is for one computer, its traffic is meant to stay on that machine, and browsers treat `localhost` as a secure context, so sign-in works without a certificate.
- **Lite has no HTTPS option.** The install, the guided page and every starter give it an `http://…localhost` address, and Lite is not built or tested with a certificate.
- **Lite answers on this computer only.** Every port a Lite deployment publishes — the front proxy's, the graph store's and, when `network.expose_conduit` is on, the Conduit's — is bound to this computer's own address (`127.0.0.1`), so other machines on a network cannot reach it, whatever the firewall allows. A deployment kept by name (section 1a.1) is Lite, so the same holds. Use Small or Enterprise for anything other people reach.
- **Small and Enterprise serve HTTPS** at `https://<your domain>`, and must: `osprey.yaml` refuses a Small or Enterprise deployment whose `network.public_origin` is not an `https://` address, and `ospreyflow apply`, the guided page and the Set-up console say so and change nothing. The front proxy (Caddy) obtains the certificate for your domain and renews it automatically. Port 80 is open only for the certificate's challenge and to send a request for your domain on to HTTPS (443); any other request on port 80 gets "not found", apart from the proxy's own health check. On Enterprise, the cluster's load balancer passes 80 and 443 to the proxy.

- **Small on your own server serves HTTPS with your organisation's own certificate** (section 5a): the front proxy is given the certificate and key, obtains nothing and calls nothing; it publishes port 443 alone (80 only if you ask, and then only to send people to 443). The certificate is checked before anything starts.
- **The managed services behind Small and Enterprise are reached over TLS:** PostgreSQL always (`sslmode` is `require` at least), the object store always over HTTPS, and the cache and the mail server over TLS unless you turn it off (`external.*` and `mail.starttls`, Appendix A).
- **A service on a gov.uk domain must be served over HTTPS,** the GOV.UK theme included, so it is Small or Enterprise, never Lite: `osprey.yaml` refuses a Lite deployment at a gov.uk address. The GOV.UK theme on a `localhost` address stays available for a demonstration on one computer.

1a. Choosing a starter

A **starter** is a theme and a domain, chosen at install. It only fills in answers the install already asks — the look, the GOV.UK service's name, organisation and phase, the demo packs and whether demo accounts are made — and every one can still be changed. The `osprey.yaml` it makes records the starter in a comment at the top; nothing at run time reads it. Every domain pack (FIBO, NIEM, STIX) stays available to every case whatever the starter: the domain chooses the demo data and what its demo cases are set to, never what the ontology offers.

	`crime`	`aml`	`fraud`	`cyber`	`blank`
Demo case's domains	NIEM	FIBO	FIBO	STIX	none chosen
Demo data	`prison-intelligence`, `hmp`	`operation-ledger`, with its synthetic screening lists	`fixture-corp`; PaySim offered as your own download, never fetched	`cyber-intrusion`	none, and no demo accounts
`ospreyflow` theme (the base look)	`ospreyflow-crime`	`ospreyflow-aml`	`ospreyflow-fraud`	`ospreyflow-cyber`	`ospreyflow-blank`
`govuk` theme (GOV.UK, a gov.uk service only)	`govuk-crime`	`govuk-aml`	`govuk-fraud`	`govuk-cyber`	`govuk-blank`

`ospreyflow starters` (or `ospreyflow install --list-starters`) prints the same table and the command for each.

A starter that loads `prison-intelligence` (`crime`) also writes `components.post_ingest_resolution: false` into the `osprey.yaml` it makes, and says so: that pack needs post-ingest resolution off (section 11), and resolution is the whole deployment's setting, so the deployment's other demo cases do not gain automatic "same as" links either. An analyst's own Resolve now still works. The same holds for any answers file whose `demo_packs` names it; one whose own `osprey.yaml` (`config:`) sets it `true` is refused before anything is installed.

One command per starter. Add `--yes` to take every other default; leave it out to be asked.

```
ospreyflow install --mode lite --starter ospreyflow-crime
ospreyflow install --mode lite --starter ospreyflow-aml
ospreyflow install --mode lite --starter ospreyflow-fraud
ospreyflow install --mode lite --starter ospreyflow-cyber
ospreyflow install --mode lite --starter ospreyflow-blank
ospreyflow install --mode lite --starter govuk-crime --service-name "Analyse crime intelligence" --organisation "<your
organisation>"
ospreyflow install --mode lite --starter govuk-aml --service-name "Investigate money laundering" --organisation "<your
organisation>"
ospreyflow install --mode lite --starter govuk-fraud --service-name "Investigate fraud" --organisation "<your
organisation>"
ospreyflow install --mode lite --starter govuk-cyber --service-name "Investigate cyber incidents" --organisation "<your
organisation>"
ospreyflow install --mode lite --starter govuk-blank --service-name "<your service's name>" --organisation "<your
organisation>"
```

The GOV.UK theme asks for the service's name, organisation and phase (`--service-name`, `--organisation`, `--phase alpha|beta|live|none`; the phase offered first is `beta`). Without a service name the install is refused, in words, before anything is changed. **Name the service, not a case:** the name is the page title (the browser tab's "<name> – GOV.UK") on every page of every case, so the names offered above describe the whole deployment; "Prison Intelligence" over the Ledger's case is the mistake this avoids. `blank` offers no name: a real service names itself.

On the guided page (`ospreyflow install --gui`, section 4.1) the starter is on the first screen, Mode, under **Starter (optional)**; a GOV.UK starter shows the service's name (filled in with the name above), organisation and phase there. The Demo packs screen then shows the starter's packs ticked, to change if you wish.

In an answers file (section 7): `starter: govuk-aml`, with `appearance.service_name`, `appearance.organisation` and `appearance.phase`.

On a deployment with no demo accounts — Small, on a cloud server or your own — a starter's demo packs still load, each into its own case, with the first administrator (`admin`) as its Author, in the administrator's own unit, and no Editor. The first administrator holds the Analyst role as well as Admin (section 9.2), so the case opens for them; they can share it from there.

1a.1 Several deployments side by side

`--name` keeps a deployment of its own beside any other on the same computer:

```
ospreyflow install --mode lite --name crime-demo --starter ospreyflow-crime
ospreyflow install --mode lite --name aml-govuk --starter govuk-aml --service-name "Investigate money laundering" --
organisation "<your organisation>"
```

Each one has:

- its own folder, `~/.ospreyflow/deployments/<name>/`, holding its `osprey.yaml`, every file rendered from it and its `deployment.env` (readable by your account alone, `600`; the folder is `700`);
- its own Compose project and volumes, named `<name>`: no case, account or index is shared;
- its own address — `--address`, by default `http://<name>.localhost:<the next free port>` from 8090 — and its own graph-store port on this computer (`deployment.graph_port`, from 2500).

A name that Docker already knows as another folder's Compose project is refused, before anything is written: two deployments under one name would share containers. The checkout itself is shared; no second checkout or worktree is needed.

Every command takes `--name`: `ospreyflow start --name crime-demo`, `ospreyflow status --name aml-govuk`, `ospreyflow demo add hmp --name crime-demo`, `ospreyflow backup --name aml-govuk` (whose backups are kept in the deployment's own folder). Without `--name`, a command acts on the deployment last used, or on the only one there is.

```
ospreyflow deployments          # each one's name, starter, address and whether it is running
ospreyflow switch aml-govuk     # stop the running one, start aml-govuk, open it
ospreyflow switch default       # back to the checkout's own
```

A Lite computer runs one deployment at a time by default, which is what `ospreyflow switch` is for.

The deployment installed in the checkout — every install before this version, with its `osprey.yaml` in the checkout and its files in `deploy/generated/` — is listed as `default` and works exactly as before: no command moves, renames or changes it. It could later be moved under `~/.ospreyflow/deployments/` (install a named deployment, restore a backup of the checkout's into it, check it, then uninstall the checkout's with `--keep-data` until you are sure); that is a step for the administrator to take deliberately, never something an update does.

1a.2 Adding a public dataset

A public dataset you download yourself can be added to any deployment, at install or later:

```
ospreyflow demo add public --file <the downloaded file> --manifest <its dataset.yaml>
```

A **manifest** says what the dataset is, its source page, its licence or terms as the source states them, the file's SHA-256, whether it holds real people's data, and the Ingest Studio recipe that loads it. The file is checked against the checksum before anything else happens; a file that differs is refused, and nothing is loaded. It loads into a case of its own, named after the dataset.

Real personal data (`real_personal_data: true` in its manifest) is loaded only once you type `yes`, accepting that it is real people's data and that your organisation has its own lawful basis to process it — as for Enron (section 11); `--accept-real-data` accepts in a scripted run. It never belongs in a repository or a test run.

The VAST Challenge catalogue. OspreyFlow ships manifests and recipes — never the data — for two IEEE VAST Challenge datasets, fictional scenarios published for visual-analytics research:

Catalogue id	Dataset	Suits	Source
`vast-2012-mc2`	VAST Challenge 2012, Mini-Challenge 2: the fictional Bank of Money's regional network — its firewall log (`Firewall-04072012.csv`)	the `cyber` starter (its case is set to STIX)	the Visual Analytics Benchmark Repository, University of Maryland
`vast-2008-mc3`	VAST Challenge 2008, Mini Challenge 3: cell phone call records on the fictional island of Isla del Sueño (synthetic)	the `crime` starter (its case is set to NIEM)	the same repository

Their terms. Neither the source pages, nor the challenges' task pages, nor the repository's mirror at Washington University state any licence or terms of use (checked 2 November 2026). No licence means no right to redistribute is granted: download the data yourself, use it on your own computer, never pass it on, and do not rely on it for commercial use without the publishers' permission. Each manifest says so.

Their checksums. OspreyFlow never downloads VAST data, so the catalogue records no checksum, and `demo add public` refuses an entry until you record the checksum of the file you downloaded:

```
python -m scripts.public_dataset --list
python -m scripts.public_dataset pin --manifest vast-2012-mc2 --file Firewall-04072012.csv --out ~/OspreyFlow/vast-2012-
mc2.yaml
ospreyflow demo add public --file Firewall-04072012.csv --manifest ~/OspreyFlow/vast-2012-mc2.yaml --name crime-demo
```

`pin` writes your own copy of the manifest, with the recipe beside it; check first that the file came from the source page, since what you pin is what every later check holds the file to. The column layout each recipe reads is the challenge's published one; check it against your download's first line.

2. Before you start

2.1 Lite

- **Docker**: Docker Desktop on macOS and Windows (on Windows with the WSL 2 back end); Docker Engine with the Compose v2 plugin on Linux. Set it to start when you sign in: the stack comes back after a reboot only once Docker does.
- **Memory**: at least 16 GB available to Docker (32 GB is comfortable).
- **Disk**: at least 60 GB free, plus the demo packs you choose (PaySim is about 0.5 GB to download and more once loaded).
- **Git**, and **internet** for the first install.
- **Port 80 free** (the deployment's one door).

2.2 Small

On your own computer, from which you build the server:

- an **AWS or Azure account** you may create resources in;
- **OpenTofu** (`tofu`), which builds the server;
- the cloud's **command line** (`aws` or `az`), signed in to that account;
- **Git** and **uv**;
- a **DNS name** you control, such as `osprey.example.org`. If the name's zone is in the same cloud account (Route 53 or Azure DNS), the records are made for you.

The server itself needs nothing from you: it installs Docker and OspreyFlow on its first boot.

2.2a Small on your own server

On the server itself (section 5a):

- **Linux on `amd64`** (the releases are built for `linux/amd64` only), with at least **32 GB of memory** (30 GiB as Docker reports it) and **60 GB free where Docker keeps its data** — put Docker's data root on the server's data disk;
- **Docker Engine with the Compose v2 plugin**, enabled at boot (`sudo systemctl enable --now docker`);
- **Git**, **uv** and **Python 3.12** (Ubuntu 24.04's own; or `uv python install 3.12`);
- the **clock synchronised** (`timedatectl`), since sign-in checks tokens against it;
- **port 443 free** on every interface;
- a **service account** in the `docker` group to install and run it as (not root);
- from the organisation: the **three names** in its DNS, pointing at the server, and a **certificate** naming them, with its unencrypted key (section 5a);
- **outbound access** to the releases and their images, or the organisation's mirror of them;
- a **folder for backups** (`server.backups`), with room for several sets, ideally on a disk of its own;
- for sign-in through the organisation's identity provider (section 5a): OspreyFlow's application **registered with it** (the install prints the two addresses), a **group of the people** who may sign in assigned to it, and **outbound access from the server to the provider** — for Entra ID, `login.microsoftonline.com` on 443 (or through the organisation's proxy);
- for the local engine on the server's **NVIDIA GPU** (optional, `server.gpu: nvidia`, section 5a.4): the **NVIDIA driver** for the GPU, and the **NVIDIA Container Toolkit** with Docker configured to use it, both installed by the server's administrator — OspreyFlow checks them and installs neither;
- recommended: `vm.max_map_count` at least 262144 (for OpenSearch).

2.3 Enterprise

On your own computer:

- what Small needs (an account, OpenTofu, the cloud's command line signed in, Git, uv, a DNS name);
- **kubectl** and **Helm**;
- on Azure, **kubelogin** (`az aks install-cli` installs it): the cluster takes Entra ID sign-ins only;
- the **addresses you work from** (`api_cidrs`): the cluster's API, and on Azure the Key Vault, answer those and nothing else, so this computer must be inside one of them.

Onto a cluster you already have, only kubectl, Helm, Git and uv are needed, with kubectl pointed at it.

2.4 Checking a machine: `ospreyflow doctor`

`ospreyflow doctor --mode lite` checks, in the order to fix them: Docker installed, Docker running, Compose v2, memory, free disk, Git, uv and port 80, and the GPU when `osprey.yaml` sets `resources.gpu: nvidia` (section 5a.4). `ospreyflow doctor --mode small --cloud aws` (or `azure`) checks Git, uv, OpenTofu and the cloud's command line. `ospreyflow doctor --mode small --config install.yaml`, with a `server:` section in the answers, checks the server you are on instead (section 5a): Docker, memory, disk, 443, the certificate, the clock and the rest, and the GPU with `server.gpu: nvidia` (section 5a.4); a warning (⚠) says what to change but does not stop an install. `ospreyflow doctor --mode enterprise --cloud aws` adds kubectl and Helm (and on Azure kubelogin); without `--cloud` it checks kubectl, Helm and that a cluster answers. Each line is a tick, or a cross with what to do about it; the exit code is 1 when anything is missing. `install` runs the same checks first and stops, having changed nothing, if one fails.

3. Getting the `ospreyflow` command

The command is installed once per computer by the bootstrap in the repository:

- **macOS and Linux**: `sh install.sh` from inside a checkout, or `OSPREYFLOW_REPO=<repository address> sh install.sh` to clone it into `~/ospreyflow`.
- **Windows**: `install.ps1` in PowerShell, the same way (`$HOME\ospreyflow`).

It installs **uv** if it is missing (from Astral's own installer), makes the checkout's Python environment, installs the command as a uv tool, and records where the checkout is (`~/.config/ospreyflow/home`, or `%APPDATA%\ospreyflow\home`). It starts nothing. If the command is not found afterwards, open a new terminal, or run `uv tool update-shell`.

The command finds its checkout by `OSPREYFLOW_HOME` first, then the recorded file, then by looking upwards from the folder you are in. Anything it prints that names a password, secret or token is hidden and replaced by a pointer to `deployment.env`.

4. Installing Lite

```
ospreyflow install --mode lite
```

asks a few questions — dashboards on or off, the folder the Ingest Studio lists, the folder for a basemap, which demo packs — then (`--starter <theme>-<domain>` fills these in first: section 1a):

1. writes `osprey.yaml` from the answers (refusing, with nothing changed, if a different `osprey.yaml` is already there, unless `--force`);
2. on a release (the checkout sits on a `vX.Y.Z` tag): checks the release's signatures and runs exactly its images, pinned by digest; otherwise builds the images from the checkout;
3. starts the deployment and waits until every service is healthy and the extraction model has downloaded (it says which, and its size: `qwen2.5:7b-instruct`, about 4.7 GB, or the 14b on a GPU, about 9 GB), so Ask works as soon as the install says it is done;
4. makes the demo accounts (unless `--no-demo-accounts`) and loads the chosen demo packs.

It ends by saying the address and that the sign-in details are in `deployment.env`.

Without questions: `ospreyflow install --mode lite --yes` takes every default; `--config install.yaml` takes the answers from a file (section 7). **Building anyway**: `--build` builds from the checkout even on a release tag.

4.1 The guided page: `ospreyflow install --gui`

Opens a page in your browser, on this computer only, behind a one-time link (anyone else, or any other link, is refused). It walks through the same answers as screens, with a starter (section 1a) offered on the first, Mode:

- **Lite**: Mode, Folders, Profile, Components, Map (register a local basemap, build it, verify it), Models, Governance, Demo packs, Review (which runs the doctor), then Install, with the install's own output shown live.
- **Small and Enterprise**: Mode, Cloud and region, Domain, Components, Models, Governance, Demo packs, Review — which **saves** the answers: a Small server is built from a terminal (section 5), never from the page.

Everything is worked on a draft copy of `osprey.yaml`; the page closes itself when the install finishes, or after 30 idle minutes. On a release, the page is the release's own — fetched the first time, with its signature checked against the release; in a developer's checkout it is built with `cd apps/harness && npm ci && npm run build`, and the command says so if it is missing or out of date.

5. Installing Small

From your own computer:

```
ospreyflow install --mode small --cloud aws --config install.yaml
```

with at least:

```
mode: small
cloud:
  provider: aws            # or azure
  region: eu-west-2        # or uksouth, …
  domain: osprey.example.org
  dns_zone: example.org    # optional: make the DNS records in this Route 53 / Azure DNS zone
  admin_email: ops@example.org   # optional
  size: small              # small (32 GB server), medium (64 GB) or large (128 GB)
```

What happens:

1. **Plan.** OpenTofu shows everything it would make in your account (below). Nothing is made yet.
2. **Build, on your yes.** Answer `yes` (or pass `--yes`) and OpenTofu builds it. Its state is kept in `.cloud/small-<cloud>/` in your checkout, readable only by you. **Keep it, privately**: it is how the server is changed later, and on Azure it holds the database password.

3. **DNS.** With a `dns_zone`, the three records (`osprey.example.org`, `id.…` and `bi.…`) are made for you. Without one, the command prints the address to point them at and waits — up to an hour — until the name resolves to the server.
4. **The server installs itself.** On first boot it installs Docker and OspreyFlow, reads the database password (and on Azure the storage key) with **its own cloud identity**, installs onto the managed services, and gets its HTTPS certificate. The command waits — up to 45 minutes — until `https://<domain>` answers. The server's own log is `/var/log/ospreyflow-first-boot.log`.
5. **The first administrator.** The server makes an account `admin` holding the Admin and Analyst roles and the highest clearance, with a **one-time code** instead of a password, and leaves the code in the cloud's secret store. The command reads it, **shows it once**, and deletes it from the store. At their first sign-in the administrator chooses their own password. Then they invite everyone else from the Admin area (section 9).

5.1 What is made in your account

	AWS	Azure
Server	One EC2 instance (r6i), encrypted disk, no SSH; reach it with Session Manager	One VM (E-series), no SSH port; Azure's service healing
Database	RDS for PostgreSQL 16, private, encrypted, its password kept by Secrets Manager	Azure Database for PostgreSQL, private, its password in Key Vault
Objects	S3: media, staging, site images, tile cache (private, encrypted)	Blob for media; the other stores on the server (SeaweedFS), covered by the server's backup
Secrets	Secrets Manager	Key Vault (purge protection on)
Recovery	EC2 automatic recovery; AWS Backup daily	Azure Backup daily
Open to the internet	80 and 443 only	80 and 443 only

Backups are kept 14 days by default (`backup_days`, 7–35).

5.2 On the server, by hand

The server's first boot runs, in effect, `ospreyflow install --mode small --config /etc/ospreyflow/install.yaml --yes --force --first-admin-code-file <file>` with the passwords in its environment. Run without `--first-admin-code-file`, it prints the first administrator's code once instead. `install --mode small` with none of `--cloud`, the managed services in its answers, or a `server:` section (section 5a) is refused, naming all three.

5a. Installing Small on your own server

For an organisation that gives you one Linux server inside its own network, with its own certificate: every store runs in a container on that server (no managed services), people reach it over HTTPS on port 443 with the organisation's certificate, and nothing else is published. Nothing is built in a cloud account. The decision is ADR-114 Amendment 33.

On the server, as the service account that will run it (not root; it must be in the `docker` group, which is root-equivalent, so it is an administrator's account):

```
git clone https://github.com/aykr/OspreyFlow.git /opt/ospreyflow
cd /opt/ospreyflow && sh install.sh
ospreyflow doctor --mode small --config install.yaml
ospreyflow install --mode small --config install.yaml --force
```

(`--force`, because the answers make an `osprey.yaml` that differs from the checkout's own.) The server needs outbound access to the releases and their images (or the organisation's mirror of them) for the install; installing with no outbound access at all is not built. `install.yaml`:

```
mode: small
server:
  address: https://osprey.example.internal       # https:// only; the names below derive from it
  certificate: /etc/ospreyflow/tls/osprey.crt     # PEM: the server certificate, then its intermediates
  key: /etc/ospreyflow/tls/osprey.key             # PEM, unencrypted; owned by the service account, mode 600
  ca: /etc/ospreyflow/tls/org-root.pem            # optional: the organisation's root
  ingest: /srv/ospreyflow/ingest                  # where the CSV exports are put
  redirect_http: false                            # true also publishes 80, only to send people to 443
  # listen_address: 192.0.2.10                    # optional: one interface of a server with several
  backups: /srv/ospreyflow/backups                # where `ospreyflow backup` writes
  memory_gib: auto                                # or a number of GiB: what the stores are sized to
  # gpu: nvidia                                   # optional: the local engine on the server's GPU (5a.4)
sign_in:                                          # optional: the organisation's identity provider
  organisation:
    alias: org                                    # part of the address the organisation registers
    label: Example Department account             # its name on the sign-in pages
    issuer: https://login.microsoftonline.com/<tenant-id>/v2.0
    client_id: 00000000-0000-0000-0000-000000000000
    # its client secret is never written here: OSPREY_ORG_SIGN_IN_SECRET in the terminal
admin_email: ops@example.internal                 # optional: the first administrator's email
components: {dashboards: false}
```

The certificate and key are required. An answers file whose `server:` lacks `server.certificate` or `server.key` is refused, in words naming both, before anything is installed. A server of your own always serves the organisation's own certificate: there is no certificate the front proxy obtains for itself, which would need port 80 and a name the public internet can reach.

The three names and the certificate. The deployment answers at `<host>`, `id.<host>` (sign-in) and `bi.<host>` (dashboards, when they are on), all on the one address. Ask the organisation's DNS to point each at the server, and its CA for a certificate naming them as subject alternative names — `osprey.example.internal`, `id.osprey.example.internal` and `bi.osprey.example.internal`, or `osprey.example.internal` and `*.osprey.example.internal`. **A wildcard covers one label only:** `*.example.internal` covers `osprey.example.internal` but not `id.osprey.example.internal`, so it is not enough. The certificate's common name is not read, as browsers do not read it.

What is checked before anything starts. `doctor`, `install` and every `apply` check the certificate and key and refuse, in words and with nothing changed: a file that cannot be read or is not PEM; a key encrypted with a passphrase; a key that does not match the certificate; a certificate that has expired or is not yet valid; a name of the deployment's it does not cover; and, with `ca`, a chain that does not reach that root (put the intermediates after the server certificate). Fewer than 30 days left is a warning. `doctor --mode small --config install.yaml` also checks: Docker installed, running and started at boot; Compose v2; an `amd64` server (the releases are built for `linux/amd64` only); 30 GiB of memory as Docker reports it (a 32 GB server); 60 GB free where Docker keeps its data; Git, uv and Python 3.12; the clock synchronised (sign-in tokens are checked against it); port 443 free on **every** interface (and 80 with `redirect_http`); port 2480 free; 20 GB free where backups are written (`server.backups`); with `sign_in`, that `OSPREY_ORG_SIGN_IN_SECRET` is set (it also prints the two addresses the organisation registers); and warns for `vm.max_map_count` below 262144, running as root, names that do not yet resolve from the server, and an identity provider whose name does not resolve from it. With `server.gpu: nvidia` it also checks the GPU (section 5a.4).

What it publishes. Port 443 (the address's own port), on every interface or on `listen_address`; port 80 only with `redirect_http: true`, and then it only redirects; the graph store's door, 2480, on the server itself (`127.0.0.1`), as is the Conduit's with `network.expose_conduit`. The front proxy serves the organisation's certificate, read-only from where it is — the key is never copied into the deployment's folder — and obtains no certificate, follows no redirect of its own and fetches nothing from the CA. It runs as the account that owns the key, so the key stays `600`.

Who may reach it is set in front of the server: the organisation's firewall or security group, or the `DOCKER-USER` chain. A port Docker publishes is **not** filtered by `ufw`'s rules. In the `DOCKER-USER` chain, match only connections that **arrive** at 443, with `--ctdir ORIGINAL`; without it the rule also drops the replies to the server's own outbound HTTPS (to the releases, the images and cosign's transparency log), and the install fails with a time-out. For example, to let one network reach the service through the interface `eth0`:

```
iptables -I DOCKER-USER -i eth0 -p tcp -m conntrack --ctdir ORIGINAL --ctorigdstport 443 \
  ! -s 192.0.2.0/24 -j DROP
```

The chain is emptied when Docker restarts, so put the rule in a unit that runs after `docker.service`.

The first administrator. The install makes an account `admin` with the Admin and Analyst roles and the highest clearance, and prints its **one-time code once**, on the terminal; there are no demo accounts. At their first sign-in they choose their own password, then invite everyone else from the Admin area (section 9). The answers' `demo_packs` are loaded after the administrator is made, each into its own case with `admin` as its Author (section 1a says what that means for opening it).

The extraction model. Once every service is healthy, the install waits for the deployment's extraction model (`models.extraction`; on a GPU, the 14b) to finish downloading and pass its digest check, and says so on screen, with its size: about 4.7 GB for `qwen2.5:7b-instruct`, about 9 GB for `qwen2.5:14b-instruct` (one to two minutes on the first server). Only then does it go on and say it is installed, so Ask works from the start. A download that is refused stops the install at stage `models`, naming `ospreyflow logs ollama-models`; run the install again once it can be fetched. `ospreyflow update`, `start --build` and `apply` fetch a model whose choice has changed before anything that uses it starts again (section 5a.4).

The installing account's umask. A server hardened to `umask 077` or `027` is fine: every file the deployment's containers read from its folder is written readable by every account whatever the umask, and `deployment.env`, which holds the secrets, stays readable by its owner alone. The organisation's root, `ca`, is mounted into the identity provider, which runs as another account: `doctor`, `install` and `apply` refuse one that not every account can read (`chmod 644` it; it holds no secret). The key stays `600`. The install's own tools reach the three names on the server itself and trust the deployment's certificate (and `ca`), so they work before the organisation's DNS does.

The upload folder. Files an analyst uploads in the Ingest Studio, and the demo packs' own files, are written to `uploaded/` inside `server.ingest` by the Conduit, which runs as uid 10001. Before anything starts, `install`, `apply`, `start` and `update` make that folder and, when uid 10001 cannot write it, give it to `10001:10001` with a short-lived container of the Conduit's own image, so the service account needs no root for it. It is never made writable by every account, and an arrangement of your own that already lets uid 10001 write (its group, and mode `2775`, say) is left as it is. If it cannot be given over, the command says why and starts nothing (section 16). Lite on a Linux computer does the same.

Renewing the certificate. Replace the two files (same paths), then run `ospreyflow apply`. It checks the new certificate, and only the front proxy is started again.

5a.1 Sign-in through the organisation's identity provider

With `sign_in.organisation` in the answers, people sign in with their organisation's own account — Microsoft Entra ID, ADFS, or any OpenID Connect provider — through OspreyFlow's identity provider (Keycloak), which brokers it. The welcome page then offers **Continue with** and the provider's name from `sign_in.organisation.label` — for example **Continue with Example Department account** — first, which goes straight to the organisation's sign-in page, and **Sign in with an OspreyFlow account** beside it, for the accounts an administrator makes (the first administrator's among them). A deployment that names a provider with no label shows **Continue with organisation sign-in**. Without `sign_in`, there is the one **Sign in**, for those accounts alone.

What the organisation does first — for Entra ID, in its admin centre's *App registrations*:

1. Register an application for OspreyFlow, a *web* application, and give it the **redirect URI** the install prints (and `ospreyflow doctor --mode small --config install.yaml` prints before it): `https://id.<host>/realms/osprey/broker/<alias>/endpoint` — exactly, with no slash added. Set its **front-channel logout / post-logout redirect URI** to the same address followed by `/logout_response`.
2. Make a **client secret** for it, and hand it over by the organisation's own secure route. It is never written in the answers file or `osprey.yaml`: set it in the terminal for the install, `export OSPREY_ORG_SIGN_IN_SECRET=…`; it is kept only in the deployment's `deployment.env` (mode 600), and the install refuses to start without it.
3. Turn on **assignment required** and assign the application to the **group of people** who may sign in: the organisation decides who may sign in at all.
4. Give the install the **issuer** (Entra ID: `https://login.microsoftonline.com/<tenant-id>/v2.0`) and the application's **client id**.
5. Allow the **server to reach the provider** on 443 — Entra ID is on the internet, at `login.microsoftonline.com` — directly or through the organisation's proxy. Nothing else on the server reaches out for sign-in, and only the identity provider does.

Roles are OspreyFlow's. Someone signing in through the organisation for the first time arrives with **no role, no handling code, and a clearance and unit of `unassigned`** that see nothing: Home shows every place dimmed until an administrator grants them. Nothing is taken from the organisation's directory — no group becomes a role. An administrator finds them in Admin → People and roles once they have signed in, and sets their roles, then their access (clearance, unit, handling codes); a later sign-in never takes those back. **No role, no list:** until they hold a role they are told no dataset's name, even if their unit is set first — the unit's dataset list and a case's datasets come back empty (section 9.2).

Someone whose email an OspreyFlow account already holds. A person arriving through the organisation for the first time is matched by nothing but their email, and an email the organisation's provider sends is not proof that the person owns the OspreyFlow account with that address (Entra ID does not promise it is verified). So OspreyFlow **never joins the two**: when an account already holds that email — someone you invited by that address, say — the sign-in page says "This email address already belongs to an OspreyFlow account, so your organisation account has not been joined to it. Sign in to that account with its username and password instead, or ask your OspreyFlow administrator." Nothing is made. Then, in Admin → People and roles (section 9.7):

- **Join them to that account**, if you are sure it is theirs: *Refused organisation sign-ins* lists each person refused in the last seven days by their name at the organisation; choose the account and confirm. Their next sign-in through the organisation lands in it, with its roles, clearance and cases. An invited account whose password was never set loses its one-time code: it is reached through the organisation from then on.
- **Or remove that account**, and ask them to sign in again: they arrive as someone new, with no role, and you grant their roles again.
- **Or leave it**: they go on with that account (**Sign in with an OspreyFlow account**).

To avoid it, invite only the people who cannot come through the organisation (the first administrator, outside staff).

Joining by email, for an organisation that verifies every address. With `sign_in.organisation.trust_email: true` in the answers (`governance.organisation_provider.trust_email` in `osprey.yaml`; off by default), a person arriving through the organisation is **joined automatically** to the OspreyFlow account holding the same email address, with its roles and clearance, instead of being refused. **This hands any account to whoever the organisation's provider gives its address**: where a person can set their own address, or another tenant can claim one, it is an account takeover — the 2023 "nOAuth" takeovers of Entra ID applications were exactly this. Turn it on only with the organisation's security officer's written sign-off that every address its provider gives is verified and cannot be changed by the person who holds it. `ospreyflow doctor` and the install warn of it every time, and so does each `repair-sign-in`. Only the provider's own address is compared: a person is never asked to type one at first sign-in. An invited account whose password was never set is joined, then asks for a password once. To turn it off, set `trust_email: false` in `osprey.yaml` and run `ospreyflow apply` (it updates the identity provider too): people whose email an account holds are refused again, and you join them by hand.

The organisation's own certificate authority. With `server.ca`, the identity provider trusts it as well as the usual public authorities, so a provider on the organisation's own certificates (ADFS, an internal Keycloak) is trusted too.

After a wipe or a restore, `ospreyflow repair-sign-in` registers the organisation's provider again, with its client secret from `deployment.env` — safe to run again, and it prints no secret. To change the secret, put the new one in `deployment.env` (`OSPREY_ORG_SIGN_IN_SECRET=`), then run `ospreyflow repair-sign-in`. A Small deployment is never given demo accounts by `repair-sign-in` or `start --build`.

5a.2 Memory

`server.memory_gib: auto` reads how much memory Docker has, once, at install, and writes it to `osprey.yaml` as `resources.memory_gib`; the stores are sized to it (appendix A's `resources`):

Memory	Graph store's heap	OpenSearch's heap	PostgreSQL's shared buffers
32 GB	12 GiB	2 GiB	1 GiB
64 GB	25 GiB	4 GiB	2 GiB
128 GB	31 GiB	8 GiB	4 GiB

The three take at most half the server, leaving the rest to the model server, the identity provider, the Conduit and the operating system. To resize, change `resources.memory_gib` (or one of its overrides, `graph_heap_gib`, `search_heap_gib`, `postgres_shared_buffers_gib`) and run `ospreyflow apply`: only the three stores are started again. An override that would give the three more than three quarters of the server is refused.

5a.3 Backups

`ospreyflow backup` writes each set to `server.backups` (default `~/OspreyFlow/backups`), readable by its owner only. A set never holds the certificate's key or `deployment.env`; it does hold the case data and the people's identities. Nothing is registered with the operating system, so schedule it with the service account's own crontab (`crontab -e`), beside the organisation's snapshots of the server's disks:

```
0 2 * * * cd /opt/ospreyflow && ~/.local/bin/ospreyflow backup >> ~/ospreyflow-backup.log 2>&1
```

Old sets are not removed: remove them by hand, or with the organisation's own retention. Restoring and updating are as for Lite (sections 13 and 14).

The guided page (`--gui`) does not install this kind of Small.

5a.4 The local engine on an NVIDIA GPU

Without a GPU the local engine (Ollama) runs on the server's processors, so a question to Ask the case on the local engine is slow, and material that may not leave the deployment can only ever run there. A server with an NVIDIA GPU can give the local engine the GPU. The decision is ADR-135 Amendment 1.

Before the install, the server's administrator installs, and OspreyFlow checks but never installs:

- the **NVIDIA driver** for the GPU (on Ubuntu, `sudo ubuntu-drivers install`, then restart the server), until `nvidia-smi` lists the GPU;
- the **NVIDIA Container Toolkit**, with Docker configured to use it:

```
sudo nvidia-ctk runtime configure --runtime=docker
sudo systemctl restart docker
```

Then add `gpu: nvidia` under `server:` in `install.yaml`; it is written to `osprey.yaml` as `resources.gpu: nvidia`. Lite on a Linux computer with an NVIDIA GPU may set `resources.gpu: nvidia` in `osprey.yaml` itself and run `ospreyflow apply`. It is refused for Small in a cloud and for Enterprise, whose servers are sized without a GPU, and on macOS and Windows, where Docker Desktop gives a container no NVIDIA GPU.

What changes. The model server alone reserves every NVIDIA GPU on the server; its image, the models' pinned weights and the gateway are the same. Image descriptions and embeddings run in the same model server, so they use the GPU too; transcription stays on the processors. The extraction model, which also answers Ask the case and Ask to search on the local engine, becomes `qwen2.5:14b-instruct` (about 9 GB, downloaded once) instead of `qwen2.5:7b-instruct`, unless `osprey.yaml` names one under `models.extraction`, which always wins. `ospreyflow apply` fetches a newly chosen model, and waits for it, before the services that use it start again. An `osprey.yaml` saved by the guided page (`--gui`) names every model, `models.extraction: qwen2.5:7b-instruct` among them, so it keeps the 7b on the GPU until that line is removed. On the GPU the model server also keeps its working memory for a question at reduced precision (`OLLAMA_FLASH_ATTENTION=1` and `OLLAMA_KV_CACHE_TYPE=q8_0`), which is what fits the 14b, with the long context it is given, wholly on a 16 GB card. On the GPU the model also stays loaded (`OLLAMA_KEEP_ALIVE=-1`): left to Ollama's default, an idle model was unloaded after five minutes and the next question waited 56 s for it to load again, against 3.3 s once loaded. Without a GPU nothing changes.

As measured, 4 November 2026, on the first server (an RTX 5060 Ti, 16 GB), the same question through the product's own route: the 14b on the GPU without those two settings used 18 GB, ran 15% on the processors and 85% on the GPU, and took 9–11 s an answer of about 120 tokens; with them it used 14 GB, ran wholly on the GPU (12.0 GiB, per `nvidia-smi`), and took 3.3–3.6 s. The 7b on the processors took 17.3 s.

What is checked before anything starts. `doctor`, `install` and `apply` refuse, in words and with nothing changed: a computer that is not Linux; `nvidia-smi` not installed, or not answering ("NVIDIA-SMI has failed because it couldn't communicate with the NVIDIA driver": install the driver, or restart after installing it); and Docker listing neither the toolkit's `nvidia` runtime nor an NVIDIA CDI device (`docker info`). With the 14b model, less than 14 GiB of GPU memory is a warning naming the 7b: set `models.extraction: qwen2.5:7b-instruct` in `osprey.yaml` and run `ospreyflow apply`. The doctor names the GPU, its memory and its driver, for example:

```
✔ The NVIDIA GPU is NVIDIA GeForce RTX 5060 Ti, 15.9 GiB (driver 595.99.02).
✔ Docker can run a container on the GPU (the nvidia runtime of the NVIDIA Container Toolkit).
✔ The GPU has 15.9 GiB of memory; qwen2.5:14b-instruct asks for at least 14 GiB.
```

To turn it off, set `resources.gpu: none` in `osprey.yaml` and run `ospreyflow apply`.

6. Installing Enterprise

From your own computer:

```
ospreyflow install --mode enterprise --cloud aws --config install.yaml
```

with at least:

```
mode: enterprise
cloud:
  provider: aws            # or azure
  region: eu-west-2        # or uksouth, …
  domain: osprey.example.org
  api_cidrs: [203.0.113.0/24]    # the addresses you work from; never 0.0.0.0/0
  admin_email: ops@example.org   # optional
  size: small              # small (3 nodes of 32 GB), medium (4 of 64 GB) or large (6 of 128 GB)
cluster:
  namespace: ospreyflow    # optional
```

What happens:

1. **Plan, then build on your yes**, as for Small (section 5): OpenTofu shows the cluster and the services it would make, and makes them when you answer `yes` (or pass `--yes`). Its state is kept in `.cloud/enterprise-<cloud>/`, readable only by you. **Keep it, privately**: it is how the cluster is changed later, and it holds secrets.
2. **What OpenTofu made becomes the answers.** It names the cluster's two storage classes and every managed service; these join your answers in `osprey.yaml`. Do not give `external:` or the storage classes yourself: with `--cloud` they are refused, since OpenTofu makes them.
3. **A kubeconfig of the install's own**, in the state folder; your `~/.kube/config` is not changed. Use it yourself with `KUBECONFIG=.cloud/enterprise-<cloud>/kubeconfig kubectl get pods -n ospreyflow`.
4. **The passwords and keys** of the managed services are read from the cloud's secret store with your own identity and handed to the install in its environment only — never on a command line, in `osprey.yaml` or on the screen.
5. **The install** puts the chart onto the cluster, makes its Secret (keeping every value already there when run again), configures sign-in, makes the first administrator, prints their one-time code once, and says the address to point `osprey.example.org`, `id.…` and `bi.…` at.

Run again, it changes nothing OpenTofu need not change, no password and no account.

Onto a cluster you already have: leave out `--cloud`, point kubectl at the cluster, and give the managed services yourself under `external:` and the cluster's classes under `cluster:` (section 7), with their passwords in the environment: `OSPREY_POSTGRES_PASSWORD`, `VALKEY_PASSWORD`, and for media on Blob `AZURE_STORAGE_KEY`. A site's own Helm values go in with `--chart-values <file>` (repeatable), applied over the rendered ones.

6.1 What is made in your account

	AWS	Azure
Cluster	EKS, its Kubernetes secrets encrypted with their own key; nodes in three private subnets	AKS, no local accounts (Entra ID only); a system pool and the deployment's own pool, three zones
Its API	Answers `api_cidrs` only	Answers `api_cidrs` only
Network policy	The VPC CNI's engine, so the chart's policies are enforced	Azure network policy
Database	RDS for PostgreSQL 16, two zones, password in Secrets Manager, deletion protection	PostgreSQL flexible server 16, zone-redundant, a delete lock, password in Key Vault
Cache	ElastiCache for Valkey, TLS and a token	Azure Cache for Redis, TLS only
Objects	S3 (as Small)	Blob for media; the other stores in the cluster
Search	Amazon OpenSearch Service (the install always asks for it; the module's own `search = false` leaves it to the cluster)	In the cluster
Shared volume	EFS (`ospreyflow-shared`)	Azure Files (`ospreyflow-shared`)
Store volumes	Encrypted gp3 (`ospreyflow-volumes`)	Zone-redundant premium disks (`ospreyflow-volumes`)

Every managed store is reached only from inside the cluster's network. Neither module has yet been built in a real account; the chart and the install have been proved in a local cluster.

7. The answers file, `install.yaml`

Every question `install` asks can be answered in this file; unknown settings are refused by name.

Setting	Meaning
`mode`	`lite`, `small` or `enterprise`
`components.dashboards`	Superset and report sync on (`true`, the default) or off
`folders.ingest`	The folder the Ingest Studio lists (absolute, or from `~`); default `~/OspreyFlow/ingest`
`folders.tiles`	Where a built basemap lives; default `~/OspreyFlow/basemap`
`models.local_only`	`true` (default): no case content leaves the deployment
`demo_packs`	A list of pack ids (section 11)
`paysim_file`	The downloaded PaySim file, when `paysim` is chosen
`mail.host`, `mail.port`, `mail.from`, `mail.starttls`, `mail.username`	A mail server for invitations (section 9.3); its password is never here
`cloud.provider`, `cloud.region`, `cloud.domain`, `cloud.size`, `cloud.dns_zone`, `cloud.admin_email`	Small (section 5) and Enterprise (section 6)
`cloud.api_cidrs`	Enterprise with `--cloud`: the addresses the cluster's API answers (section 6)
`cluster.namespace`, `cluster.storage_class`, `cluster.shared_storage_class`	Enterprise: the namespace, and onto a cluster you already have its storage classes (section 6)
`server`: `server.address`, `server.certificate`, `server.key`, `server.ca`, `server.ingest`, `server.redirect_http`, `server.listen_address`, `server.backups`, `server.memory_gib`, `server.gpu`	Small on your own server (section 5a); refused with `cloud` or `external`, and for Lite and Enterprise. `server.certificate` and `server.key` are required. `server.backups` is where backups are written (default `~/OspreyFlow/backups`); `server.memory_gib` is `auto` or a number of GiB, at least 16 (section 5a.2); `server.gpu` is `none` (the default) or `nvidia`, the local engine on the server's NVIDIA GPU (section 5a.4)
`admin_email`	Small on your own server: the first administrator's email
`sign_in.organisation`: `alias`, `label`, `issuer`, `client_id`, `trust_email`	Small on your own server: sign-in through the organisation's identity provider (section 5a.1). `alias` defaults to `org`; `issuer` is `https://`. Its client secret is never here — `OSPREY_ORG_SIGN_IN_SECRET` in the terminal — and a setting naming a secret is refused. `trust_email` is `false` (the default) or `true`, joining by email — only with the security officer's sign-off (section 5a.1)
`external`	The managed services the deployment runs on — written by OpenTofu, or by you for a cluster you already have
`config`	Use this `osprey.yaml` exactly as it is, instead of `components`, `folders` and `models`
`starter`	A starter, `<theme>-<domain>` (section 1a): fills in the answers below that are not given
`appearance.brand`, `appearance.service_name`, `appearance.organisation`, `appearance.phase`	The look (appendix A's `appearance`); `govuk` needs `service_name`, which names the whole service
`demo_accounts`	`true` (default) makes the demo accounts; `false` makes none (the `blank` starter's answer)
`grading.scheme`	`5x5x5` (default), `3x5x2`, or a scheme file (`.yaml`, beside `osprey.yaml`): the scheme drawn items are graded in. Changed later only by `ospreyflow grading change` (§8), which changes the items and this setting together

The answers become `osprey.yaml` (appendix A): `mode` sets `profile`, `components.dashboards` sets both `reporting.sync` and `reporting.superset`, and the address is `http://ospreyflow.localhost` for Lite, `https://<domain>` for Small and Enterprise, and `server.address` for Small on your own server (with `server.certificate`, `key` and `ca` as `network.tls`, `server.backups` as `components.storage.backups`, `server.memory_gib` as `resources.memory_gib`, `server.gpu` as `resources.gpu`, and `sign_in.organisation` as `governance.organisation_sign_in` and `governance.organisation_provider`).

8. Running it

Command	What it does
`ospreyflow start`	Brings the deployment up and waits for every service; `--build` rebuilds from the checkout first
`ospreyflow stop`	Stops every container; nothing is removed
`ospreyflow switch [<name>]`	Makes this the deployment running: stops any other OspreyFlow deployment on the machine (each with its own settings), then starts and opens the named one (`default` for the checkout's; section 1a.1). `--list` names each deployment, running or stopped, and changes nothing. A deployment in another checkout is still picked with `OSPREYFLOW_HOME=<its product folder> ospreyflow switch`
`ospreyflow deployments`	Lists this computer's deployments — the checkout's as `default`, and each kept by name — with the starter each was made from, its address and whether it is running

Command	What it does
`ospreyflow starters`	Lists the starters, and the install command for each (section 1a)
`ospreyflow status`	Each service's state and health; exits 1 unless everything is running and healthy
`ospreyflow open`	Opens the Glass in your browser
`ospreyflow logs [service] [--follow] [--tail N]`	The services' logs (the last 200 lines by default)
`ospreyflow apply`	Applies a changed `osprey.yaml` to the installed deployment (section 8.3): renders it again, keeps every password and key, asks for a newly enabled provider's key (from `OSPREY_MODEL_KEY_<NAME>` or a hidden prompt), and restarts only the services whose settings changed. It makes no account, adds no demo pack and touches no data
`ospreyflow repair-sign-in [--no-demo-accounts]`	Registers the sign-in again — the identity provider's clients, roles and the demo accounts (leave them out with `--no-demo-accounts`; a Small deployment installed without them never gets them), the Conduit's own client secret from the deployment's settings, which a wiped or re-imported identity provider no longer holds, the workspace's own client (which is given no refresh token), and the organisation's identity provider with its client secret, its first sign-in (refusing, or joining by email when `trust_email` is on) and the record of refused sign-ins Admin → People lists (section 5a.1); safe to run again, and prints no secret
`ospreyflow models`	Lists the model engines, each role's default engine, and whether each provider's key is present (yes or no — never the key)
`ospreyflow models key <name>`	Sets or replaces a provider's key, from `OSPREY_MODEL_KEY_<NAME>` in the terminal or a hidden prompt; writes it to `deployment.env` alone and restarts the model gateway (and the Conduit when the key's presence changes)
`ospreyflow models remove-key <name>`	Removes a provider's key; the provider stays enabled but shows "no key" and is not offered to analysts
`ospreyflow grading change --to <scheme> --mapping <file> --dry-run`	Says how many drawn items each line of the mapping (every grade of the old scheme to one of the new) would move, writes nothing, and gives the token the change needs. `--to` is `5x5x5`, `3x5x2` or a scheme file: a YAML file with `scheme` (a name of its own), `source`, `intelligence` and `handling`, each its list of grades. Runs beside a running deployment
`ospreyflow grading change --to <scheme> --mapping <file> --confirm <token> [--stop-api]`	Changes every live drawn item's grade, each keeping the grade it had before beside the new one; refused unless the token is the dry run's for the items as they are now, and while the Conduit runs unless `--stop-api` says to stop it. After the change it sets `grading.scheme` (a scheme file kept beside `osprey.yaml`), applies the settings and starts the Conduit. A refusal names the items it concerns and changes nothing; a run stopped part way leaves the Conduit stopped: run the dry run and the change again
`ospreyflow map list`	Lists the map providers, each with its tier, whether its key is set (never the key) and its state; the local basemap, the place-name fonts and the prefetch areas
`ospreyflow map verify`	Checks every provider's attribution, and a tier-4 service's projection and zooms, in the Conduit
`ospreyflow map prefetch`	Fetches every prefetch area's tiles now, saying for each how many were fetched and any failure in plain words
`ospreyflow map build <region> --unit <unit> [--planetiler-jar <path>]`	Builds the tier-1 basemap in the Conduit (the jar copied into the tiles folder first), and its place names as the gazetteer dataset `gazetteer-osm-<region>`, held by `--unit` (required; an unknown unit, or a re-build for another unit, is refused)
`ospreyflow uninstall [--keep-data] [--yes]`	Removes the containers; with `--keep-data` the data volumes stay, and the next install of the same deployment finds them; without it cases, accounts and indexes go too. Your checkout, `osprey.yaml` and your own folders are never touched. (Before the stores had named volumes, section 13, a reinstall did not find the stores' data)

Every command takes `--name <name>` to act on a deployment kept by name, or `--name default` for the checkout's own (section 1a.1). Every service restarts itself if it stops; nothing is registered with the operating system.

Enterprise is looked after with Kubernetes' own tools, not these verbs (which drive a Compose deployment): `kubectl get pods -n ospreyflow`, `kubectl logs`, and `helm uninstall ospreyflow -n ospreyflow` to remove it (the stores' volume claims are left in place, and the classes OpenTofu makes keep a volume even when its claim is deleted).

8.1 Addresses

One front proxy is the deployment's only door. Under the address in `network.public_origin`:

- the **Glass** — with its four places, the Ingest Studio, Rules and Monitoring and Admin among them — at the name itself;
- **sign-in** (Keycloak) at `id.`;
- **dashboards** (Superset) at `bi.`, when dashboards are on.

Lite publishes port 80 (or its own address's port) and `2480` for the graph store's own tools, both on this computer only (`127.0.0.1`): other machines cannot reach a Lite deployment. Small publishes 80 (for the certificate and the move to HTTPS) and 443 on every network interface, because other people reach it. Small on your own server publishes 443 alone (80 only with `redirect_http`, and then only to redirect), and 2480 and the Conduit's door on the server only (section 5a). Which of them is plain HTTP and which HTTPS: the note **HTTP or HTTPS** in section 1. The Conduit's own port is published only with `network.expose_conduit: true` — on Lite, on this computer only.

8.2 Where things are

Where	What
`osprey.yaml` (the checkout)	The deployment's settings; never a secret
`~/.ospreyflow/deployments/<name>/`	A deployment kept by name (section 1a.1): its own `osprey.yaml`, every file rendered from it, its `deployment.env` (`600`) and its `backups/`; `~/.ospreyflow/current` names the one last used

Where	What
`deploy/generated/<profile>/`	The deployment: `compose.yaml`, `deployment.env` (every password and key it made), `Caddyfile`, `glass.json`, `realm.json`, `litellm.yaml`, `versions.lock`, `RUNBOOK.md`, `state/`
`backups/`	Backup sets
`.install/`	The guided page's draft and answers; a release install's verified lock
`.cloud/`	OpenTofu's state for a Small server or an Enterprise cluster, and the cluster's kubeconfig — keep it private
Your ingest and basemap folders	As the answers named them

`RUNBOOK.md`, written for each deployment, lists what runs, its paths and its addresses.

`deployment.env` is readable by your own account alone (`600`): `ospreyflow install` writes it so, and `ospreyflow apply`, `models key` and `models remove-key` keep it so.

8.3 Changing a setting

Edit `osprey.yaml` in the checkout, then run:

```
ospreyflow apply
```

It checks the file first, and if anything in it is wrong it says what, and changes nothing. Then it renders the deployment again from it, keeping every password and key the deployment already has, and starts again only the services whose settings changed; the rest keep running. A provider newly enabled under `models.providers` needs its key: give it as `OSPREY_MODEL_KEY_<NAME>` in the same terminal, or type it at the hidden prompt `apply` shows. `apply` makes no account, adds no demo pack, rebuilds nothing and never touches the stored data. Do not run `ospreyflow install` again over a running deployment to change a setting; `ospreyflow start --build` rebuilds the code but reads the settings the deployment already has.

A changed `deployment.name` names a different deployment, which `apply` refuses: install it as a new one.

9. People and accounts

Everyone signs in through the deployment's identity provider; the password is only ever typed on its own sign-in page. What a person may do is their **roles**; what they may see is their **clearance**, unit and handling codes, and the cases they are given.

9.1 The Admin place

Admin is one of the four places (key `A`); Home and the place switcher offer it to whoever holds one of its sections' rights. A side list groups its sections, each shown only to someone holding its right, and each section's routes refuse anyone without it, so hiding a section is never the control. Under the GOV.UK theme the list is a GOV.UK side navigation.

Group	Section	Right	What it does
People	**People and roles**	`manage_people`	Invite people; set their roles, clearance, unit and handling codes; the Super user preset; **Disable…** with its transfers (section 9.9), re-enable; reset a sign-in; remove an account; join someone the organisation's sign-in refused to their account (section 9.7); name an Author for a case that has none
People	**Roles**	`manage_people`	The built-in roles and their rights; custom roles; teams, their leads and cover (sections 9.2 and 9.8)
People	**Dashboard identities**	`manage_dashboards`	Register a dashboard's account (its secret shown once), see when it last pulled, remove it
Data	**Datasets**	`administer_system`	Every dataset's kind, unit, highest marking, egress, promotion policy, Authors and linked cases (section 9.10)
Data	**Connections**	`administer_system`	The named connections pipelines read through: files, a SQL database, an HTTP API or JSON files
Running	**Operations**	`operate_schedules`	Every scheduled or watched pipeline (pause, resume, run now, change its time, its runs), and promotions waiting for review (section 9.11)
Running	**System**	`administer_system`	Each component's health, the models in use, the version and whether an update exists, and who dataset owners may be
Running	**Models**	`manage_models`	Model engines, each job's model, their keys, limits and usage (section 10.1)
Running	**Maps**	`manage_geospatial`	Map providers and their keys, the local basemap, prefetch areas (section 10a)
Policies	**Grading scheme**	`administer_system`	The deployment's grading scheme, read-only, with **Copy the grading change command** (section 8)
Policies	**Approval rights** (coming)	`administer_system`	Who may approve each kind of decision, and a warning where fewer than two can
Policies	**Uploads** (coming)	`administer_system`	The largest picture an analyst may add, and the formats accepted
Audit	**Audit**	`read_audit`	The audit log, filtered by who, what and when (section 9.11)
Demo packs	**Demo packs**	`administer_system`	Which packs are loaded, and the command that adds one

System → Acting for people says "The Conduit cannot act for people: run `ospreyflow repair-sign-in`" when the identity provider refuses the Conduit's own credential.




Figure 3. Admin → People and roles: each person's roles, with Access, Disable and Reset sign-in

9.2 Roles

The words below are the Glass's own, copied from `help/roles.ts`, the file the help page *Roles, teams and Authors* reads them from; a test (`test_guide_role_words.py`) fails if a copy here says anything different.

Role	What it is for	Places it opens
Analyst	Investigates cases, works alerts and keeps watches. Reads figures and boards.	The Glass, Rules and Monitoring
Data Engineer	Builds and runs pipelines, reviews promotions into a dataset and decides held rows.	The Glass, the Ingest Studio, Admin (Operations)
Administrator (`osprey-admin`)	Looks after people, roles, teams, datasets and the deployment. Does not investigate by being one.	Admin, the Glass
Reports Viewer	Reads a case's figures and the dashboards, and sees the alerts on cases they can read. Never works an alert.	The Glass
Rule author	Writes the rules that raise alerts, and works the alerts in the queue.	The Glass, Rules and Monitoring
Super user (a preset)	Analyst, Data Engineer and Rule author together, given as three roles. Still never the second person on their own work.	All four

Custom roles. Admin → Roles lists the built-in roles with their rights (**Copy ‹role› into a new role**) and the deployment's own under **Custom roles**, each with **Edit**, **Copy**, its versions and who holds it. **New role** asks for a **Role name** and its rights, grouped as Cases, Investigation (the Glass), Alerts and rules, Ingest Studio, Reporting, Administration and Other. **Nobody can give more than the person giving it holds** — clearance included — which is why the first administrator holds the highest clearance. A single right can also be given on its own. Each built-in role, a custom role, a team and its lead have a short tip in Roles, and People folds open **What each role and level lets a person do**. A refusal for a missing right names the roles that have it: "You need ‹Right›; the ‹Role› role has it. Ask an administrator to give it to you." (in Admin, after "Not done."). `write_sql_transforms`, the Ingest Studio's expert steps, is in no built-in role: give it on its own (developer guide, section 3.4b).

Each right, in plain words:

Right	Lets a person
`create_case`	Start a case.
`share_case`	Give people a level in a case.
`remove_case`	Remove a case they are an Author of.
`export`	Export from a case, through the export checks.
`export_override`	Export an item that asks its originator first, with a reason.
`investigate`	Search, expand, follow paths and filter in a case.
`edit_graph`	Add and change entities and links in a case.
`confirm_inferred`	Confirm what a model suggested, so it is no longer inferred.
`extract_files`	Add files to a case, run extraction and decide its findings.
`resolve_entities`	Say two entities are the same, or not.
`record_assessment`	Record judgements, gaps and assumptions.

Right	Lets a person
`ask_model`	Ask the model a question about a case.
`run_analysis`	Run analyses such as communities and centrality.
`propose_link_type`	Propose a new type of link.
`draw_on_boards`	Draw on a case's boards.
`promote_to_dataset`	Propose a drawn item for the dataset.
`propose_types`	Propose a new entity type.
`read_alert_queue`	See the alerts in a case's queue.
`triage_alerts`	Claim, close and hand back alerts.
`deploy_rules`	Turn rules on and off for a case.
`read_rule_audit`	Read who changed which rule, and when.
`read_held_rows`	See rows a load held back for review.
`decide_held_rows`	Release or reject held rows.
`trace_ownership`	Trace ownership and neighbourhood risk.
`keep_watches`	Keep watches and hotlists.
`load_screening_lists`	Load and refresh licensed screening lists.
`author_rules`	Write the rules that raise alerts.
`manage_strength_influencers`	Change what makes a link strong.
`edit_pipelines`	Build and change pipelines.
`verify_pipelines`	Test a pipeline against its sample.
`publish_pipelines`	Deploy a pipeline.
`run_pipelines`	Run a pipeline.
`schedule_pipelines`	Put a pipeline on a schedule.
`add_ingest_files`	Add files for a pipeline to load.
`revert_loads`	Take back a load.
`edit_target_model`	Change a dataset's domain model.
`review_promotions`	Review items proposed for a dataset.
`accept_types`	Accept a proposed type into a domain model.
`merge_datasets`	Merge a drawn dataset into another.
`read_reports`	Read a case's figures and the dashboards.
`read_report_feed`	Download a case's figures for a dashboard.
`read_data_feeds`	See the data feeds a case's pipelines send.
`administer_system`	Change how the deployment runs.
`manage_people`	Add people and give them roles.
`manage_dashboards`	Register dashboards.
`operate_schedules`	Pause and resume schedules.
`manage_ontology`	Change the deployment's ontology.
`manage_geospatial`	Choose the maps the deployment shows.
`read_audit`	Read the audit log.
`read_export_ledger`	Read the record of what left the deployment.
`manage_models`	Choose the models and their keys.

Someone with no role sees no datasets. A person holding no role (or only a role this deployment does not know) is told no dataset's name or id anywhere: the list a new case chooses from and the datasets a case reads come back empty, and a model engine's reason for being unavailable names none, whatever unit or case level they have been given. Home tells them "Your account opens no place yet. Ask an administrator to give you a role.", and *No cases to show* when they hold no case. A single right given on its own counts as a role here. Set their roles first, or straight after their access, and they see what that role allows.

The first administrator (`admin`, on a deployment with no demo accounts) holds both the **Admin** and the **Analyst** roles from the start, whether or not demo packs are loaded. The Admin role alone does not open a case's graph, and the first administrator is the Author of every demo pack's case there. An `admin` made by v0.4.6 or earlier holds Admin alone: add the Analyst role in People and roles.

9.3 Inviting someone

Invite a person asks for a sign-in name, their first and last name, optionally an email, a clearance, a unit, handling codes and, for each role, **Invite as ‹role›**. With a mail server configured and an email given, they get an email with a link to set their password. Otherwise you are shown a **one-time code** (sixteen letters in four groups) to give them in person; it is shown once, and at first sign-in they choose their own password. **Reset sign-in** works the same way.




Figure 4. A person's access opened under their row: clearance, unit and handling codes

A mail server is set in `osprey.yaml`'s `mail:` (appendix A); if it signs in, its password is given once at install as `OSPREY_SMTP_PASSWORD` and kept only in `deployment.env`. With mail, the sign-in page also offers *Reset your password*.

9.4 Monitoring: whom a hotlist's alerts reach

Analysts work alerts in **Rules and Monitoring** (the alerts journey, coming, rewrites this section): the case's rule alerts reach every member of the case; a watched pattern's alerts reach its owner and the people of the owner's **unit** (the unit set on their account, section 9.3); a hotlist's alerts reach its owner, and the owner's unit too only when the hotlist is shared. Two settings in `osprey.yaml` decide hotlists:

```
monitoring:
  hotlist_audience: only_me        # or team: a new hotlist is shared with its owner's unit
  hotlist_audience_editable: true  # false: owners cannot choose, and a change is refused
```

`hotlist_audience` is where a **new** hotlist starts; it never changes an existing one, and every hotlist made before the setting existed reaches only its owner until the owner changes it. With `hotlist_audience_editable: false`, every new hotlist takes `hotlist_audience`, the Glass offers no choice and says so, and a change is refused in words. A match on data its owner cannot see is never shared. Change either with `ospreyflow apply` (section 8.3). Both are in appendix A.

9.5 Screening lists: subscribing, licences and the refresh

OspreyFlow screens customers against sanctions, PEP and adverse-media lists that the deployment **subscribes** to. Each list is read through its **connector**, which knows one publisher's own export format:

Connector	Reads	Licence (as its publisher states it, 1 November 2026)
OFAC SDN list	`SDN.CSV`, with `ALT.CSV` and `ADD.CSV` beside it when present	A US Government work, in the public domain; OFAC's own pages state no licence
HM Treasury OFSI consolidated list	`ConList.csv`	Open Government Licence v3.0. **Reads a closed list**: the OFSI Consolidated List closed on 28 January 2026 and is no longer updated. Use the UK Sanctions List below for UK designations
UK Sanctions List (FCDO)	`UK-Sanctions-List.xml` (the XML format)	Open Government Licence v3.0 (Crown copyright). The only source of UK sanctions designations since 28 January 2026. Its XML schema carries a notice of its own about commercial use; OspreyFlow does not ship it
UN Security Council consolidated list	`consolidated.xml`	**Licence not confirmed.** No open licence found: the UN's terms of use allow personal, non-commercial use. Confirm with the UN before relying on it. Synthetic lists only until then
EU consolidated financial sanctions list	the FSF XML 1.1 file	The European Commission's reuse notice (Decision 2011/833/EU)

Connector	Reads	Licence (as its publisher states it, 1 November 2026)
OpenSanctions	`entities.ftm.json`	**Licence not confirmed.** CC BY-NC 4.0: **non-commercial only**. Screening inside a business is commercial use and needs OpenSanctions' data licence. Synthetic lists only until then

Check the licence for your use before you subscribe. The architecture's licence register (spec 00 §7) records where each statement was read.

A closed list: OFSI. HM Treasury closed the OFSI Consolidated List on 28 January 2026; the FCDO's UK Sanctions List is now the only source of UK designations. OspreyFlow keeps the OFSI connector, so a file you already hold can still be read, but nothing new will ever be published to it: the Lists tab says "Closed list" on such a list's row, and the subscribe form names the connector "reads a closed list" and points to the UK Sanctions List. To screen against UK designations, download `UK-Sanctions-List.xml` from the list's page (gov.uk/government/publications/the-uk-sanctions-list; the FCDO keeps it at a fixed address, `sanctionslist.fcdo.gov.uk/docs/UK-Sanctions-List.xml`), put it in the ingest folder, and subscribe to it through the **UK Sanctions List (FCDO)** connector. OspreyFlow does not fetch it for you. The connector reads the XML only (its schema is published; the CSV's column order is not).

Licence not confirmed: UN and OpenSanctions. Until their licences for a customer's screening are confirmed, these two connectors read OspreyFlow's own synthetic lists only. The Lists tab marks each such list "Licence not confirmed", with the reason, and the subscribe form says so beside the connector. A real UN or OpenSanctions file is refused, in words, even when this device's exceptions admit its dataset, and nothing loads; `python -m scripts.load_screening_list` refuses a list whose dataset is `opensanctions` or `un_consolidated` the same way.

Real lists and this device. OspreyFlow ships only synthetic lists. A real list loads only when this device's own `config/real_data_exceptions.yaml` (never committed, never copied between machines) names its dataset — for example `ofac_sdn` — for the use the subscription gives; otherwise the refresh is refused, in words, and nothing loads. Add an entry with `python -m scripts.real_data_exceptions add`. A list counts as synthetic only when its file is one of OspreyFlow's own (`packages/demo_fixtures/screening_lists/`, known by its fingerprint); a file cannot make itself synthetic by saying so.

Where lists live now. Lists are imported and refreshed in the **Ingest Studio → 2 Sources**, under its screening lists (and, for `load_screening_lists`, from Rules and Monitoring), and each dataset subscribes to the lists its rules read. **The rest of this section was written for the Glass's former Monitoring → Lists**, which no longer exists: read it for what a list does, not where. It is being rewritten with the alerts journey (coming).

Subscribing. In the Glass, open **Monitoring → Lists** (it needs the `load_screening_lists` right, which the administrator and data-engineer roles hold). Under **Subscribe to a list**, give the list a name, choose its connector, name its file inside the ingest folder (for example `lists/SDN.CSV`), and, for a real list, the dataset it is. A location outside the ingest folder is refused. Put each new download of the list in the same place.

The refresh. Refresh now beside a list (or, on the host, `python -m scripts.refresh_screening_list "<list name>"`, with `--list` to see the subscriptions) reads the file again and applies it as a new **version**: the publisher's own date where the format has one, otherwise the file's fingerprint. OspreyFlow compares it with the version before and re-screens every customer of every case with a screening rule against **the added and changed entries only**, as each rule's deployer and within that case's datasets; each new match is a high-severity alert in that case's queue, its link to the listed party inferred until a person confirms it. A file that is not in the connector's format fails in words and leaves the list as it was. Every refresh is recorded under **Latest refreshes**, with what it added, changed and removed, and how many customers it re-screened and how many alerts it raised **in your own unit**: each screening rule re-screens as its deployer, and its customers and alerts are counted for the deployer's unit alone, so an administrator never learns how many of another unit's customers a list touched. *Refresh now* answers the same way. The audit records who refreshed which list.

When. A list is refreshed when someone presses **Refresh now**, runs the command, or on the list's own **refresh schedule**. Under **Refresh schedule** in Monitoring → Lists, choose the list, **every day** or **every week** (and the day), and the hour (UK time), then **Save the schedule**; **by hand only** stops it. The **Schedule** column shows when each list is refreshed and when next.

- **A scheduled refresh runs as the person who saved the schedule**, resolved afresh each time — never as the system. If they can no longer sign in or no longer hold `load_screening_lists`, that refresh is refused, recorded under **Latest refreshes** in words, and nothing is read; save the schedule again as someone who holds the right.
- Each scheduled time runs once, whichever Conduit replica takes it; after downtime only the latest runs. A refresh that ran on its schedule says so under **Latest refreshes**.
- Put each new download in the list's location before the scheduled hour: the schedule reads the file that is there.

9.6 Approval rights: a second person

Three decisions wait for a second person with the right, and **the person who proposed one can never approve it** (ADR-133 decision 7):

Decision	Who proposes it	Who approves it
Deploying, changing or retiring a rule **for the whole deployment**	An Author of the case who holds `deploy_rules` and `administer_system` (an analyst who is also an administrator)	**Another** person with the same rights and level
Closing a **high-severity** alert another person may see	A member of the case who triages alerts (`triage_alerts`, Editor)	**Another** member who triages alerts in that case
A new version of the **installation-wide connection-strength influencers** (ADR-139)	Anyone holding `manage_strength_influencers` (the Analyst and Admin roles hold it)	**Another** person holding it

A rule for one case, or just for its author, needs no approval. An alert only its owner may see (their own hotlist's, kept to them) is closed by its owner alone, since no second person may read it. Writing a rule as a sentence needs `keep_watches` as well as `deploy_rules`, so a data engineer attaches rules to pipelines (Checks on load) but does not write them.

So a deployment that writes whole-deployment rules needs at least two people holding both the Analyst and the Admin roles (or `deploy_rules` and `administer_system` granted singly), each an Author of a case the rule is listed in (a whole-deployment rule is listed in every

case). With one such person, a whole-deployment rule can be proposed but never run.

Approving influencers. In the Glass's rail, **Connection strength**, a version waiting for a second person shows what it would put in force, who proposed it and why. Another holder of the right chooses **Approve version N**, or **Send it back** with words; its proposer sees the approval withheld and may withdraw it. Until a version is approved, the influencers shipped in the weights file are in force. Every version is kept, with who proposed and who decided it, and each step is in the audit stream. A case's Author may add influencers for that case, or switch off installation-wide ones in it, without a second person; that too is audited. Give the right singly (`right:manage_strength_influencers`) to someone who should set influencers without the rest of a role.

Every proposal, approval and rejection is in the case's rule audit, and every rule keeps its versions — who proposed each and who decided it. **After upgrading to this version**, a whole-deployment rule that was running waits for a second person's approval before it runs again, and is listed as waiting, "deployed before a second person's approval was needed".

9.7 Removing someone, and joining an organisation account

Remove on a person's row deletes their account from the identity provider, once you confirm it: they can no longer sign in, and their sign-in name and email address are free again. Nothing they made is changed — cases, alerts, recipes and history keep their id, which is shown where their name was; the audit log's entry for the removal says whose id it was. A case whose last Author is removed is still reached by an administrator's access to its sharing. To keep the account but stop them signing in, **Disable** it instead. You cannot remove your own account, an account OspreyFlow itself uses (none is offered), or the last enabled person who can manage people.

Refused organisation sign-ins shows, above the people, everyone who signed in through the organisation in the last seven days and was refused because an OspreyFlow account already holds their email address (section 5a.1) — by their name at the organisation, how often, and when last. Choose the account that is theirs and **Join**; confirm, and their next sign-in through the organisation lands in that account, with its roles, clearance and cases. Join only when you are sure they are the same person: the organisation said only that its account carries the same address. Each account joins one organisation account; an account already joined, or one OspreyFlow itself uses, is not offered. Every removal and every join is in the audit log.

9.8 Teams and leads

A **team** is a set of people with a lead. Admin → Roles makes one from a role (**Team for**): a **Team name** and an optional **Team mailbox**, then **Make a team**. Its status line says who leads it, who covers and until when, and who is acting today. **Name** sets the lead and **Hand over** passes it on; under **Cover for** and **Cover's last day**, **Save cover** names someone to stand in while the lead is away, and **End cover** ends it. Only a member of the team may be its lead or cover, the lead cannot cover for themselves, a cover needs a last day (today or later), and a service account is never a lead or a cover. A team can answer for a dataset (section 9.10); its members do while they are in it, and not after. *Coming:* a case level given to a team, and a rule's alerts routed to a team for its lead to hand out.

9.9 Disable, and what a person owns

Disable… on a person's row first reads what they answer for and asks who takes each item: "‹name› answers for N things. Choose who takes each one: nothing is deleted, and every transfer is audited." Each item has its own **Transfer to…**; then **Transfer and disable**, or **Confirm disabling** when they own nothing (and **Cancel**). It lists:

- the cases of which they are the only Author, a dataset's home case among them;
- the teams they lead;
- their hotlists, watches and saved patterns;
- the typology rules they own;
- their pipeline and screening-list schedules.

A transfer is refused, in words, when its recipient cannot take it: the person being disabled, a service account, someone disabled, someone of another unit, someone outside the team, someone without the right the item's runs need, or someone who is not an Author of the item's case. Items of another unit are left to that unit's administrator ("N transferred, and those stand; not disabled yet…"). You cannot disable your own account. **Enable** brings a disabled person back.

The panel ends with what it does not list yet: private views, boards, promotions waiting for review, reviews waiting on the person, and proposed types. The Conduit already reads a person's views, boards, link-type proposals and drawn-item watches (`GET /v1/admin/people/{user_id}/ownership`, for `manage_people`), each in your unit and, for proposals and watches, only at a marking you may see; it never names or counts an item you may not see, and says only that some exist. *Coming:* the panel reading that list, transferring those items, and refusing to disable someone who still owns items you may not see.

9.10 Datasets, their Authors and linked cases

Admin → **Datasets** lists every dataset: its **Kind** (*Source*, loaded through the Ingest Studio; *Composite*, read from several sources; *Drawn*, made by a drawing), its **Unit**, the **Highest marking it may hold** (or the deployment's highest), its **Egress** (section 10) and its details:

- **Promotion of drawn items**: *Author promotes*, or *Second person reviews*. It names who can approve, says "No one can approve a promotion: none of its Authors holds Review promotions." when nobody can, and warns when fewer than two people can ("one absence stops every promotion").
- **Authors**: the people or team who answer for the dataset, who are its home case's Authors. **Change owner of ‹dataset›** asks "Who answers for ‹dataset›?" and is audited. Before its first *Make live* a dataset says "Not live yet: who answers for it is asked at its first Make live."
- **Linked cases**: every case reading it, open or removed, with its analyst layer's items, links and size (never the layer's contents), the home case tagged. For a removed case's layer, **Merge ‹case› into the dataset (dry run)** and **Delete ‹case›'s layer (dry run)** say what each would do. The merge and the delete themselves are done by the dataset's Authors in the Ingest Studio's 4 Runs (developer guide, section

7.8); Admin's screen offers the dry runs only, though its delete route exists (`POST /v1/admin/datasets/{dataset_id}/cases/{investigation_id}/delete`, `administer_system`).

Who may be an owner. Admin → System's **Dataset owners may be** is *People and teams* (the default), *People only* or *Teams only*. It governs every naming of a dataset's owners; a client who wants no person's name shown as an owner chooses teams only. A service account is never an owner.

A home case per dataset. Every dataset has one home case, named for it and of its unit. It holds the dataset's own reports and its alerts that belong to no working case. It is made at a dataset's first *Make live*, which refuses to go live until someone answers for the dataset ("who answers for this dataset?"), and with a drawing made as a case of its own. For datasets that existed before, `python -m scripts.make_home_cases` gives each its home case, dry run first.

9.11 Operations and Audit

Operations (`operate_schedules`) has the schedules (pipeline, case, schedule, owner, next and last run; **Pause**, **Resume**, **Run now**, **Save schedule**) and **Promotions waiting for review**: the load, the dataset it goes into, who sent it, when, and how long it has waited. **Alert the reviewers and administrators after N days** (1 to 90) sets when a waiting promotion is overdue; an overdue one alerts the dataset's Authors who hold `review_promotions`, and administrators of its unit. A promotion is listed only to someone who may review it; with none, it says "No promotion you may see is waiting for review." Each overdue one raises its alert once, and its row reads "‹N› days, overdue".

Audit (`read_audit`) reads the audit log. **Which entries** chooses the record (*Cases, people, datasets and loads*; the *Rule audit of one case*; or the *Engines' history*, which also needs `manage_models`), a kind (analyst assertions, loads and promotions, types, people and roles, datasets, reads and refusals), a person, a case, a dataset and a period; then **Show entries**. Each entry gives when, who, what, its kind, its case and its words. Entries about another unit's cases are not shown, and where your own read of a record would not show its words, the entry says "Withheld: your own read of this record would not show them".

10. Models

By default every model runs on the deployment itself (extraction, vision, transcription and embedding — appendix A, `models.*`) and **no case content leaves it**. A client with its own agreement with one or more model providers may enable them as further **engines**: `openai`, `anthropic` and `gemini` (Google), and other LiteLLM providers such as `azure` or `bedrock` in the same shape.

```
models:
  local_only: false
  sendable_handling_codes: [P]
  providers:
    - name: gemini
      roles: {extraction: gemini/gemini-2.5-flash}
    - name: openai
      label: OpenAI (client tenancy)
      roles: {extraction: gpt-4o, vision: gpt-4o-mini}
      privacy_contract: true
      contract_reference: DPA 2026/07
  defaults:
    extraction: gemini
```

- **`providers`** lists each enabled provider: its model for each role it takes, an optional `api_base` (`https://` only) and an optional `label` — the name analysts see. Without one, the label is OpenAI, Anthropic or Gemini.
- **`defaults`** names each role's default engine: `local` or a provider's name. A role not named runs on `local`.
- **`privacy_contract`** marks a provider as under a privacy contract: set it to `true` only when your organisation holds a data-processing agreement with the provider that covers this key. It is `false` unless you set it. **`contract_reference`** says which agreement, in words ("DPA 2026/07"); it is shown to analysts, so it is never a secret, and one that looks like a key is refused.
- The older single `provider:` is still read, as a one-entry list whose roles default to it. Naming both `provider` and `providers` is refused.

Keys. Each provider's key is `OSPREY_MODEL_KEY_<NAME>` — for example `OSPREY_MODEL_KEY_GEMINI` (the single `provider:` keeps `OSPREY_MODEL_PROVIDER_KEY`). Give it in the installer's terminal before `ospreyflow install`, or on the guided install's Models screen; an enabled provider without its key stops the install, and a later install keeps a key already given. To enable a provider on a running deployment, add it to `osprey.yaml` and run `ospreyflow apply` (section 8.3), which takes its key from `OSPREY_MODEL_KEY_<NAME>` or asks for it at a hidden prompt. On a running deployment, `ospreyflow models key <name>` sets or replaces a key and `ospreyflow models remove-key <name>` removes it (section 8); `ospreyflow models` says whether each is present. A key is kept in `deployment.env` alone and read only by the deployment's model gateway — never by the Conduit, never written to `osprey.yaml`, never shown in the Admin area or any page of the Glass.

On the guided install page (section 4.1), the Models screen has a key field for each enabled provider. A key typed there is sent only to the install page, on this computer — a request from anywhere else is refused — and is held there until the install gives it to `deployment.env`. It is never written anywhere else, never logged and never shown again: the field empties once the key is sent, and the page says only "key set" or "no key".

What may leave. Material is sent to a provider only when both of these allow it:

- **its handling code** is in `sendable_handling_codes` (one list, for every engine); and
- **every dataset it comes from** allows that provider. Each dataset has an **egress** setting: - `none` — never sent to a hosted engine. **This is every dataset's setting until you change it.** - `contracted` — sent only to a provider marked `privacy_contract: true`. - `any` — sent to

any enabled provider.

Anything else runs on the local engine, whatever was chosen, and is refused in words when the deployment has no local model for the role. Material whose datasets are not known is treated as `none`, so nothing leaves by omission. Embeddings never leave the deployment.

Setting a dataset's egress. Only an administrator sets it: Admin → Datasets lists every dataset, the unit that holds it and its egress; choose the setting and press Save beside it. Each change is recorded in the audit log — who made it, when, and from what to what.

> **After upgrading to this release, hosted engines receive nothing** until an administrator sets
>
> a dataset's egress to `contracted` or `any`. Every existing dataset, demo packs included, starts
>
> at `none`; until you change one, every question runs on the deployment's own models, whatever
>
> engine an analyst chooses. Set only the datasets you are entitled to send.

Who chooses. The administrator sets each role's default. An analyst may choose, for each question in Ask the case, among the engines offered — the local engine and each enabled provider that has a key — each shown "under contract" or "no contract". An engine the case's datasets may not reach is shown but cannot be chosen, with the reason beneath the choice. Ask to search offers the same choice: its question goes under the case's handling and from the case's datasets, through the same two checks, and the deployment's own model answers whenever they do not allow the engine chosen. Every answer names the engine and model that produced it.

Admin → System shows each role's model, each engine with its models, the roles it is the default for, whether its key is present and whether it is under a privacy contract (with its reference), and a notice that case content then leaves the deployment. `ospreyflow models` shows the same mark beside each provider ("privacy contract: yes (DPA 2026/07)" or "privacy contract: no"), and the guided install's Models screen shows it as the configuration holds it.

10.1 Models in Admin

Admin → **Models** (`manage_models`) does on screen what `ospreyflow models` does from the command line, which stays for headless use and recovery. **What the installer declared** says whether the deployment is local-only (`local_only` in `osprey.yaml`). **Engines** lists each engine, its jobs and models, whether it is under a privacy contract, its key, its limits and **Edit**, **Set limits**, **Enter key** or **Rotate key**, **Remove key**, **Test the connection** and **Remove**; **Add an engine** adds one. A key is **write-only**: its field says "not shown, never sent back", and the screen says only *Key set*, *No key*, or *Key lost: enter it again*. **Each job's default engine** sets the engine for extraction and Ask, image description, transcription and embeddings. **Limits** are requests a minute, tokens a minute and a token budget for a period, applied by the gateway on the engine's own key. **Usage** gives each engine's calls, failures and tokens by job, from the gateway's own records, never by person. Every change is in **History** and the audit log.

10a. Maps

Admin → **Maps** (`manage_geospatial`) holds the map providers, the local basemap and prefetched areas; `ospreyflow map list`, `map verify`, `map prefetch` and `map build` do the same from the command line (section 8).

- **Providers**, tier 1 to 4, each with its attribution and licence, its key, its state, **Make the default**, **Edit**, **Enter key** or **Rotate key**, **Remove key** and **Remove**; **Add a provider** adds one. A key is kept the way a model key is: never shown back, and never given to the browser. Where more than one provider is drawable, analysts choose between them with the map's **Basemap** switch.
- **The local basemap**: choose the **Region to build**, the **Unit the place names are held by** (empty: your own) and **Build the basemap**; **Verify the providers** checks each one answers. The build also makes the region's gazetteer dataset, held by that unit. A dataset takes a gazetteer of its own unit (`PUT`, `DELETE /v1/datasets/{dataset_id}/gazetteers/{gazetteer_id}`, with `run_pipelines`): its places are copied into the dataset, so a case still reads one dataset; removing it deletes nothing ("...its places stay in this dataset as its own, and the map's place search no longer offers them..."). *Coming:* doing this on screen.
- **Prefetch areas**: areas whose tiles are fetched ahead of use, and **Fetch every area** by hand only, every 6 hours, every day or every week.

Changes are in **History** and the audit log.

11. Demo packs

Id	What it shows	How it arrives
`hmp`	Prison intelligence: a prison's people and places, cell shares, co-defendants, conflicts, incidents, visits in person and by video, phones, calls and payments (synthetic)	Generated
`fixture-corp`	Network shapes, and duplicate records matched without being merged (synthetic)	Generated
`operation-ledger`	Preventive AML: a structuring ring, onboarding screened before it commits, ownership through a trust (synthetic)	Generated
`prison-intelligence`	Prison intelligence, end to end: a fictional jail's records as an intelligence team receives them, loaded through the Ingest Studio from source files, each with its own marking (synthetic)	Generated
`prison-intelligence-scale`	The same estate at scale: 3,000 prisoners and 30,000 links across six establishments, to show a large network grouped by community (synthetic)	Generated
`cyber-intrusion`	Cyber threat analysis in STIX 2.1: a fictional threat actor's campaign against a water company — its backdoor, two command-and-control servers, the indicators that find them and the traffic observed; its case is set to STIX (synthetic)	Generated
`paysim`	Mobile-money fraud: 6.36 million simulated transactions with fraud labels	Downloaded by you

Id	What it shows	How it arrives
`enron`	**Real data**: about 150 people's real email at Enron, 1998–2002 — who wrote to whom, when, and about what	Downloaded by you; accepted before it loads; never by an install

Which a starter brings is section 1a's table: a starter loads its domain's packs, into cases set to its domain's packs. A **public dataset** of your own choosing, such as a VAST Challenge dataset, is added with `ospreyflow demo add public` (section 1a.2).

Choose them at install (`demo_packs`), or later: `ospreyflow demo list`, `ospreyflow demo add <id>`. Each loads into its own case, with the installing administrator as Author: the demo administrator where there are demo accounts (the demo analyst its Editor), and otherwise the first administrator, `admin`, in their own unit, with no Editor (section 1a); they hold the Analyst role as well as Admin, so the case opens for them. Adding **HMP** again is safe: a deployment that loaded it before v0.2.0 gains only its prison network, in the same case, and one that already has the network is left as it is. **PaySim** is a download: get `PS_20174392719_1491204439457_log.csv` from its Kaggle page and pass it with `ospreyflow demo add paysim --file <path>`; it is checked by size and checksum before anything starts. PaySim is CC BY-SA 4.0 (E. A. Lopez-Rojas, A. Elmir and S. Axelsson, 2016); its licence and attribution travel with it.

Prison Intelligence seeds its case through the Ingest Studio's own pipelines, as a data engineer would, and has commands for rehearsing a demonstration: `--reset-live` between rehearsals, and two for the session itself (`DEMO_GUIDE.md` in the repository gives each, in full). It needs `components.post_ingest_resolution` off (appendix A), or a live load in the demonstration adds automatic "same as" links and every rehearsal reset then refuses. An install whose `demo_packs` names it (the `crime` starter's does) writes the setting off itself (section 1a). Added later, on a deployment where it is on, `ospreyflow demo add prison-intelligence` refuses, in words, with nothing added: set `post_ingest_resolution: false` under `components:` in the deployment's `osprey.yaml`, run `ospreyflow apply`, then add it again. Resolution is the whole deployment's setting; no case or dataset can turn it off on its own. Its **scale cohort** (`prison-intelligence-scale`) is written straight into the graph in a case of its own, with no pipeline runs, so the rehearsal reset does not touch it; adding it again changes nothing, and a run that stopped part-way says so rather than finishing it. `python -m scripts.write_pid_files --out <folder> --profile scale` writes its 3,000 prison numbers as `scale_cohort_list.txt`, to paste into *Add many from a list*.

Enron is the one pack of **real personal data**: the email of real people, released during the US regulator's investigation and distributed by Carnegie Mellon University. OspreyFlow never carries it, and an install never adds it. To use it, download `enron_mail_20150507.tar.gz` (423 MB) from https://www.cs.cmu.edu/~enron/ yourself, then:

```
ospreyflow demo add enron --file enron_mail_20150507.tar.gz
```

It checks the file is exactly the May 7, 2015 version (size and SHA-256), then says what it is — real people's names, addresses and private correspondence; **no licence is stated**, CMU distributing it "as a resource for researchers" and asking that you "be sensitive to the privacy of the people involved"; your organisation needs its **own lawful basis** to process it — and loads it only when you type `yes`. (`--accept-real-data` accepts in a scripted run, and says so.) It is unpacked into the demo data folder — 150 mailboxes, about 517,000 messages and 2.5 GB, so allow 3 GB free with the download — with a record of the acceptance beside it, and loads into its own case, "Enron corpus (real data)", shared with no demo account but the administrator and analyst. The terms are in `packages/demo_fixtures/licences/enron/NOTICE.md`.




Figure 5. Admin → Demo packs: what each pack shows, where it was loaded, and the command for the rest

12. Dashboards

With dashboards on, **report sync** pulls each case's figures into a reporting database every 15 minutes (`reporting.sync_interval_seconds`), and **Superset** shows them at `bi.`, signing people in through the deployment's identity provider (below). A business intelligence tool (Power BI,

Tableau, Qlik) reads the same figures:

1. register the dashboard in Admin → Dashboards and copy its secret (shown once);
2. add it to `REPORT_SYNC_DASHBOARDS` in `deployment.env` (a JSON list of `{"client_id", "secret"}`) and restart: `ospreyflow stop`, `ospreyflow start`;
3. a case's Author gives the dashboard's account Viewer on the case.

Each pull is made as that account, at its clearance, audited and recorded in the export ledger.




Figure 6. Admin → Dashboards: registering a dashboard's account and seeing when it last pulled




Figure 7. Superset at bi.: the boards and charts built on the reporting figures

The monitoring board

The feed also carries four monitoring sections, for every kind of alert (typology, hotlist and monitor), each a row of `section`, `label`, `typology`, `week_start` and `value` in the reporting database's `figures` table, beside `raised`, `open_by_age` and `outcome`:

`section`	`label`	What it counts
`raised_by_rule`	`typology` (with its `typology`), `hotlists` or `monitors`	alerts raised each week, by rule
`closed`	the closing reason as stored: `true_positive` (True match), `false_positive` (False positive), `duplicate`, `no_further_action` or `referred`; or `closed` (taken back, no outcome)	alerts closed each week, by outcome

section	label	What it counts
time_to_close	under a day, 1 to 7 days, 7 to 30 days, over 30 days	alerts closed in the period, by how long they took
hotlist_matches	hotlists	hotlist matches each week

A typology rule is named by its typology, never by its own name, which an analyst writes and the feed does not carry. Every figure is counted as the dashboard's account may see it; a hotlist kept "only me" is counted for its owner alone, so never on a dashboard.

In the Glass, the rail's **Dashboards** draws an **Alert monitoring** board itself, first among the boards, from the same figures counted as the person reading it: raised each week and by rule, closed by outcome, time to close, hotlist matches and the team view. A Reports Viewer's *Open the dashboard* opens it filtered to an alert's rule and period. It needs no Superset set-up. For a board of your own in Superset, none ships as a file: build it from the `figures` table, filtered on these sections — for example a stacked bar of `raised_by_rule` by `week_start` and `label`, a bar of `closed` by `label`, a table of `time_to_close`, and a line of `hotlist_matches` — with a filter on `case_name`. Report sync fills it on its next pull; nothing else needs to change.

13. Backup and restore

Coming (ADR-114 Amendment 37): every install names its backups folder at setup, never inside the checkout. Until then, Lite writes into the checkout's `backups/` and Small on your own server into `server.backups`.

Lite. `ospreyflow backup` writes a set to `backups/<time>-<profile>-<commit>/`: the graph store, every PostgreSQL database (the identity provider's accounts as their own export), the analytics database, the object store (each object with its checksum), the configuration, and a manifest of checksums. Taken while the Conduit runs, the stores may be captured at slightly different instants — it says so; `--require-quiesced` refuses to run unless the Conduit is stopped.

`ospreyflow restore <set>` is a **dry run** first: it checks every checksum and estimates how long it will take. `ospreyflow restore <set> --yes` restores. It refuses a set whose checksums do not match, a deployment that is not empty, and a set from another ontology version. Passwords are not restored: the deployment's own are kept. Once PostgreSQL is restored, the restore starts the identity provider (Keycloak) again and waits until it answers before it brings the accounts back: a Keycloak left running while the database under it was replaced refused the restore, with "could not authenticate to Keycloak: 500" (section 16).

Small. The cloud protects the data: the database's own backups and snapshots, and the server's daily backup. `ospreyflow backup` refuses a deployment on a managed database, saying so; restore from the cloud's console.

Small on your own server. As Lite, every store in the set, written to `server.backups` (section 5a.3), each set readable by its owner only; the certificate's key and `deployment.env` are never in it. Schedule it with a cron line, for example `0 2 * * * cd /opt/ospreyflow && ~/.local/bin/ospreyflow backup`. A person who signs in through the organisation's identity provider is restored still linked to it. OpenSearch is not in the set, as on Lite (below).

A fresh deployment has no published recipes and no analytics events yet: its first set records them as **empty** (the manifest's `empty` list, and the backup's last lines say so), and a restore of it restores nothing for them. **Where the stores keep their data** (Lite, and Small on your own server). In Docker named volumes of the deployment's own: `<project>_postgres-data` (every PostgreSQL database — the Conduit's records, the accounts, the audit log), `<project>_arcadedb-databases` and `<project>_arcadedb-config` (the graph and its server's settings), `<project>_valkey-data` (the working sets and job queues), `<project>_opensearch-data`, beside `<project>_osprey-data`, `<project>_osprey-staging` and `<project>_objectstore-data`. `<project>` is `osprey-local-lite`, `osprey-small`, or the `deployment.name` you gave; `docker volume ls` lists them. They outlive a stopped, recreated or removed container, so a restart, `ospreyflow apply`, an update and `uninstall --keep-data` keep them; `ospreyflow uninstall` without `--keep-data` removes them. A deployment installed with v0.4.10 or earlier kept PostgreSQL and ArcadeDB in unnamed volumes, and Valkey and OpenSearch inside their containers; its data is moved into the named volumes once (section 14). A backup reads each store through its own running server, so it is the same wherever the data is kept. **Not in a backup:** Valkey's working sets and queues, and OpenSearch, which holds no index of OspreyFlow's yet — so there is nothing of it to restore or rebuild, and a restore starts it empty.

A backup that fails removes the set it had started, and says so, so no half-written set is left beside the good ones. If it cannot remove all of it, it says what it could not remove, renames the set `<set>.incomplete` with a file `INCOMPLETE` in it, and `ospreyflow restore` refuses it; remove it as root (`sudo rm -rf <set>.incomplete`).

Once the object store holds files (a demo pack or an upload has put some there), it is copied as the account that runs `ospreyflow backup`, so that account can remove its working copy. With v0.4.8 and earlier on Linux such a backup failed with "Permission denied" (section 16).

Enterprise. The cloud protects its managed services as for Small. **The graph store and the analytics database run in the cluster, and nothing backs them up yet**: `ospreyflow backup` drives a Compose deployment and does not reach a cluster. Until it does, take snapshots of their volumes with the cloud's own tools.

Audit. The audit log is in the same PostgreSQL as everything else, so it is in the same backup and shares its retention.

14. Updates

Releases are tagged `vMAJOR.MINOR.PATCH`, with signed images and a signed list of every image by digest. Each release's notes are its section of `CHANGELOG.md`.

Which installs `update` moves, and how the others are updated:

Your install	How it is updated
Lite, installed from a release tag	`ospreyflow update` (below)
Lite, built from the checkout (`--build`, or a checkout on no release tag)	`git pull`, then `ospreyflow start --build`. `update` refuses this install, saying so
Small	**Not yet by `update`**: its first step, the backup, refuses a deployment on a managed database (section 13). The cloud's own backups protect the data
Small on your own server, installed from a release tag	`ospreyflow update`, as Lite: its backup is written to `server.backups` first
Enterprise	Move the checkout to the release's tag and run the install again: the chart is upgraded in place, every password and account kept

Checking for a newer release. The deployment never calls out to look. Run `ospreyflow update --check` on the computer that holds the checkout: it asks the repository's releases and leaves the answer where Admin → System shows it, with when it asked: "*vX.Y.Z* is available", "Up to date", or "The last update check could not answer" and why; before the first check it says "Not checked for updates yet", and an install built from its checkout is told it moves with `git pull` and `ospreyflow start --build`. It checks only when you run it — to be told each week, add it to that computer's own scheduler, for example a cron line `0 8 * * 1 ospreyflow update --check`. If the repository is private, set `GITHUB_TOKEN` to a token that can read it first; without one the check cannot answer, and says so.




Figure 8. Admin → System: each component's health, the models in use, the version, and the last update check

Moving to a release.

- `ospreyflow update` moves to the newest release (`--to vX.Y.Z` for another; `--yes` asks nothing). It checks every image's signature first and changes nothing if one fails; refuses if a local change to a file would be overwritten ("commit or undo them first"); **backs everything up**; moves the checkout to the tag; starts the release's images and checks each service runs them. If anything fails after the backup it **rolls back** — the previous release and its data restored from the backup just taken — and says so.
- **Without internet**: on a machine with it, `ospreyflow update --make-bundle <file> --to vX.Y.Z` writes the release, verified, to one file; carry it over and run `ospreyflow update --from <file>`, which checks it again with no network. - **A bundle carries one platform's images**: `linux/amd64` unless `--platform` names another, whatever the machine making it runs on, so a bundle made on an Apple-silicon Mac is for an amd64 server as it stands. A release is built for `linux/amd64` and `linux/arm64`; for an arm64 server, add `--platform linux/arm64`. Any other platform is refused before anything is fetched, and says which platforms a release has. - `--from` refuses a bundle for another platform than its machine's before it checks or loads anything, and says what to run instead, for example: "this bundle carries the images for linux/arm64, and this machine is linux/amd64; nothing was verified or loaded. Make one for it on any machine that reaches the release: ospreyflow update --make-bundle FILE --platform linux/amd64". A bundle made before this version names no platform: it carries the platform of the machine that made it, and on another it is refused when its cosign image is checked.

An update moves forward only.

The stores' one-time move to named volumes. A deployment installed with v0.4.10 or earlier keeps its PostgreSQL and ArcadeDB data in unnamed volumes, and Valkey's and OpenSearch's inside their containers (section 13). The first `ospreyflow update` after that — after its backup and before anything starts — moves the data into the stores' named volumes, once; so does the first `ospreyflow start`, `start --build`, `apply` or `install` that brings such a deployment up from a newer checkout. The deployment is stopped while it moves: each store is started alone on its old data and asked what it holds, its data is copied with its own image keeping every owner and permission (Valkey's from its container, through a temporary image of it that is removed afterwards), the copy is checked file by file against the original, and the store is

started on its named volume in a container of its own, apart from the deployment's, and must hold the same as before. Only then does the command start the deployment on the named volumes. It says, for example:

```
The stores' data moves to named volumes, once: postgres, arcadedb, valkey, opensearch. The deployment is stopped while
it moves; the old volumes are kept.
  postgres: the databases keycloak, osprey, postgres, superset.
  postgres: copying /var/lib/postgresql/data from 3f9c…e1 to osprey-small_postgres-data…
  postgres: /var/lib/postgresql/data copied and checked (2114 entries, the same owners, modes and contents).
  …
  valkey: keys that do not expire db0: 1.
  valkey: copying /data from valkey's container to osprey-small_valkey-data…
  …
  opensearch: holds no index of its own, so nothing is copied; it starts on its named volume empty.
  postgres: on its named volume it holds the databases keycloak, osprey, postgres, superset, as before.
  …
The stores' data is in their named volumes, checked; they start on them next.
The old volumes are left in place: 3f9c…e1, 7a20…4b, c51d…90, 0be8…7f. Once the deployment works as before, remove them
with:
  docker volume rm 3f9c…e1 7a20…4b c51d…90 0be8…7f
```

Run again, it does nothing. It needs room for a second copy of the stores' data on the disk where Docker keeps its volumes (`ospreyflow doctor` shows that disk). **If the move fails**, it says why and removes nothing: the named volumes it filled are removed, each store's data is where it was, no container of the deployment's has been replaced, and every file the command wrote is put back as it was, so the deployment still runs from the files that name its old data. An update then rolls back to the previous release on that data, with nothing restored ("rolled back to … on its own data, which was never moved"). `apply`, `install` and `start --build` stop, saying "…, and the deployment's files are as they were. The deployment is stopped; ospreyflow start starts it on that data." — or "Nothing was stopped." when the move refused before it stopped anything — and `ospreyflow start` then brings the deployment up on its old data. If an update fails after a move that succeeded, it rolls back as for any other failure (the backup restored) and removes the named volumes the move filled; the old volumes are kept either way.

14.1 Removing the old store volumes

After the move, each store's old volume is left as it was — a long hexadecimal name — and nothing uses it. Check the deployment first: sign in, open a case, and take a backup (`ospreyflow backup`, section 13). Then remove the volumes the move named, with the command it printed:

```
docker volume rm <name> <name> …
```

Docker refuses to remove a volume a container still uses, so nothing in use can be removed this way. If the move's words are lost, `docker volume ls --filter dangling=true` lists the volumes no container uses; this deployment's are among them, but so may be other programs', so do not remove them all (`docker volume prune` would). Until they are removed they cost only disk.

15. Scheduled and watched pipelines

A published pipeline can run on a **schedule** (hourly, daily, on weekdays or weekly at a time, in a named time zone, or a cron expression; never more often than every 15 minutes) and when a **file arrives** in its dataset's folder (a filename pattern such as `*.csv`; each new file runs once, a minute after it stops changing). Both are set on the Ingest Studio's Publish screen by someone holding `schedule_pipelines`, and run **as that person**, with every check their own run would get. A run that is refused or fails tells its owner in their alerts; three refusals in a row pause it. Admin → Schedules and runs lists every one.




Figure 9. Admin → Schedules and runs

16. When something is wrong

Symptom	Look at
`install` stops at the checks	The crossed line says what to fix; nothing was changed
A service is not healthy	`ospreyflow status`, then `ospreyflow logs <service>`
The page does not open	`ospreyflow status`; that port 80 (Lite) or the DNS records (Small) are right
Nobody can sign in	`ospreyflow logs keycloak`; that the address in `osprey.yaml` is the one in the browser; then `ospreyflow repair-sign-in`
Rules say "the rule's deployer could not be resolved", a hotlist reads **Stopped**, or a list refresh re-screens 0 customers — typically after the stores were wiped; Admin → System's **Acting for people** says "The Conduit cannot act for people"	The Conduit cannot act for people: the identity provider no longer holds its client secret. Run `ospreyflow repair-sign-in`, then run the rule again. The System line turns green within half a minute
Someone signing in through the organisation is told "This email address already belongs to an OspreyFlow account"	An account you made holds their email, and OspreyFlow does not join the two by itself (section 5a.1). Join them in Admin → People and roles' *Refused organisation sign-ins*, or remove that account and they arrive again, or they sign in with that account (section 9.7)
Refused organisation sign-ins does not list someone who was refused	It lists the last seven days, from a deployment updated to the release after v0.4.10 and repaired since (`ospreyflow repair-sign-in`, which also makes the identity provider record the refusals). Someone refused before that, or more than seven days ago, is not listed: ask them to sign in through the organisation once more, then look again. Someone already joined to an account is not listed either
Admin → People and roles says "the identity provider refused the Conduit — its account needs manage-users, manage-clients and view-events"	Run `ospreyflow repair-sign-in`, which grants the Conduit's account what it needs
Removing someone is refused: "the only enabled person who can manage people"	Give someone else the Admin role (or the `manage_people` right) first, so the deployment is never left with no administrator. Your own account cannot be removed either: another administrator removes it
`doctor`, the install or `repair-sign-in` warns "Sign-in through the organisation joins by email"	`sign_in.organisation.trust_email` is on (section 5a.1). Keep it only with the security officer's written sign-off; otherwise set `trust_email: false` in `osprey.yaml` and run `ospreyflow apply`
Windows ask people to sign in again after about half an hour away	As intended: a window renews its sign-in only after the person has done something, so one left alone ends at the identity provider's idle limit (Keycloak's default, 30 minutes). The page is kept; they sign in again in a small window
`doctor`, `install` or `apply` says "the certificate is refused"	Each reason is named, and nothing was changed. "does not match": the key is another certificate's. "encrypted with a passphrase": write the key unencrypted (`openssl pkey -in <encrypted> -out <key>`), mode 600. "does not cover id....": a wildcard for the parent domain covers one label only; ask for `id.<host>` and `bi.<host>`, or `*.<host>` (section 5a). "expired" or "not valid until": a new certificate, or the server's clock. "does not reach the organisation's root": put the intermediates after the server certificate. "the identity provider … cannot" read the root: `chmod 644` the `ca` file. Then run the command again

Symptom	Look at
Nobody can sign in through the organisation (Small on your own server)	The organisation's page says the redirect URI is not registered: register exactly the address `ospreyflow doctor --mode small --config install.yaml` prints (section 5a.1). The sign-in comes back with "Unexpected error when authenticating with identity provider": the client secret is wrong (put the right one in `deployment.env`, then `ospreyflow repair-sign-in`) or the server cannot reach the provider (`login.microsoftonline.com` for Entra ID). `repair-sign-in` says "could not read the organisation's sign-in settings": the issuer is wrong, the provider cannot be reached, or — for a provider on the organisation's own certificates — `server.ca` is missing
Someone signed in through the organisation and sees nothing	As intended until an administrator grants them roles and access in Admin → People and roles (section 5a.1)
`doctor` says too little disk where backups are written	Give `server.backups` more room, or name another folder; remove old sets
People on the network cannot connect to Small on your own server	Port 443 is open in front of the server — its firewall or security group, or the `DOCKER-USER` chain; `ufw` does not filter a port Docker publishes — and the three names resolve to the server in the organisation's DNS
`doctor`, `install` or `apply` refuses the GPU	Each reason is named, and nothing was changed: install the NVIDIA driver and restart until `nvidia-smi` lists the GPU; install the NVIDIA Container Toolkit and run `sudo nvidia-ctk runtime configure --runtime=docker` and `sudo systemctl restart docker`; on macOS or Windows, set the GPU to `none` (section 5a.4)
`ospreyflow update --from` says "this bundle carries the images for linux/arm64, and this machine is linux/amd64", or "the bundle's cosign image is not the one pinned for linux/amd64"	The bundle was made for another platform: the second words are a bundle made with v0.4.10 or earlier, before `--platform`, which carried the platform of the machine that made it (an Apple-silicon Mac's is arm64). Nothing was verified or loaded. Make it again with `ospreyflow update --make-bundle <file> --platform linux/amd64` (the default) on any machine that reaches the release (section 14)
`ospreyflow demo add` or an upload fails with "Permission denied: '/var/lib/osprey/ingest/uploaded/...'", or `install`, `apply`, `start` or `update` says "the Conduit (uid 10001) cannot write .../uploaded"	Linux only: the Conduit's upload folder in `server.ingest` (Lite: `components.storage.ingest`) is not its own. A deployment installed or updated with v0.4.8 or earlier has it so: run `ospreyflow apply` or `ospreyflow start` once with a later version, which gives the folder over (section 5a). When giving it over fails, the command names Docker's reason; or give it over yourself, `sudo chown 10001:10001 <server.ingest>/uploaded`, and run the command again
`ospreyflow backup` fails with "Permission denied" on a file under `.objects-staging`, or a folder named `….incomplete` is left where backups are written	Linux, v0.4.8 or earlier, once the object store holds files: the object store's copy belonged to the Conduit's user. Update, then back up again. Remove what was left as root (`sudo rm -rf <folder>`); a folder with an `INCOMPLETE` file in it is not a backup, and `restore` refuses it (section 13)
Ask on the local engine fails after the extraction model was changed (the GPU switched on, or `models.extraction`)	`ospreyflow apply` fetches the newly chosen model, and waits for it, before anything that uses it starts again; if the download fails it stops with nothing changed, saying "the model download (ollama-models) did not finish": `ospreyflow logs ollama-models` says why, then run `ospreyflow apply` again. With v0.4.8 or earlier, `apply` never fetched it: `docker compose --env-file <deployment>/deployment.env -f <deployment>/compose.yaml up -d --force-recreate --no-deps ollama-models` fetches it (the 14b is about 9 GB)
A Small server never answered	Its log, `/var/log/ospreyflow-first-boot.log` (Session Manager on AWS)
An update rolled back	Its own words say why, and where its backup is
`start`, `apply`, `install` or `update` says "the stores' data could not be moved to named volumes"	Nothing was removed, and the deployment's files are as they were: `ospreyflow start` runs it on its old data (section 14). "both its current volume … and the named volume … hold data": the named volume is left from an earlier attempt — look at it, and remove it (`docker volume rm <name>`) only if it holds nothing you need; then run the command again. "holds the indexes …": OpenSearch holds an index OspreyFlow did not write, which would not survive the move; snapshot or remove it first. "No space left on device": free room for a second copy of the stores' data where Docker keeps its volumes. "is not the same as the original": the copy did not keep an owner or a permission; say so, with the line it names
Old unnamed volumes after the move	Expected: section 14.1 says how to remove them once the deployment works as before
`restore` fails on 'identity' with "could not authenticate to Keycloak: 500"	The identity provider was running on a database replaced under it, and builds its tables only when it starts. From the release after v0.4.10 the restore starts it again itself before that step. With v0.4.10 or earlier, everything before the accounts is restored: run `ospreyflow stop` then `ospreyflow start`, and ask for the accounts to be brought back from the same set (the restore's identity step on its own); do not run the whole restore again, which refuses a deployment that is no longer empty
The model download stopped with `rename …-partial …: no such file or directory`	A model server restarted mid-download and removed the half-fetched file (fixed from the release after 15 October 2026). Run `ospreyflow start` while the deployment is up: it starts the download again and the server keeps running, so it completes

Appendix A — every `osprey.yaml` setting

Made from the deployment's own schema. Settings marked *section* hold the settings below them.

Option	Value	Default	What it does
`profile`	`local-lite` | `small` | `cluster`	`local-lite`	Which kind of deployment: one machine (local-lite), a cloud server on managed services or a server of your own with every store in a container (small), or a cluster.

Option	Value	Default	What it does
`components`	section	—	Which stores the deployment runs, and where their data lives.
`components.graph_store`	`arcadedb` | `janusgraph`	`arcadedb`	The graph store.
`components.analytics_engine`	`duckdb` | `clickhouse`	`duckdb`	Where events are counted: DuckDB inside the Conduit, or ClickHouse shared by several.
`components.post_ingest_resolution`	bool	true	Whether a load queues entity resolution afterwards (`OSPREY_POST_INGEST_RESOLUTION`). False for a demonstration whose people must not gain automatic `SAME_AS` links; an analyst's own Resolve now still works.
`components.search`	`opensearch` | `postgres-fulltext`	`opensearch`	Search; postgres-fulltext is the lighter variant.
`components.storage`	section	—	Folders: inside the containers, and on the host for ingest and tiles.
`components.storage.data`	str	`/var/lib/osprey/data`	Where the deployment keeps its data inside the containers.
`components.storage.staging`	str	`/var/lib/osprey/staging`	Where loads stage their rows before they reach the graph.
`components.storage.backups`	str	`/var/lib/osprey/backups`	Where backups are written.
`components.storage.ingest`	str	`/var/lib/osprey/ingest`	The host folder of source files the Ingest Studio lists (read-only to it; uploads go to its uploaded/ folder). A relative path is read from the folder osprey.yaml is in.
`components.storage.tiles`	str	`/var/lib/osprey/tiles`	The host folder a built basemap lives in. A relative path is read from the folder osprey.yaml is in.
`components.source_path`	str or none	none	The owned services (workspace, api, ingest) are PULLED, by the digest recorded in versions.lock, from the registry reference harness/render.py's own service_images names. This is the operator path: the harness image itself carries no services/ or apps/workspace source, and a review found that the documented one-command bootstrap could not Launch without it — a clean laptop has no checkout. Set to a checkout root containing services/api/Dockerfile, services/ingest/Dockerfile and apps/workspace/Dockerfile (this repository's own root, for a developer/CI run) to BUILD owned images from source instead. Declared and the Dockerfiles absent is refused by name (harness.render.MissingDockerfileError) — never silently treated as the pull path.
`models`	section	—	The local models, and the client's own model providers (engines) if any are enabled.
`models.local_only`	bool	true	No hosted fallback
`models.hosted_fallback`	str or none	none	A provider name, never a credential.
`models.sendable_handling_codes`	list of str	—	Which handling codes may leave for a hosted model.
`models.provider`	section or none	none	The older one-provider form, read as a one-entry providers list; not with providers.
`models.provider.name`	str	required	LiteLLM's name for the provider: openai, anthropic, gemini, azure, bedrock…
`models.provider.label`	str or none	none	The name analysts see for this engine. Default: OpenAI, Anthropic or Gemini for those three, else the provider's name capitalised.
`models.provider.roles`	mapping	required	The roles it takes, each with the provider's model for it
`models.provider.api_base`	str or none	none	The provider's address, where it is not LiteLLM's default (an Azure deployment, a proxy)
`models.provider.privacy_contract`	bool	false	True when the deployment's organisation holds a data-processing agreement with the provider covering this key. A dataset whose egress is `contracted` is sent only to a provider marked so. Default: false.

Option	Value	Default	What it does
`models.provider.contract_reference`	str or none	none	The agreement's reference, in words (for example DPA 2026/07); never a secret. Shown beside the mark.
`models.providers`	list of section	—	The providers (engines) an administrator enables, each reached through the deployment's gateway; each key is OSPREY_MODEL_KEY_<NAME>.
`models.providers.name`	str	required	LiteLLM's name for the provider: openai, anthropic, gemini, azure, bedrock...
`models.providers.label`	str or none	none	The name analysts see for this engine. Default: OpenAI, Anthropic or Gemini for those three, else the provider's name capitalised.
`models.providers.roles`	mapping	required	The roles it takes, each with the provider's model for it
`models.providers.api_base`	str or none	none	The provider's address, where it is not LiteLLM's default (an Azure deployment, a proxy)
`models.providers.privacy_contract`	bool	false	True when the deployment's organisation holds a data-processing agreement with the provider covering this key. A dataset whose egress is `contracted` is sent only to a provider marked so. Default: false.
`models.providers.contract_reference`	str or none	none	The agreement's reference, in words (for example DPA 2026/07); never a secret. Shown beside the mark.
`models.defaults`	mapping	—	Each role's default engine, `local` or an enabled provider's name. A role not named runs on `local` (for the single `provider`, on it).
`models.extraction`	`qwen2.5:7b-instruct` | `qwen2.5:14b-instruct`	`qwen2.5:7b-instruct`	The local model that extracts entities from text. Default: qwen2.5:7b-instruct, the model the product ships with; with resources.gpu: nvidia and this not named, qwen2.5:14b-instruct.
`models.vision`	`moondream:1.8b-v2-q4_K_M`	`moondream:1.8b-v2-q4_K_M`	The local model that describes an image and reads its text.
`models.transcription`	`Systran/faster-whisper-tiny.en`	`Systran/faster-whisper-tiny.en`	The local model that transcribes a video's speech.
`models.embedding`	`all-minilm:22m-l6-v2-fp16`	`all-minilm:22m-l6-v2-fp16`	The local model that turns text into vectors.
`governance`	section	—	Identity, handling, ontology and the marking shown on screen.
`governance.identity_provider`	str	`keycloak`	The identity provider people sign in through.
`governance.handling_scheme`	str	`uk-law-enforcement`	The handling scheme every item is marked under.
`governance.ontology`	str	`default`	The ontology the deployment starts from.
`governance.organisation_sign_in`	str or none	none	The alias of an organisation's own identity provider brokered by Keycloak. When set, the welcome page offers *Continue with organisation sign-in* (*Continue with <label>* when `organisation_provider` names one), which goes straight to it. Default: none — one *Sign in* to the OspreyFlow form.
`governance.organisation_provider`	section or none	none	Small on a server of your own: the organisation's identity provider, brokered by Keycloak; its client secret is never here (section 5a.1).
`governance.organisation_provider.label`	str	required	The provider's name as people know it, shown on the welcome page's button (Continue with <label>) and on the identity provider's own sign-in pages (for example 'Example Department account').
`governance.organisation_provider.issuer`	str	required	The provider's issuer, an https:// address; its discovery document is read from <issuer>/.well-known/openid-configuration (for Entra ID, https://login.microsoftonline.com/<tenant>/v2.0).
`governance.organisation_provider.client_id`	str	required	The application (client) id the organisation registered for OspreyFlow.

Option	Value	Default	What it does
`governance.organisation_provider.trust_email`	bool	false	ADR-114 Amendment 33, 'Step 33': true joins a person arriving through the organisation to the OspreyFlow account holding the same email address, automatically, with its roles and clearance. Off by default: a person whose email an account holds is refused in words, and an administrator joins them in Admin, People and roles. Turn it on only with the organisation's security officer's written sign-off that every address its provider gives is verified and cannot be set by the person who holds it: anyone who can make the provider give an address takes over the account that holds it (the 2023 'nOAuth' account takeovers).
`governance.marking`	str or none	none	The protective marking shown where no case data is on screen: the welcome page, Home, the Ingest Studio and the Admin area; inside a case, the strip shows this or the highest marking on screen, whichever is higher. One of the handling scheme's classifications. Default: the scheme's lowest.
`governance.real_data_exceptions`	str	`config/real_data_exceptions.yaml`	A path to the gitignored list, never its contents.
`cluster`	section	—	A Kubernetes deployment: its namespace, storage classes and machines.
`cluster.hosts`	list of section	—	One machine.
`cluster.hosts.name`	str	required	The machine's name
`cluster.hosts.address`	str	required	Where the machine is reached
`cluster.hosts.roles`	list of str	—	What runs on it
`cluster.namespace`	str	`ospreyflow`	The Kubernetes namespace the deployment is installed in
`cluster.storage_class`	str or none	none	The storage class each store's own volumes use; the cluster's default when unset
`cluster.shared_storage_class`	str or none	none	Required for a cluster: the storage class of the one volume every Conduit shares (ReadWriteMany) — EFS on AWS, Azure Files on Azure
`network`	section	—	The address the deployment answers at, and what it publishes.
`network.expose_conduit`	bool	false	Publish the Conduit's own port on the host in addition to the workspace's. Not needed to use the deployment — the workspace proxies /v1 — and turning it on widens the exposed surface by a whole tier. For an operator debugging the Conduit directly, or a second client that is not the Glass.
`network.public_origin`	str	`http://ospreyflow.localhost`	The origin a browser uses to reach the Glass; the identity provider is `id.` and the dashboards `bi.` in front of the same host, with the same scheme and port, and the front proxy publishes that port. `06_DECISIONS.md` ADR-050 objection 2's resolution: the identity-provider realm is rendered from this value at apply time and the Glass's public client is registered with an exact redirect URI and post-logout URI derived from it — no wildcards. Change this to move the deployment to another name or port; nothing else needs to agree with it.
`network.tls`	section or none	none	Small on a server of your own: the organisation's certificate (ADR-114 Amendment 33).
`network.tls.certificate`	str	required	The server certificate, then its intermediates, in PEM: an absolute path.
`network.tls.key`	str	required	The certificate's private key in PEM, unencrypted: an absolute path. Owned by the installing account, mode 600; the front proxy runs as that account to read it.
`network.tls.ca`	str or none	none	Optional: the organisation's root certificate (PEM), an absolute path. With it, the certificate's chain is checked to reach it, and the host's own tools trust it.

Option	Value	Default	What it does
`network.redirect_http`	bool	false	Small on a server of your own, with network.tls only: also publish port 80, and only to send people to the https:// address. Default: false — port 443 alone.
`network.listen_address`	str or none	none	Small on a server of your own, with network.tls only: the one address of the server the front proxy publishes on. Default: none — every interface.
`map`	section or none	none	The basemaps the map offers.
`map.default`	str	required	The provider the map opens on, by its id
`map.providers`	list of section	required	One basemap.
`map.providers.id`	str	required	The provider's own name, as map.default names it
`map.providers.label`	str	required	What the Glass's map menu calls it
`map.providers.kind`	`vector` | `raster` | `image` | `dem`	required	
`map.providers.licence`	section	required	The basemap's licence.
`map.providers.licence.id`	str	required	The licence's identifier, e.g. ODbL-1.0 or OGL-UK-3.0
`map.providers.licence.redistributable`	bool	required	Whether the tiles may be passed on to others
`map.providers.licence.client_scope`	`open` | `per-deployment` | `per-seat`	required	Who the licence covers: anyone, this deployment, or each seat
`map.providers.licence.note`	str or none	none	Anything the licence asks to be said
`map.providers.source`	str or none	none	Where the tiles are: a file (file://...pmtiles) or a provider's address; one of source, service and endpoint, or profile
`map.providers.service`	`wmts` | `wms` | `wfs` | `ogc-features` or none	none	
`map.providers.endpoint`	str or none	none	An OGC service's base address (with service), never a tile URL
`map.providers.layer`	str or none	none	The service's layer to show
`map.providers.tile_matrix_set`	str or none	none	WMTS: the tile matrix set
`map.providers.format`	str or none	none	WMTS: the tile image format
`map.providers.wmts_style`	str or none	none	WMTS: the service's STYLE
`map.providers.zoom_min`	int or none	none	The lowest zoom the provider serves
`map.providers.zoom_max`	int or none	none	The highest zoom the provider serves
`map.providers.profile`	str or none	none	A ready-made provider (providers/<profile>.yaml) to use
`map.providers.variables`	mapping	—	Values the profile's addresses are filled with
`map.providers.credential`	str or none	none	The provider's key, as env:VARIABLE — a name, never the key itself
`map.providers.credential_param`	str or none	none	WMTS: the query parameter the provider's key goes in
`map.providers.proxy`	`required` | `recommended` | `none`	`none`	Whether tiles are fetched through the Conduit (which caches them and keeps the key on the server) rather than by the browser
`map.providers.cache`	section or none	none	Keeping fetched tiles a while (online providers only).
`map.providers.cache.ttl_days`	int	required	How long a fetched tile is kept, in days
`map.providers.cache.prefetch_areas`	list of str	—	Areas whose tiles are fetched ahead of use
`map.providers.style`	str or none	none	The map style: bundled:osprey-dark, bundled:osprey-light, or the profile's own
`map.providers.attribution`	str	required	The credit shown on the map, as the licence asks
`reporting`	section	—	Dashboards for the business: report sync and Superset.
`reporting.sync`	bool	false	Run report-sync
`reporting.sync_interval_seconds`	int	`900`	How often each case is pulled into the mart, in seconds.

Option	Value	Default	What it does
`reporting.sync_memory`	str	`256m`	Report sync's memory limit.
`reporting.superset`	bool	false	Run Superset
`reporting.superset_memory`	str	`2g`	Superset's memory limit.
`monitoring`	section	—	Monitoring and alerts: whom a new hotlist's alerts reach, and who changes it.
`monitoring.hotlist_audience`	`only_me` | `team`	`only_me`	Whom a new hotlist's alerts reach: its owner alone (only_me), or also the owner's team, the people of the owner's organisational unit (team). Applies to hotlists made after it is set, never to an existing one.
`monitoring.hotlist_audience_editable`	bool	true	Whether a hotlist's owner may choose its audience, when making it or later. When false, every new hotlist takes hotlist_audience and a change is refused.
`connectors`	section	—	The Studio's SQL and API connectors: the private hosts an operator admits them to.
`connectors.private_hosts`	list of str	—	The private hosts a SQL or API connection may reach: each a host name in full (nomis-replica.client.internal) or a network inside 10.0.0.0/8, 172.16.0.0/12, 192.168.0.0/16, 100.64.0.0/10 or fc00::/7 (10.20.0.0/16) that a connection's host name resolves into. Everything else inside a network stays refused. Never admitted, whatever is listed: this machine, a cloud's metadata services (169.254.0.0/16, fd00:ec2::/32, 100.100.0.0/16), Docker's and the cluster's own names, and any address in the Conduit's own networks or the deployment's own services'. A host must still be on the egress allow-list.
`connectors.secrets`	list of str	—	The name of each SQL or API connection's secret (NOMIS_REPLICA for OSPREY_CONNECTION_SECRET_NOMIS_REPLICA in deployment.env). Only the Conduit is given a declared secret, every other service having it blanked, and a connection whose secret is not declared reads nothing.
`mail`	section or none	none	A mail server, for invitations and password resets by email.
`mail.host`	str	required	The mail server's name
`mail.port`	int	`587`	The mail server's port.
`mail.from_address`	str	required	The address invitations come from
`mail.starttls`	bool	true	Whether mail is sent over TLS (STARTTLS).
`mail.username`	str or none	none	A relay that takes mail without signing in. With one, the password comes from OSPREY_SMTP_PASSWORD at install.
`welcome`	section	—	The welcome page before sign-in: its About section and footer links.
`welcome.about`	bool	true	Off for an internal-only deployment.
`welcome.account_help`	str or none	none	Where people get help with their account.
`welcome.accessibility`	str or none	none	The organisation's accessibility statement.
`welcome.privacy`	str or none	none	The organisation's privacy notice.
`welcome.service_status`	str or none	none	A page saying whether the service is up.
`deployment`	section	—	Which deployment this is, on a machine that runs more than one.
`deployment.name`	str or none	none	Names this deployment's Compose project, its volumes and its rendered folder, so a second deployment on the same machine shares none of them.
`deployment.graph_port`	int or none	none	The port on this machine (127.0.0.1 only) the graph store's own tools reach it at. A deployment installed beside another with ospreyflow install --name is given one of its own, so the two share no port.

Option	Value	Default	What it does
`appearance`	section	—	How every page looks: the deployment's brand, and what its page title names.
`appearance.brand`	`ospreyflow` | `govuk`	`ospreyflow`	The GOV.UK look, for a service on a gov.uk domain only.
`appearance.service_name`	str or none	none	The service's name, in the page title.
`appearance.organisation`	str or none	none	The organisation in the GOV.UK footer and the page title.
`appearance.phase`	`alpha` | `beta` | `live` | `none`	`none`	The phase banner shows at alpha or beta.
`grading`	section	—	The scheme every drawn node and link is graded in (ADR-143 decision 11); changed only by `ospreyflow grading change`.
`grading.scheme`	str	`5x5x5`	The scheme drawn items are graded in: 5x5x5; 3x5x2, whose handling code (P or C) is part of the grade and never merged with the marking; or the path of a scheme file (.yaml, beside this file unless absolute) naming its own scheme and each part's grades.
`external`	section	—	What a cloud runs for the deployment instead of a container (Small).
`external.postgres`	section or none	none	A cloud's managed PostgreSQL; its password arrives at install.
`external.postgres.host`	str	required	The managed server's address
`external.postgres.port`	int	`5432`	Its port
`external.postgres.database`	str	`ospreyflow`	The deployment's database on it
`external.postgres.user`	str	`osprey`	The login, which needs CREATEROLE and CREATEDB there
`external.postgres.sslmode`	`require` | `verify-ca` | `verify-full`	`require`	A managed server is reached over TLS.
`external.object_store`	section or none	none	A cloud's S3, for every S3-protocol store (AWS).
`external.object_store.endpoint`	str	required	Host and port, no scheme: always HTTPS
`external.object_store.region`	str	required	The region the buckets live in
`external.object_store.credentials`	`instance` | `keys`	`instance`	The server's own cloud identity, no key anywhere; `keys` reads OSPREY_S3_ACCESS_KEY and OSPREY_S3_SECRET_KEY at apply.
`external.object_store.bucket_prefix`	str	`ospreyflow-`	Each bucket is <prefix><name>, as OpenTofu made them
`external.media`	section or none	none	Media on Azure Blob; its key arrives at install.
`external.media.blob_account`	str	required	The Blob storage account
`external.media.blob_container`	str	`media`	The container media is kept in
`external.valkey`	section or none	none	A cloud's managed Valkey or Redis (cluster only).
`external.valkey.host`	str	required	The managed cache's address
`external.valkey.port`	int	`6379`	Its port
`external.valkey.tls`	bool	true	Whether it is reached over TLS
`external.search`	section or none	none	A cloud's managed OpenSearch (cluster on AWS only).
`external.search.url`	str	required	The domain's HTTPS address
`resources`	section	—	Small on a server of your own: the stores sized to the server's memory (section 5a.2); and, on Lite or such a Small on Linux, the local engine on an NVIDIA GPU (section 5a.4).
`resources.memory_gib`	int or none	none	The memory the stores are sized to, in GiB (as Docker reports it). Default: none — the stores keep their fixed sizes.
`resources.graph_heap_gib`	int or none	none	Overrides the graph store's heap (-Xmx), in GiB; at most 31.
`resources.search_heap_gib`	float or none	none	Overrides OpenSearch's heap (-Xms and -Xmx), in GiB.

Option	Value	Default	What it does
`resources.postgres_shared_buffers_gib`	float or none	none	Overrides PostgreSQL's shared_buffers, in GiB.
`resources.gpu`	`none` | `nvidia`	`none`	The local engine runs on the CPU. nvidia: the ollama service reserves every NVIDIA GPU, and the extraction model is qwen2.5:14b-instruct unless models.extraction names one. The NVIDIA driver and Container Toolkit are the administrator's to install.