Supplementary code for the <u>Build a Large Language Model From Scratch</u> book by Sebastian Raschka Code repository: <a href="https://github.com/rasbt/LLMs-from-scratch">https://github.com/rasbt/LLMs-from-scratch</a> **Appendix A: Introduction to PyTorch (Part 2)** A.9 Optimizing training performance with GPUs A.9.1 PyTorch computations on GPU devices In [1]: import torch print(torch.\_\_version\_\_) 2.4.0+cu121 In [2]: | print(torch.cuda.is\_available()) True In [3]: tensor\_1 = torch.tensor([1., 2., 3.])  $tensor_2 = torch.tensor([4., 5., 6.])$ print(tensor\_1 + tensor\_2) tensor([5., 7., 9.]) In [4]: tensor\_1 = tensor\_1.to("cuda") tensor\_2 = tensor\_2.to("cuda") print(tensor\_1 + tensor\_2) tensor([5., 7., 9.], device='cuda:0') In [5]: tensor\_1 = tensor\_1.to("cpu") print(tensor\_1 + tensor\_2) Traceback (most recent call last) /tmp/ipykernel\_2321/2079609735.py in <cell line: 2>() 1 tensor\_1 = tensor\_1.to("cpu") ----> 2 print(tensor\_1 + tensor\_2) RuntimeError: Expected all tensors to be on the same device, but found at least two devices, cuda:0 and cpu! A.9.2 Single-GPU training In [6]: X\_train = torch.tensor([ [-1.2, 3.1],[-0.9, 2.9],[-0.5, 2.6],[2.3, -1.1],[2.7, -1.5]y\_train = torch.tensor([0, 0, 0, 1, 1]) X\_test = torch.tensor([ [-0.8, 2.8],[2.6, -1.6],y\_test = torch.tensor([0, 1]) In [7]: **from torch.utils.data import** Dataset class ToyDataset (Dataset): **def** \_\_init\_\_(self, X, y): self.features = Xself.labels = ydef \_\_getitem\_\_(self, index): one\_x = self.features[index] one\_y = self.labels[index] return one\_x, one\_y def \_\_len\_\_(self): return self.labels.shape[0] train\_ds = ToyDataset(X\_train, y\_train) test\_ds = ToyDataset(X\_test, y\_test) In [8]: from torch.utils.data import DataLoader torch.manual\_seed(123) train\_loader = DataLoader( dataset=train\_ds, batch\_size=2, shuffle=**True**, num\_workers=1, drop\_last=**True** test\_loader = DataLoader( dataset=test\_ds, batch\_size=2, shuffle=False, num\_workers=1 **Solution: Annotations Part 1 1.** Function Class  $f_{\theta}$ : The **function class**  $f_{\theta}$  refers to the neural network architecture that maps input data x to output logits. In this case, the function class is defined by the neural network model that consists of two hidden layers and an output layer. The network architecture is: 1. **Input layer**: The input data has num\\_inputs dimensions. 2. 1st hidden layer: A fully connected (linear) layer with 30 neurons and a ReLU activation function. 3. 2nd hidden layer: Another fully connected (linear) layer with 20 neurons and a ReLU activation function. 4. **Output layer**: A fully connected (linear) layer with num\\_outputs neurons, which outputs the logits for the final predictions. Mathematically, the function class  $f_{\theta}(x)$  can be represented as:  $f_{\theta}(x) = W_3 \cdot \text{ReLU}(W_2 \cdot \text{ReLU}(W_1 \cdot x + b_1) + b_2) + b_3$ where: •  $W_1, b_1$  are the weights and biases of the 1st hidden layer. ullet  $W_2,b_2$  are the weights and biases of the 2nd hidden layer. •  $W_3, b_3$  are the weights and biases of the output layer. • ReLU is the ReLU activation function applied element-wise after the first two linear layers. The function class describes how the input is transformed through the layers and activation functions to produce the output logits. 2. Parameter Space  $\theta$ : The parameter space  $\theta$  refers to the set of all learnable parameters (weights and biases) in the neural network. In this model,  $\theta$  includes: •  $W_1$  and  $b_1$ : Weights and biases of the 1st hidden layer (dimensions: [num\_inputs, 30] for weights and [30] for biases). •  $W_2$  and  $b_2$ : Weights and biases of the 2nd hidden layer (dimensions: [30, 20] for weights and [20] for biases). •  $W_3$  and  $b_3$ : Weights and biases of the output layer (dimensions: [20, num\_outputs] for weights and [num\_outputs] for biases). These parameters are learned during training by minimizing a loss function through optimization algorithms like stochastic gradient descent (SGD) or Adam. The parameter space  $\theta$  is the collection of all these weights and biases that define the transformations applied by the neural network to the input data. In [9]: class NeuralNetwork(torch.nn.Module): def \_\_init\_\_(self, num\_inputs, num\_outputs): super().\_\_init\_\_() self.layers = torch.nn.Sequential( # 1st hidden layer torch.nn.Linear(num\_inputs, 30), torch.nn.ReLU(), # 2nd hidden layer torch.nn.Linear(30, 20),

```
torch.nn.ReLU(),
           # output layer
           torch.nn.Linear(20, num_outputs),
   def forward(self, x):
       logits = self.layers(x)
       return logits
Solution Annotations: Part 2
1. Loss Function l:
```

#### loss = F.cross\_entropy(logits, labels) • Cross-entropy loss is used for classification tasks and measures the difference between the predicted class probabilities (after applying softmax) and the true class labels. It computes the negative log-likelihood of the true class based on the predicted probabilities.

• For a single data point  $(x_i,y_i)$ , the cross-entropy loss  $l(f_{\theta}(x_i),y_i)$  is given by:  $l(f_{\theta}(x_i),y_i) = -\log\Biggl(\frac{\exp(f_{\theta}(x_i)_{y_i})}{\sum_{k=1}^K \exp(f_{\theta}(x_i)_k)}\Biggr)$ 

The **loss function** used in the code is **cross-entropy loss**, which is applied to the predicted logits and the true labels:

•  $f_{\theta}(x_i)_k$  is the predicted logit for class k, •  $y_i$  is the true class label for input  $x_i$ , ullet K is the total number of classes (in this case, 2).

2. Empirical Risk L: The **empirical risk** L represents the average loss over the entire training set. It is the quantity the model is trying to minimize during training. In the case of mini-

batch training (as in this code), the empirical risk is computed as the average cross-entropy loss over the data points in the mini-batch.

This loss function is computed for each data point and averaged over the mini-batch during training.

## where $l(f_{\theta}(x_i), y_i)$ is the cross-entropy loss for each example $(x_i, y_i)$ .

In [10]: import torch.nn.functional as F

torch.manual\_seed(123)

for epoch in range(num\_epochs):

 $num\_epochs = 3$ 

distribution.

In the code, the empirical risk is minimized using stochastic gradient descent (SGD) as the optimizer: optimizer = torch.optim.SGD(model.parameters(), lr=0.5) This step updates the model parameters  $\theta$  to minimize the empirical risk.

 $L( heta) = rac{1}{n} \sum_{i=1}^n l(f_ heta(x_i), y_i)$ 

3. Probability Distribution  $p_{\theta}$  (Log-Likelihood View): In the log-likelihood view, the cross-entropy loss can be interpreted as minimizing the negative log-likelihood of the true class under a predicted probability

The logits output by the model  $f_{ heta}(x_i)$  are converted into class probabilities using the **softmax function**:

### $p_{ heta}(y_i|x_i) = rac{\exp(f_{ heta}(x_i)_{y_i})}{\sum_{k=1}^K \exp(f_{ heta}(x_i)_k)}$ where: • $f_{\theta}(x_i)_k$ is the logit for class k,

model = NeuralNetwork(num\_inputs=2, num\_outputs=2)

Mathematically, if there are n training examples, the empirical risk  $L(\theta)$  is:

•  $p_{\theta}(y_i|x_i)$  is the predicted probability for the true class  $y_i$ . The **log-likelihood** for a single data point is the log of the probability assigned to the correct class:  $\log(p_{ heta}(y_i|x_i)) = \log\Biggl(rac{\exp(f_{ heta}(x_i)_{y_i})}{\sum_{k=1}^K \exp(f_{ heta}(x_i)_k)}\Biggr)$ 

The negative log-likelihood is what the cross-entropy loss computes, and by minimizing this loss, the model maximizes the likelihood of the correct class under the predicted probability distribution. The loss function and the empirical risk are thus directly related to the likelihood function of the true labels given the model's predictions.

device = torch.device("cuda" if torch.cuda.is\_available() else "cpu") # NEW

model = model.to(device) # NEW optimizer = torch.optim.SGD(model.parameters(), lr=0.5)

```
model.train()
             for batch_idx, (features, labels) in enumerate(train_loader):
                 features, labels = features.to(device), labels.to(device) # NEW
                 logits = model(features)
                 loss = F.cross_entropy(logits, labels) # Loss function
                 optimizer.zero_grad()
                 loss.backward()
                 optimizer.step()
                 ### LOGGING
                 print(f"Epoch: {epoch+1:03d}/{num_epochs:03d}"
                       f" | Batch {batch idx:03d}/{len(train loader):03d}"
                       f" | Train/Val Loss: {loss:.2f}")
             model.eval()
             # Optional model evaluation
         Epoch: 001/003 | Batch 000/002 | Train/Val Loss: 0.75
         Epoch: 001/003 | Batch 001/002 | Train/Val Loss: 0.65
         Epoch: 002/003 | Batch 000/002 | Train/Val Loss: 0.44
         Epoch: 002/003 | Batch 001/002 | Train/Val Loss: 0.13
         Epoch: 003/003 | Batch 000/002 | Train/Val Loss: 0.03
         Epoch: 003/003 | Batch 001/002 | Train/Val Loss: 0.00
In [11]: def compute_accuracy(model, dataloader, device):
             model = model.eval()
             correct = 0.0
             total_examples = 0
             for idx, (features, labels) in enumerate(dataloader):
                 features, labels = features.to(device), labels.to(device) # New
                 with torch.no_grad():
                     logits = model(features)
                 predictions = torch.argmax(logits, dim=1)
                 compare = labels == predictions
                 correct += torch.sum(compare)
```

### Out[12]: 1.0 In [13]: compute\_accuracy(model, test\_loader, device=device) Out[13]: 1.0

A.9.3 Training with multiple GPUs

total\_examples += len(compare)

In [12]: compute\_accuracy(model, train\_loader, device=device)

return (correct / total\_examples).item()

# CPU

See DDP-script.py

